

AIX Version 6.1

*Performance Tools Guide and  
Reference*

**IBM**



AIX Version 6.1

*Performance Tools Guide and  
Reference*

**IBM**

**Note**

Before using this information and the product it supports, read the information in "Notices" on page 363.

This edition applies to AIX Version 6.1 and to all subsequent releases and modifications until otherwise indicated in new editions.

© **Copyright IBM Corporation 2002, 2018.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

## About this document . . . . . v

Highlighting . . . . .	v
Case-sensitivity in AIX . . . . .	v
ISO 9000. . . . .	v

## Performance Tools Guide and Reference 1

What's new in Performance Tools Guide and Reference . . . . .	2
CPU Utilization Reporting Tool (curt) . . . . .	2
Syntax for the curt Command . . . . .	2
Measurement and Sampling . . . . .	3
Examples of the curt command . . . . .	4
Simple performance lock analysis tool (splat) . . . . .	32
splat command syntax. . . . .	32
Measurement and sampling . . . . .	33
Examples of generated reports . . . . .	35
Hardware performance monitor APIs and tools . . . . .	50
Performance monitor accuracy . . . . .	51
Performance monitor context and state . . . . .	51
Performance monitoring agent . . . . .	52
POWERCOMPAT events . . . . .	53
Thread accumulation and thread group accumulation . . . . .	57
Security considerations . . . . .	57
The pmapi library . . . . .	58
The hpm library and associated tools. . . . .	70
Perfstat API programming . . . . .	80
API characteristics . . . . .	80
Global interfaces. . . . .	81
Component-Specific interfaces. . . . .	100
WPAR Interfaces . . . . .	185
RSET Interfaces. . . . .	195
Cached metrics interfaces . . . . .	200
Node interfaces. . . . .	203
Change history of the perfstat API . . . . .	212
Kernel tuning . . . . .	217
Migration and compatibility . . . . .	217
Tunables file directory . . . . .	218
Tunable parameters type . . . . .	219
Common syntax for tuning commands . . . . .	219

Tunable file-manipulation commands . . . . .	221
Initial setup . . . . .	224
Reboot tuning procedure . . . . .	224
Recovery Procedure . . . . .	225
Kernel tuning using the SMIT interface. . . . .	225
Kernel Tuning using the Performance Plug-In for Web-based System Manager . . . . .	230
The procmon tool . . . . .	241
Overview of the procmon tool. . . . .	241
Components of the procmon tool. . . . .	242
Filtering processes. . . . .	244
Performing AIX commands on processes . . . . .	244
Profiling tools . . . . .	245
The timing commands . . . . .	245
The prof command . . . . .	245
The gprof command . . . . .	247
The tprof command . . . . .	249
X-Windows Performance Profiler (Xprofiler) . . . . .	256
The svmon command . . . . .	314
Security . . . . .	315
The svmon configuration file . . . . .	315
Summary report metrics. . . . .	316
Report formatting options . . . . .	316
Segment details and -O options . . . . .	318
Additional -O options . . . . .	322
Reports details . . . . .	326
Remote Statistics Interface API Overview . . . . .	348
Remote Statistics Interface list of subroutines . . . . .	349
RSI Interface Concepts and Terms . . . . .	350
A Simple Data-Consumer Program . . . . .	354
Expanding the data-consumer program. . . . .	358
Inviting data suppliers . . . . .	359
A Full-Screen, character-based monitor . . . . .	360
List of RSI Error Codes . . . . .	361

## Notices . . . . . 363

Privacy policy considerations . . . . .	365
Trademarks . . . . .	365

## Index . . . . . 367



---

## About this document

The Performance Tools Guide and Reference provides experienced system administrators, application programmers, service representatives, system engineers, end users, and system programmers with complete, detailed information about the various performance tools that are available for monitoring and tuning AIX® systems and applications running on those systems.

The information contained in this document pertains to systems running AIX 6.1, or later. Any content that is applicable to earlier releases will be noted as such.

---

## Highlighting

The following highlighting conventions are used in this document:

<b>Bold</b>	Identifies commands, subroutines, keywords, files, structures, directories, and other items whose names are predefined by the system. Also identifies graphical objects such as buttons, labels, and icons that the user selects.
<i>Italics</i>	Identifies parameters whose actual names or values are to be supplied by the user.
Monospace	Identifies examples of specific data values, examples of text similar to what you might see displayed, examples of portions of program code similar to what you might write as a programmer, messages from the system, or information you should actually type.

---

## Case-sensitivity in AIX

Everything in the AIX operating system is case-sensitive, which means that it distinguishes between uppercase and lowercase letters. For example, you can use the **ls** command to list files. If you type **LS**, the system responds that the command is not found. Likewise, **FILEA**, **FiLea**, and **filea** are three distinct file names, even if they reside in the same directory. To avoid causing undesirable actions to be performed, always ensure that you use the correct case.

---

## ISO 9000

ISO 9000 registered quality systems were used in the development and manufacturing of this product.



---

## Performance Tools Guide and Reference

The performance of a computer system is based on human expectations and the ability of the computer system to fulfill these expectations. The objective for performance tuning is to make those expectations and their fulfillment match.

The path to achieving this objective is a balance between appropriate expectations and optimizing the available system resources. The performance-tuning process demands great skill, knowledge, and experience, and cannot be performed by only analyzing statistics, graphs, and figures. If results are to be achieved, the human aspect of perceived performance must not be neglected. Performance tuning also takes into consideration problem-determination aspects as well as pure performance issues.

Expectations can often be classified as either of the following:

Item	Descriptor
Throughput expectations	A measure of the amount of work performed over a period of time
Response time expectations	The elapsed time between when a request is submitted and when the response from that request is returned

The performance-tuning process can be initiated for a number of reasons:

- To achieve optimal performance in a newly installed system
- To resolve performance problems resulting from the design (sizing) phase
- To resolve performance problems occurring in the run-time (production) phase

Performance tuning on a newly installed system usually involves setting some base parameters for the operating system and applications. Throughout this book, there are sections that describe the characteristics of different system resources and provide guidelines regarding their base tuning parameters, if applicable.

Limitations originating from the sizing phase will either limit the possibility of tuning, or incur greater cost to overcome them. The system might not meet the original performance expectations because of unrealistic expectations, physical problems in the computer environment, or human error in the design or implementation of the system. In the worst case, adding or replacing hardware might be necessary. Be particularly careful when sizing a system to permit enough capacity for unexpected system loads. In other words, do not design the system to be 100 percent busy from the start of the project.

When a system in a productive environment still meets the performance expectations for which it was initially designed, but the demands and needs of the utilizing organization have outgrown the system's basic capacity, performance tuning is performed to delay or even to avoid the cost of adding or replacing hardware.

Many performance-related issues can be traced back to operations performed by a person with limited experience and knowledge who unintentionally restricted some vital logical or physical resource of the system.

**Note:** The metrics reported by any statistics tool such as `lparstat`, `vmstat`, `iostat`, `mpstat` and so on including the applications that are based on `Perfstat` API or `SPMI` API varies to a certain extent at any point of time. If the command is run multiple times for an instance, the values may not be similar for that instance.

---

## What's new in Performance Tools Guide and Reference

Read about new or significantly changed information for the Performance Tools Guide and Reference topic collection.

### How to see what's new or changed

In this PDF file, you might see revision bars (|) in the left margin that identify new and changed information.

### October 2016

The following information is a summary of the updates made to this topic collection:

- Updated the Node interfaces topic with the **perfstat\_cluster\_disk** interface example.
- Added information about the **perfstat\_ssp\_ext** component-specific interface.

---

## CPU Utilization Reporting Tool (curt)

The CPU Utilization Reporting Tool (**curt**) command converts an AIX trace file into a number of statistics related to CPU utilization and either process, thread or pthread activity. These statistics ease the tracking of specific application activity.

The **curt** command works with both uniprocessor and multiprocessor AIX Version 4 and AIX Version 5 traces.

### Syntax for the curt Command

Review the syntax, flags, and parameters for the **curt** command.

The syntax for the **curt** command is as follows:

```
curt -i inputfile [-o outputfile] [-n gensymsfile] [-m trcnmfile] [-a pidnamefile] [-f timestamp] [-l timestamp] [-r PURR][-ehpstP]
```

### Flags

Item	Descriptor
<b>-i</b> <i>inputfile</i>	Specifies the input AIX trace file to be analyzed.
<b>-o</b> <i>outputfile</i>	Specifies an output file (default is <b>stdout</b> ).
<b>-n</b> <i>gensymsfile</i>	Specifies a names file produced by <b>gensyms</b> .
<b>-m</b> <i>trcnmfile</i>	Specifies a names file produced by <b>trcnm</b> .
<b>-a</b> <i>pidnamefile</i>	Specifies a PID-to-process name mapping file.
<b>-f</b> <i>timestamp</i>	Starts processing trace at <i>timestamp</i> seconds.
<b>-l</b> <i>timestamp</i>	Stops processing trace at <i>timestamp</i> seconds.
<b>-r</b> <i>PURR</i>	Uses the PURR register to calculate CPU times.
<b>-e</b>	Outputs elapsed time information for system calls.
<b>-h</b>	Displays usage text (this information).
<b>-p</b>	Outputs detailed process information.
<b>-s</b>	Outputs information about errors returned by system calls.
<b>-t</b>	Outputs detailed thread information.
<b>-P</b>	Outputs detailed pthread information.

### Parameters

<b>Item</b>	<b>Descriptor</b>
<i>gensymsfile</i>	The names file as produced by the <b>gensyms</b> command.
<i>inputfile</i>	The AIX trace file to be processed by the <b>curt</b> command.
<i>outputfile</i>	The name of the output file created by the <b>curt</b> command.
<i>pidnamefile</i>	If the trace process name table is not accurate, or if more descriptive names are desired, use the <b>-a</b> flag to specify a PID to process name mapping file. This is a file with lines consisting of a process ID (in decimal) followed by a space, then an ASCII string to use as the name for that process.
<i>timestamp</i>	The time in seconds at which to start and stop the trace file processing.
<i>trcnmfile</i>	The names file as produced by the <b>trcnm</b> command.
<i>PURR</i>	The name of the register that is used to calculate CPU times.

## Measurement and Sampling

A *raw*, or unformatted, system trace is read by the **curt** command to produce CPU utilization summaries. The summary information is useful for determining which application, system call, Network File System (NFS) operation, hypervisor call, pthread call, or interrupt handler is using most of the CPU time and is a candidate for optimization to improve system performance.

The following table lists the minimum trace hooks required for the **curt** command. Using only these trace hooks will limit the size of the trace file. However, other events on the system might not be captured in this case. This is significant if you intend to analyze the trace in more detail.

Hook ID	Event Name	Event Explanation
100	HKWD_KERN_FLIH	Occurrence of a first level interrupt, such as an I/O interrupt, a data access page fault, or a timer interrupt (scheduler).
101	HKWD_KERN_SVC	A thread has issued a system call.
102	HKWD_KERN_SLIH	Occurrence of a second level interrupt, that is, first level I/O interrupts are being passed on to the second level interrupt handler which then is working directly with the device driver.
103	HKWD_KERN_SLIHRET	Return from a second level interrupt to the caller (usually a first level interrupt handler).
104	HKWD_KERN_SYSCRET	Return from a system call to the caller (usually a thread).
106	HKWD_KERN_DISPATCH	A thread has been dispatched from the run queue to a CPU.
10C	HKWD_KERN_IDLE	The idle process has been dispatched.
119	HKWD_KERN_PIDSIG	A signal has been sent to a process.
134	HKWD_SYSC_EXECVE	An exec supervisor call (SVC) has been issued by a (forked) process.
135	HKWD_SYSC_EXIT	An exit supervisor call (SVC) has been issued by a process.
139	HKWD_SYSC_FORK	A fork SVC has been issued by a process.
200	HKWD_KERN_RESUME	A dispatched thread is being resumed on the CPU.
210	HKWD_KERN_INITP	A kernel process has been created.
215	HKWD_NFS_DISPATCH	An entry or exit NFS V2 and V3 operation has been issued by a process.
38F	HKWD_DR	A processor has been added/removed.
419	HKWD_CPU_PREEMPT	A processor has been preempted.
465	HKWD_SYSC_CRTHREAD	A <b>thread_create</b> SVC has been issued by a process.
47F	HKWD_KERN_PHANTOM_EXTINT	A phantom interrupt has occurred.
488	HKWD_RFS4_VOPS	An entry or exit NFS V4 client operation (VOPS) has been issued by a process.
489	HKWD_RFS4_VFSOPS	An entry or exit NFS V4 client operation (VFSOPS) has been issued by a process.
48A	HKWD_RFS4_MISCOPS	An entry or exit NFS V4 client operation (MISCOPS) has been issued by a process.
48D	HKWD_RFS4	An entry or exit NFS V4 server operation has been issued by a process.

Hook ID	Event Name	Event Explanation
492	HKWD_KERN_HCALL	A hypervisor call has been issued by the kernel.
605	HKWD_PTHREAD_VPSLEEP	A <b>pthread vp_sleep</b> operation has been done by a pthread.
609	HKWD_PTHREAD_GENERAL	A general pthread operation has been done by a pthread.

Trace hooks 119 and 135 are used to report on the time spent in the **exit** system call. Trace hooks 134, 139, 210, and 465 are used to keep track of TIDs, PIDs and process names.

Trace hook 492 is used to report on the time spent in the hypervisor.

Trace hooks 605 and 609 are used to report on the time spent in the pthreads library.

To get the PTHREAD hooks in the trace, you must execute your pthread application using the instrumented **libpthreads.a** library.

## Examples of the **curt** command

Preparing the **curt** command input is a three-stage process.

Trace and name files are generated using the following process:

1. **Build the raw trace.** On a 4-way machine, this will create files as listed in the example code below. One raw trace file per CPU is produced. The files are named **trace.raw-0**, **trace.raw-1**, and so forth for each CPU. An additional file named **trace.raw** is also generated. This is a master file that has information that ties together the other CPU-specific traces.
  - Note:** If you want pthread information in the **curt** report, you must add the instrumented **libpthreads** directory to the library path, **LIBPATH**, when you build the trace. Otherwise, the `export LIBPATH` statement in the example below is unnecessary.
2. **Merge the trace files.** To merge the individual CPU raw trace files to form one trace file, run the **trcpt** command. If you are tracing a uniprocessor machine, this step is not necessary.
3. **Create the supporting **gensymsfile** and **trcnmfile** files by running the **gensyms** and **trcnm** commands.** Neither the **gensymsfile** nor the **trcnmfile** file are necessary for the **curt** command to run. However, if you provide one or both of these files, or if you use the **trace** command with the **-n** option, the **curt** command outputs names for system calls and interrupt handlers instead of just addresses. The **gensyms** command output includes more information than the **trcnm** command output, and so, while the **trcnmfile** file will contain most of the important address to name mapping data, a **gensymsfile** file will enable the **curt** command to output more names, and is the preferred address to name mapping data collection command.

The following is an example of how to generate input files for the **curt** command:

```
# HOOKS="100,101,102,103,104,106,10C,119,134,135,139,200,210,215,38F,419,465,47F,488,489,48A,
      48D,492,605,609"
# SIZE="1000000"
# export HOOKS SIZE
# trace -n -C all -d -j $HOOKS -L $SIZE -T $SIZE -afo trace.raw
# export LIBPATH=/usr/ccs/lib/perf:$LIBPATH
# trcon ; pthread.app ; trcstop
# unset HOOKS SIZE
# ls trace.raw*
trace.raw  trace.raw-0  trace.raw-1  trace.raw-2  trace.raw-3
# trcpt -C all -r trace.raw > trace.r
# rm trace.raw*
# ls trace*
trace.r
# gensyms > gensyms.out
# trcnm > trace.nm
```

## Overview of information generated by the `curl` command

Review the following information to learn the different information that is generated by the `curl` command, and how you generate specialized reports.

The following is an overview of the content of the report that the `curl` command generates:

- A report header, including the trace file name, the trace size, and the date and time the trace was taken. The header also includes the command that was used when the trace was run. If the PURR register was used to calculate CPU times, this information is also included in the report header.
- For each CPU (and a summary of all the CPUs), processing time expressed in milliseconds and as a percentage (idle and non-idle percentages are included) for various CPU usage categories.
- For each CPU (and a summary of all the CPUs), processing time expressed in milliseconds and as a percentage for CPU usage in application mode for various application usage categories.
- Average thread affinity across all CPUs and for each individual CPU.
- For each CPU (and for all the CPUs), the Physical CPU time spent and the percentage of total time this represents.
- Average physical CPU affinity across all CPUs and for each individual CPU.
- The physical CPU dispatch histogram of each CPU.
- The number of preemptions, and the number of `H_CEDE` and `H_CONFER` hypervisor calls for each individual CPU.
- The total number of idle and non-idle process dispatches for each individual CPU.
- Average pthread affinity across all CPUs and for each individual CPU.
- The total number of idle and non-idle pthread dispatches for each individual CPU.
- Information on the amount of CPU time spent in application and system call (`syscall`) mode expressed in milliseconds and as a percentage by thread, process, and process type. Also included are the number of threads per process and per process type.
- Information on the amount of CPU time spent executing each kernel process, including the idle process, expressed in milliseconds and as a percentage of the total CPU time.
- Information on the amount of CPU time spent executing calls to `libpthread`, expressed in milliseconds and as percentages of the total time and the total application time.
- Information on completed system calls that includes the name and address of the system call, the number of times the system call was executed, and the total CPU time expressed in milliseconds and as a percentage with average, minimum, and maximum time the system call was running.
- Information on pending system calls, that is, system calls for which the system call return has not occurred at the end of the trace. The information includes the name and address of the system call, the thread or process which made the system call, and the accumulated CPU time the system call was running expressed in milliseconds.
- Information on completed hypervisor calls that includes the name and address of the hypervisor call, the number of times the hypervisor call was executed, and the total CPU time expressed in milliseconds and as a percentage with average, minimum, and maximum time the hypervisor call was running.
- Information on pending hypervisor calls, which are hypervisor calls that were not completed by the end of the trace. The information includes the name and address of the hypervisor call, the thread or process which made the hypervisor call, and the accumulated CPU time the hypervisor call was running, expressed in milliseconds.
- Information on completed pthread calls that includes the name of the pthread call routine, the number of times the pthread call was executed, and the total CPU time expressed in milliseconds and the average, minimum, and maximum time the pthread call was running.
- Information on pending pthread calls, that is, pthread calls for which the pthread call return has not occurred at the end of the trace. The information includes the name of the pthread call, the process, the thread and the pthread which made the pthread call, and the accumulated CPU time the pthread call was running expressed in milliseconds.

- Information on completed NFS operations that includes the name of the NFS operation, the number of times the NFS operation was executed, and the total CPU time, expressed in milliseconds, and as a percentage with average, minimum, and maximum time the NFS operation call was running.
- Information on pending NFS operations, where the NFS operations did not complete before the end of the trace. The information includes the sequence number for NFS V2/V3, or opcode for NFS V4, the thread or process which made the NFS operation, and the accumulated CPU time that the NFS operation was running, expressed in milliseconds.
- Information on the first level interrupt handlers (FLIHs) that includes the type of interrupt, the number of times the interrupt occurred, and the total CPU time spent handling the interrupt with average, minimum, and maximum time. This information is given for all CPUs and for each individual CPU. If there are any pending FLIHs (FLIHs for which the resume has not occurred at the end of the trace), for each CPU the accumulated time and the pending FLIH type is reported.
- Information on the second level interrupt handlers (SLIHs), which includes the interrupt handler name and address, the number of times the interrupt handler was called, and the total CPU time spent handling the interrupt with average, minimum, and maximum time. This information is given for all CPUs and for each individual CPU. If there are any pending SLIHs (SLIHs for which the return has not occurred at the end of the trace), the accumulated time and the pending SLIH name and address is reported for each CPU.

To create additional, specialized reports, run the **curt** command using the following flags:

Item	Descriptor
-e	Produces reports containing statistics and additional information on the System Calls Summary Report, Pending System Calls Summary Report, Hypervisor Calls Summary Report, Pending Hypervisor Calls Summary Report, System NFS Calls Summary Report, Pending NFS Calls Summary, Pthread Calls Summary, and the Pending Pthread Calls Summary. The additional information pertains to the total, average, maximum, and minimum elapsed times that a system call was running.
-s	Produces a report containing a list of errors returned by system calls.
-t	Produces a report containing a detailed report on thread status that includes the amount of CPU time the thread was in application and system call mode, what system calls the thread made, processor affinity, the number of times the thread was dispatched, and to which CPU(s) it was dispatched. The report also includes dispatch wait time and details of interrupts.
-p	Produces a report containing a detailed report on process status that includes the amount of CPU time the process was in application and system call mode, application time details, threads that were in the process, pthreads that were in the process, pthread calls that the process made and system calls that the process made.
-P	Produces a report containing a detailed report on pthread status that includes the amount of CPU time the pthread was in application and system call mode, system calls made by the pthread, pthread calls made by the pthread, processor affinity, the number of times the pthread was dispatched and to which CPU(s) it was dispatched, thread affinity, and the number of times the pthread was dispatched and to which kernel thread(s) it was dispatched. The report also includes dispatch wait time and details of interrupts.

## Default report generated by the curt command

The **curt** command output always includes this default report in its output, even if one of the flags described in the previous section is used.

This section explains the default report created by the **curt** command, as follows:

```
# curt -i trace.r -n gensyms.out -o curt.out
```

### General information:

The general information displays the time and date when the report was generated, and is followed by the syntax of the **curt** command line that was used to produce the report.

This section also contains some information about the AIX **trace** file that was processed by the **curt** command. This information consists of the **trace** file's name, size, and its creation date. The command used to invoke the AIX trace facility and gather the trace file is displayed at the end of the report.

The following is a sample of the general information section:

```
Run on Wed Apr 26 10:51:33 2XXX
Command line was:
curt -i trace.raw -n gensyms.out -o curt.out
----
AIX trace file name = trace.raw
AIX trace file size = 787848
Wed Apr 26 10:50:11 2XXX
System: AIX 5.3 Node: bu Machine: 00CFEDAD4C00
AIX trace file created = Wed Apr 26 10:50:11 2XXX

Command used to gather AIX trace was:
  trace -n -C all -d -j 100,101,102,103,104,106,10C,134,139,200,215,419,465,47F,488,489,48A,48D,492,605,609
  -L 1000000 -T 1000000 -afo trace.raw
```

### System summary:

The system summary information produced by the **curt** command describes the time spent by the whole system (all CPUs) in various execution modes.

The following is a sample of the System summary:

System Summary			
processing total time (msec)	percent total time (incl. idle)	percent busy time (excl. idle)	processing category
4998.65	45.94	75.21	APPLICATION
591.59	5.44	8.90	SYSCALL
110.40	1.02	1.66	HCALL
48.33	0.44	0.73	KPROC (excluding IDLE and NFS)
352.23	3.24	5.30	NFS
486.19	4.47	7.32	FLIH
49.10	0.45	0.74	SLIH
8.83	0.08	0.13	DISPATCH (all procs. incl. IDLE)
1.04	0.01	0.02	IDLE DISPATCH (only IDLE proc.)
-----	-----	-----	
6646.36	61.08	100.00	CPU(s) busy time
4234.76	38.92		IDLE
-----	-----		
10881.12			TOTAL

Avg. Thread Affinity = 0.99

Total Physical CPU time (msec) = 20417.45  
Physical CPU percentage = 100.00%

The System Summary has the following fields:

Item	Descriptor
<b>processing total time</b>	Total time in milliseconds for the corresponding processing category.
<b>percent total time</b>	Time from the first column as a percentage of the sum of total trace elapsed time for all processors. This includes whatever amount of time each processor spent running the IDLE process.
<b>percent busy time</b>	Time from the first column as a percentage of the sum of total trace elapsed time for all processors without including the time each processor spent executing the IDLE process.
<b>Avg. Thread Affinity</b>	Probability that a thread was dispatched to the same processor on which it last executed.
<b>Total Physical CPU time</b>	The real time that the virtual processor was running and not preempted.
<b>Physical CPU percentage</b>	Gives the Physical CPU Time as a percentage of total time.

The possible execution modes or processing categories are interpreted as follows:

Item	Descriptor
APPLICATION	The sum of times spent by all processors in User (that is, non-privileged) mode.
SYSCALL	The sum of times spent by all processors doing System Calls. This is the portion of time that a processor spends executing in the kernel code providing services directly requested by a user process.
HCALL	The sum of times spent by all processors doing Hypervisor Calls. This is the portion of time that a processor spends executing in the hypervisor code providing services directly requested by the kernel.
KPROC	The sum of times spent by all processors executing kernel processes other than IDLE and NFS processes. This is the portion of time that a processor spends executing specially created dispatchable processes that only execute kernel code.
NFS	The sum of times spent by all processors executing NFS operations. This is the portion of time that a processor spends executing in the kernel code providing NFS services directly requested by a kernel process.
FLIH	The sum of times spent by all processors executing FLIHs.
SLIH	The sum of times spent by all processors executing SLIHs.
DISPATCH	The sum of times spent by all processors executing the AIX dispatch code. This sum includes the time spent dispatching all threads (that is, it includes dispatches of the IDLE process).
IDLE DISPATCH	The sum of times spent by all processors executing the AIX dispatch code where the process being dispatched was the IDLE process. Because the DISPATCH category includes the IDLE DISPATCH category's time, the IDLE DISPATCH category's time is not separately added to calculate either CPU(s) busy time or TOTAL (see below).
CPU(s) busy time	The sum of times spent by all processors executing in APPLICATION, SYSCALL, KPROC, FLIH, SLIH, and DISPATCH modes.
IDLE	The sum of times spent by all processors executing the IDLE process.
TOTAL	The sum of CPU(s) busy time and IDLE.

The System Summary example indicates that the CPU is spending most of its time in application mode. There is still 4234.76 ms of IDLE time so there is enough CPU to run applications. If there is insufficient CPU power, do not expect to see any IDLE time. The Avg. Thread Affinity value is 0.99 showing good processor affinity; that is, threads returning to the same processor when they are ready to be run again.

### System application summary:

The system application summary information produced by the **curt** command describes the time spent by the system as a whole (all CPUs) in various execution modes.

The following is a sample of the System Application Summary:

```

                System Application Summary
                -----
processing      percent      percent
total time     total time   application
(msec)         (incl. idle)   time    processing category
=====
      3.95         0.42         0.07    PTHREAD
      4.69         0.49         0.09    PDISPATCH
      0.13         0.01         0.00    PIDLE
     5356.99       563.18        99.84    OTHER
-----
     5365.77       564.11       100.00  APPLICATION

```

Avg. Pthread Affinity = 0.84

The System Application Summary has the following fields:

Item	Descriptor
processing total time	Total time in milliseconds for the corresponding processing category.
percent total time	Time from the first column as a percentage of the sum of total trace elapsed time for all processors. This includes whatever amount of time each processor spent running the IDLE process.
percent application time	Time from the first column as a percentage of the sum of total trace elapsed application time for all processors
Avg. Pthread Affinity	Probability that a pthread was dispatched on the same kernel thread on which it last executed.

The possible execution modes or processing categories are interpreted as follows:

Item	Descriptor
PTHREAD	The sum of times spent by all pthreads on all processors in traced pthread library calls.
PDISPATCH	The sum of times spent by all pthreads on all processors executing the libpthreads dispatch code.
PIDLE	The sum of times spent by all kernel threads on all processors executing the <b>libpthreads vp_sleep</b> code.
OTHER	The sum of times spent by all pthreads on all processors in non-traced user mode.
APPLICATION	The sum of times spent by all processors in User (that is, non-privileged) mode.

### Processor summary and processor application summary:

This part of the **curl** command output is displayed by a processor-by-processor basis.

The same description that was given for the system summary and system application summary applies here, except that this report covers each processor rather than the whole system.

Below is a sample of this output:

```

Processor Summary processor number 0
-----
processing    percent    percent
total time    total time  busy time
(msec) (incl. idle) (excl. idle) processing category
-----
45.07         0.88       5.16 APPLICATION
591.39        11.58      67.71 SYSCALL
0.00          0.00       0.00 HCALL
47.83         0.94       5.48 KPROC (excluding IDLE and NFS)
0.00          0.00       0.00 NFS
173.78        3.40       19.90 FLIH
9.27          0.18       1.06 SLIH
6.07          0.12       0.70 DISPATCH (all procs. incl. IDLE)
1.04          0.02       0.12 IDLE DISPATCH (only IDLE proc.)
-----
873.42        17.10      100.00 CPU(s) busy time
4232.92       82.90
-----
5106.34                                TOTAL

```

Avg. Thread Affinity = 0.98

Total number of process dispatches = 1620

Total number of idle dispatches = 782

Total Physical CPU time (msec) = 3246.25

Physical CPU percentage = 63.57%

Physical processor affinity = 0.50

Dispatch Histogram for processor (PHYSICAL CPUid : times\_dispatched).

```

PROC 0 : 15
PROC 24 : 15

```

Total number of preemptions = 30  
 Total number of H\_CEDE = 6 with preemption = 3  
 Total number of H\_CONFER = 3 with preemption = 2

Processor Application Summary processor 0

```

-----
processing      percent      percent
total time     total time  application
(msec) (incl. idle)  time  processing category
=====
1.66           0.04         0.06  PTHREAD
2.61           0.05         0.10  PDISPATCH
0.00           0.00         0.00  PIDLE
2685.12        56.67        99.84  OTHER
-----
2689.39        56.76        100.00 APPLICATION
  
```

Avg. Pthread Affinity = 0.78

Total number of pthread dispatches = 104  
 Total number of pthread idle dispatches = 0

Processor Summary processor number 1

```

-----
processing      percent      percent
total time     total time  busy time
(msec) (incl. idle) (excl. idle) processing category
=====
4985.81        97.70        97.70  APPLICATION
0.09           0.00         0.00  SYSCALL
0.00           0.00         0.00  HCALL
0.00           0.00         0.00  KPROC (excluding IDLE and NFS)
0.00           0.00         0.00  NFS
103.86         2.04         2.04  FLIH
12.54          0.25         0.25  SLIH
0.97           0.02         0.02  DISPATCH (all procs. incl. IDLE)
0.00           0.00         0.00  IDLE DISPATCH (only IDLE proc.)
-----
5103.26        100.00       100.00 CPU(s) busy time
0.00           0.00         IDLE
-----
5103.26        TOTAL
  
```

Avg. Thread Affinity = 0.99

Total number of process dispatches = 516  
 Total number of idle dispatches = 0

Total Physical CPU time (msec) = 5103.26  
 Physical CPU percentage = 100.00%  
 Physical processor affinity = 1.00  
 Dispatch Histogram for processor (PHYSICAL CPUid : times\_dispatched).  
 Total number of preemptions = 0  
 Total number of H\_CEDE = 0 with preemption = 0  
 Total number of H\_CONFER = 0 with preemption = 0

Processor Application Summary processor 1

```

-----
processing      percent      percent
total time     total time  application
(msec) (incl. idle)  time  processing category
=====
2.29           0.05         0.09  PTHREAD
2.09           0.04         0.08  PDISPATCH
0.13           0.00         0.00  PIDLE
  
```

2671.86	56.40	99.83	OTHER
-----	-----	-----	
2676.38	56.49	100.00	APPLICATION

Avg. Pthread Affinity = 0.83

Total number of pthread dispatches = 91  
 Total number of pthread idle dispatches = 5

The following terms are referred to in the example above:

**Total number of process dispatches**

The number of times AIX dispatched any non-IDLE process on the processor.

**Total number of idle dispatches**

The number of IDLE process dispatches.

**Total number of pthread dispatches**

The number of times the libpthreads dispatcher was executed on the processor.

**Total number of pthread idle dispatches**

The number of `vp_sleep` calls.

**Application summary by thread ID (Tid):**

The application summary, by Tid, displays an output of all the threads that were running on the system during the time of trace collection and their CPU consumption. The thread that consumed the most CPU time during the time of the trace collection is displayed at the top of the output.

```

Application Summary (by Tid)
-----
-- processing total (msec) -- -- percent of total processing time --
combined application syscall combined application syscall name (Pid Tid)
-----
4986.2355 4986.2355 0.0000 24.4214 24.4214 0.0000 cpu(18418 32437)
4985.8051 4985.8051 0.0000 24.4193 24.4193 0.0000 cpu(19128 33557)
4982.0331 4982.0331 0.0000 24.4009 24.4009 0.0000 cpu(18894 28671)
83.8436 2.5062 81.3374 0.4106 0.0123 0.3984 disp+work(20390 28397)
72.5809 2.7269 69.8540 0.3555 0.0134 0.3421 disp+work(18584 32777)
69.8023 2.5351 67.2672 0.3419 0.0124 0.3295 disp+work(19916 33033)
63.6399 2.5032 61.1368 0.3117 0.0123 0.2994 disp+work(17580 30199)
63.5906 2.2187 61.3719 0.3115 0.0109 0.3006 disp+work(20154 34321)
62.1134 3.3125 58.8009 0.3042 0.0162 0.2880 disp+work(21424 31493)
60.0789 2.0590 58.0199 0.2943 0.0101 0.2842 disp+work(21992 32539)

```

...(lines omitted)...

The output is divided into two main sections:

- The total processing time of the thread in milliseconds (processing total (msec))
- The CPU time that the thread has consumed, expressed as a percentage of the total CPU time (percent of total processing time)

The Application Summary (by Tid) has the following fields:

Item	Descriptor
name (Pid Tid)	The name of the process associated with the thread, its process id, and its thread id.

The **processing total (msec)** displays the following values:

Item	Descriptor
combined	The total amount of CPU time, expressed in milliseconds, that the thread was running in either application mode or system call mode.
application	The amount of CPU time, expressed in milliseconds, that the thread spent in application mode.
syscall	The amount of CPU time, expressed in milliseconds, that the thread spent in system call mode.

The **percent of total processing time** displays the following values:

Item	Descriptor
combined	The amount of CPU time that the thread was running, expressed as percentage of the total processing time.
application	The amount of CPU time that the thread the thread spent in application mode, expressed as percentage of the total processing time.
syscall	The amount of CPU time that the thread spent in system call mode, expressed as percentage of the total processing time.

In the example above, we can investigate why the system is spending so much time in application mode by looking at the Application Summary (by Tid), where we can see the top three processes of the report are named **cpu**, a test program that uses a great deal of CPU time. The report shows again that the CPU spent most of its time in application mode running the **cpu** process. Therefore the **cpu** process is a candidate to be optimized to improve system performance.

#### Application summary by process ID (Pid):

The application summary, by Pid, has the same content as the application summary, by Tid, except that the threads that belong to each process are consolidated and the process that consumed the most CPU time during the monitoring period is at the beginning of the list.

The name (PID) (Thread Count) column shows the process name, its process ID, and the number of threads that belong to this process and that have been accumulated for this line of data.

```

Application Summary (by Pid)
-----
-- processing total (msec) --      -- percent of total processing time --
combined  application  syscall  combined  application  syscall  name (Pid)(Thread Count)
=====  =====  =====  =====  =====  =====  =====
4986.2355  4986.2355  0.0000  24.4214   24.4214   0.0000  cpu(18418)(1)
4985.8051  4985.8051  0.0000  24.4193   24.4193   0.0000  cpu(19128)(1)
4982.0331  4982.0331  0.0000  24.4009   24.4009   0.0000  cpu(18894)(1)
 83.8436   2.5062  81.3374   0.4106     0.0123   0.3984  disp+work(20390)(1)
 72.5809   2.7269  69.8540   0.3555     0.0134   0.3421  disp+work(18584)(1)
 69.8023   2.5351  67.2672   0.3419     0.0124   0.3295  disp+work(19916)(1)
 63.6399   2.5032  61.1368   0.3117     0.0123   0.2994  disp+work(17580)(1)
 63.5906   2.2187  61.3719   0.3115     0.0109   0.3006  disp+work(20154)(1)
 62.1134   3.3125  58.8009   0.3042     0.0162   0.2880  disp+work(21424)(1)
 60.0789   2.0590  58.0199   0.2943     0.0101   0.2842  disp+work(21992)(1)

...(lines omitted)...

```

#### Application summary by process type:

The application summary by process type consolidates all processes of the same name and sorts them in descending order of combined processing time.

The name (thread count) column shows the name of the process, and the number of threads that belong to this process name (type) and were running on the system during the monitoring period.

Application Summary (by process type)

```

-----
-- processing total (msec) --      -- percent of total processing time --
combined  application  syscall  combined  application  syscall  name (thread count)
-----  -----  -----  -----  -----  -----  -----
14954.0738  14954.0738  0.0000  73.2416   73.2416  0.0000  cpu(3)
 573.9466   21.2609  552.6857  2.8111    0.1041  2.7069  disp+work(9)
 20.9568    5.5820  15.3748  0.1026    0.0273  0.0753  trcstop(1)
 10.6151    2.4241  8.1909   0.0520    0.0119  0.0401  i4llmd(1)
  8.7146    5.3062  3.4084   0.0427    0.0260  0.0167  dtgreet(1)
  7.6063    1.4893  6.1171   0.0373    0.0073  0.0300  sleep(1)

```

...(lines omitted)...

Kproc summary by thread ID (Tid):

The Kproc summary, by Tid, displays an output of all the kernel process threads that were running on the system during the time of trace collection and their CPU consumption. The thread that consumed the most CPU time during the time of the trace collection is displayed at the beginning of the output.

Kproc Summary (by Tid)

```

-----
-- processing total (msec) --      -- percent of total time --
combined  kernel  operation  combined  kernel  operation  name (Pid Tid Type)
-----  -----  -----  -----  -----  -----  -----
1930.9312  1930.9312  0.0000  13.6525  13.6525  0.0000  wait(8196 8197 W)
 2.1674    2.1674  0.0000  0.0153  0.0153  0.0000  .WSMRefreshServe(0 3 -)
 1.9034    1.9034  1.8020  0.0135  0.0135  0.0128  nfsd(36882 49177 N)
 0.6609    0.5789  0.0820  0.0002  0.0002  0.0000  kbiod(8050 86295 N)

```

...(lines omitted)...

Kproc Types

```

-----
Type Function                      Operation
-----  -----  -----
W  idle thread                      -
N  NFS daemon                       NFS Remote Procedure Calls

```

The Kproc Summary has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>name (Pid Tid Type)</b>	The name of the kernel process associated with the thread, its process ID, its thread ID, and its type. The <b>kproc</b> type is defined in the Kproc Types listing following the Kproc Summary.

**processing total (msec)**

<b>Item</b>	<b>Descriptor</b>
<b>combined</b>	The total amount of CPU time, expressed in milliseconds, that the thread was running in either operation or kernel mode.
<b>kernel</b>	The amount of CPU time, expressed in milliseconds, that the thread spent in unidentified kernel mode.
<b>operation</b>	The amount of CPU time, expressed in milliseconds, that the thread spent in traced operations.

**percent of total time**

<b>Item</b>	<b>Descriptor</b>
<b>combined</b>	The amount of CPU time that the thread was running, expressed as percentage of the total processing time.
<b>kernel</b>	The amount of CPU time that the thread spent in unidentified kernel mode, expressed as percentage of the total processing time.
<b>operation</b>	The amount of CPU time that the thread spent in traced operations, expressed as percentage of the total processing time.

## Kproc Types

<b>Item</b>	<b>Descriptor</b>
<b>Type</b>	A single letter to be used as an index into this listing.
<b>Function</b>	A description of the nominal function of this type of kernel process.
<b>Operation</b>	A description of the traced operations for this type of kernel process.

## Application Pthread summary by process ID (Pid):

The application Pthread summary, by PID, displays an output of all the multi-threaded processes that were running on the system during trace collection and their CPU consumption, and that have spent time making pthread calls. The process that consumed the most CPU time during the trace collection is displayed at the beginning of the list.

### Application Pthread Summary (by Pid)

```

-----
-- processing total (msec) --      -- percent of total application time --
application   other   pthread  application   other   pthread  name (Pid)(Pthread Count)
=====
1277.6602    1274.9354    2.7249    23.8113       23.7605    0.0508    ./pth(245964)(52)
802.6445     801.4162     1.2283    14.9586       14.9357    0.0229    ./pth32(245962)(12)

```

...(lines omitted)...

The output is divided into two main sections:

- The total processing time of the process in milliseconds (processing total (msec))
- The CPU time that the process has consumed, expressed as a percentage of the total application time

The Application Pthread Summary has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>name (Pid) (Pthread Count)</b>	The name of the process associated with the process ID, and the number of pthreads of this process.

### processing total (msec)

<b>Item</b>	<b>Descriptor</b>
<b>application</b>	The total amount of CPU time, expressed in milliseconds, that the process was running in user mode.
<b>pthread</b>	The amount of CPU time, expressed in milliseconds, that the process spent in traced call to the pthreads library.
<b>other</b>	The amount of CPU time, expressed in milliseconds, that the process spent in non traced user mode.

### percent of total application time

<b>Item</b>	<b>Descriptor</b>
<b>application</b>	The amount of CPU time that the process was running in user mode, expressed as percentage of the total application time.
<b>pthread</b>	The amount of CPU time that the process spent in calls to the pthreads library, expressed as percentage of the total application time.
<b>other</b>	The amount of CPU time that the process spent in non traced user mode, expressed as percentage of the total application time.

### System calls summary:

The System Calls Summary provides a list of all the system calls that have completed execution on the system during the monitoring period. The list is sorted by the total CPU time in milliseconds consumed by each type of system call.

System Calls Summary						
Count	Total Time (msec)	% sys time	Avg Time (msec)	Min Time (msec)	Max Time (msec)	SVC (Address)
605	355.4475	1.74%	0.5875	0.0482	4.5626	kwrite(4259c4)
733	196.3752	0.96%	0.2679	0.0042	2.9948	kread(4259e8)
3	9.2217	0.05%	3.0739	2.8888	3.3418	execve(1c95d8)
38	7.6013	0.04%	0.2000	0.0051	1.6137	__loadx(1c9608)
1244	4.4574	0.02%	0.0036	0.0010	0.0143	lseek(425a60)
45	4.3917	0.02%	0.0976	0.0248	0.1810	access(507860)
63	3.3929	0.02%	0.0539	0.0294	0.0719	_select(4e0ee4)
2	2.6761	0.01%	1.3380	1.3338	1.3423	kfork(1c95c8)
207	2.3958	0.01%	0.0116	0.0030	0.1135	_poll(4e0ecc)
228	1.1583	0.01%	0.0051	0.0011	0.2436	kiocntl(4e07ac)
9	0.8136	0.00%	0.0904	0.0842	0.0988	.smtcheckinit(1b245a8)
5	0.5437	0.00%	0.1087	0.0696	0.1777	open(4e08d8)
15	0.3553	0.00%	0.0237	0.0120	0.0322	.smtcheckinit(1b245cc)
2	0.2692	0.00%	0.1346	0.1339	0.1353	statx(4e0950)
33	0.2350	0.00%	0.0071	0.0009	0.0210	_sigaction(1cada4)
1	0.1999	0.00%	0.1999	0.1999	0.1999	kwaitpid(1cab64)
102	0.1954	0.00%	0.0019	0.0013	0.0178	klseek(425a48)

...(lines omitted)...

The System Calls Summary has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>Count</b>	The number of times that a system call of a certain type (see SVC (Address)) has been called during the monitoring period.
<b>Total Time (msec)</b>	The total CPU time that the system spent processing these system calls, expressed in milliseconds.
<b>% sys time</b>	The total CPU time that the system spent processing these system calls, expressed as a percentage of the total processing time.
<b>Avg Time (msec)</b>	The average CPU time that the system spent processing one system call of this type, expressed in milliseconds.
<b>Min Time (msec)</b>	The minimum CPU time that the system needed to process one system call of this type, expressed in milliseconds.
<b>Max Time (msec)</b>	The maximum CPU time that the system needed to process one system call of this type, expressed in milliseconds.
<b>SVC (Address)</b>	The name of the system call and its kernel address.

### Pending system calls summary:

The pending system calls summary provides a list of all the system calls that have been executed on the system during the monitoring period but have not completed. The list is sorted by Tid.

Pending System Calls Summary		
Accumulated	SVC (Address)	Procname (Pid Tid)

```

Time (msec)
=====
0.0656  _select(4e0ee4)      sendmail(7844 5001)
0.0452  _select(4e0ee4)      syslogd(7514 8591)
0.0712  _select(4e0ee4)      snmpd(5426 9293)
0.0156  kiocntl(4e07ac)      trcstop(47210 18379)
0.0274  kwaitpid(1cab64)     ksh(20276 44359)
0.0567  kread4259e8)        ksh(23342 50873)

```

...(lines omitted)...

The Pending System Calls Summary has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>Accumulated Time (msec)</b>	The accumulated CPU time that the system spent processing the pending system call, expressed in milliseconds.
<b>SVC (Address)</b>	The name of the system call and its kernel address.
<b>Procname (Pid Tid)</b>	The name of the process associated with the thread that made the system call, its process ID, and the thread ID.

### Hypervisor calls summary:

The Hypervisor calls summary provides a list of all the hypervisor calls that have completed execution on the system during the monitoring period. The list is sorted by the total CPU time, in milliseconds, consumed by each type of hypervisor call.

Hypervisor Calls Summary						
Count	Total Time (msec)	% sys time	Avg Time (msec)	Min Time (msec)	Max Time (msec)	HCALL (Address)
4	0.0077	0.00%	0.0019	0.0014	0.0025	H_XIRR(3ada19c)
4	0.0070	0.00%	0.0017	0.0015	0.0021	H_EOI(3ad6564)

The Hypervisor Calls Summary has the following fields:

<b>Item</b>	<b>Description</b>
<b>Count</b>	The number of times that a hypervisor call of a certain type has been called during the monitoring period.
<b>Total Time (msec)</b>	The total CPU time that the system spent processing hypervisor calls of this type, expressed in milliseconds.
<b>% sys Time</b>	The total CPU time that the system spent processing the hypervisor calls of this type, expressed as a percentage of the total processing time.
<b>Avg Time (msec)</b>	The average CPU time that the system spent processing one hypervisor call of this type, expressed in milliseconds.
<b>Min Time (msec)</b>	The minimum CPU time that the system needed to process one hypervisor call of this type, expressed in milliseconds.
<b>Max Time (msec)</b>	The maximum CPU time that the system needed to process one hypervisor call of this type, expressed in milliseconds.
<b>HCALL (address)</b>	The name of the hypervisor call and the kernel address of its caller.

### Pending Hypervisor calls summary:

The pending Hypervisor calls summary provides a list of all the hypervisor calls that have been executed on the system during the monitoring period but have not completed. The list is sorted by Tid.

Pending Hypervisor Calls Summary		
Accumulated Time (msec)	HCALL (Address)	Procname (Pid Tid)
0.0066	H_XIRR(3ada19c)	syncd(3916 5981)

The Pending Hypervisor Calls Summary has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>Accumulated Time (msec)</b>	The accumulated CPU time that the system spent processing the pending hypervisor call, expressed in milliseconds.
<b>HCALL (address)</b>	The name of the hypervisor call and the kernel address of its caller.
<b>Procname (Pid Tid)</b>	The name of the process associated with the thread that made the hypervisor call, its process ID, and the thread ID.

**System NFS calls summary:**

The system NFS calls summary provides a list of all the system NFS calls that have completed execution on the system during the monitoring period. The list is divided by NFS versions, and each list is sorted by the total CPU time, in milliseconds, consumed by each type of system NFS call.

System NFS Calls Summary							
Count	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	% Tot Time	% Tot Count	Opcode
253	48.4115	0.1913	0.0952	1.0097	98.91	98.83	RFS2_READLINK
2	0.3959	0.1980	0.1750	0.2209	0.81	0.78	RFS2_LOOKUP
1	0.1373	0.1373	0.1373	0.1373	0.28	0.39	RFS2_NULL
-----							
256	48.9448	0.1912					NFS V2 TOTAL
3015	4086.9121	1.3555	0.1035	31.6976	40.45	17.12	RFS3_READ
145	2296.3158	15.8367	1.1177	42.9125	22.73	0.82	RFS3_WRITE
10525	2263.3336	0.2150	0.0547	2.9737	22.40	59.77	RFS3_LOOKUP
373	777.2854	2.0839	0.2839	17.5724	7.69	2.12	RFS3_READDIRPLUS
2058	385.9510	0.1875	0.0875	1.1993	3.82	11.69	RFS3_GETATTR
942	178.6442	0.1896	0.0554	1.2320	1.77	5.35	RFS3_ACCESS
515	97.0297	0.1884	0.0659	0.9774	0.96	2.92	RFS3_READLINK
25	11.3046	0.4522	0.2364	0.9712	0.11	0.14	RFS3_READDIR
3	2.8648	0.9549	0.8939	0.9936	0.03	0.02	RFS3_CREATE
3	2.8590	0.9530	0.5831	1.4095	0.03	0.02	RFS3_COMMIT
2	1.1824	0.5912	0.2796	0.9028	0.01	0.01	RFS3_FSSTAT
1	0.2773	0.2773	0.2773	0.2773	0.00	0.01	RFS3_SETATTR
1	0.2366	0.2366	0.2366	0.2366	0.00	0.01	RFS3_PATHCONF
1	0.1804	0.1804	0.1804	0.1804	0.00	0.01	RFS3_NULL
-----							
17609	10104.3769	0.5738					NFS V3 TOTAL
105	2296.3158	15.8367	1.1177	42.9125	22.73	0.82	CLOSE
3025	2263.3336	0.2150	0.0547	2.9737	22.40	59.77	COMMIT
373	777.2854	2.0839	0.2839	17.5724	7.69	2.12	CREATE
2058	385.9510	0.1875	0.0875	1.1993	3.82	11.69	DELEGPURGE
942	178.6442	0.1896	0.0554	1.2320	1.77	5.35	DELEGRETURN
515	97.0297	0.1884	0.0659	0.9774	0.96	2.92	GETATTR
25	11.3046	0.4522	0.2364	0.9712	0.11	0.14	GETFH
3	2.8648	0.9549	0.8939	0.9936	0.03	0.02	LINK
3	2.8590	0.9530	0.5831	1.4095	0.03	0.02	LOCK
2	1.1824	0.5912	0.2796	0.9028	0.01	0.01	LOCKT
1	0.2773	0.2773	0.2773	0.2773	0.00	0.01	LOCKU
1	0.2366	0.2366	0.2366	0.2366	0.00	0.01	OOKUP
1	0.1804	0.1804	0.1804	0.1804	0.00	0.01	LOOKUPP
1	0.1704	0.1704	0.1704	0.1704	0.00	0.01	NVERIFY
-----							
17609	10104.3769	0.5738					NFS V4 SERVER TOTAL
3	2.8590	0.9530	0.5831	1.4095	0.03	0.02	NFS4_ACCESS
2	1.1824	0.5912	0.2796	0.9028	0.01	0.01	NFS4_VALIDATE_CACHES
1	0.2773	0.2773	0.2773	0.2773	0.00	0.01	NFS4_GETATTR
1	0.2366	0.2366	0.2366	0.2366	0.00	0.01	NFS4_CHECK_ACCESS
1	0.0000	0.0000	0.1804	0.1804	0.00	0.01	NFS4_HOLD

```

1      0.1704    0.1704    0.1704    0.1704    0.00    0.01  NFS4_RELE

```

```

-----
17609  10104.3769  0.5738  -----  -----  -----  -----  -----
NFS V4 CLIENT TOTAL

```

The System NFS Calls Summary has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>Count</b>	The number of times that a certain type of system NFS call (see <b>Opcode</b> ) has been called during the monitoring period.
<b>Total Time (msec)</b>	The total CPU time that the system spent processing system NFS calls of this type, expressed in milliseconds.
<b>Avg Time (msec)</b>	The average CPU time that the system spent processing one system NFS call of this type, expressed in milliseconds.
<b>Min Time (msec)</b>	The minimum CPU time that the system needed to process one system NFS call of this type, expressed in milliseconds.
<b>Max Time (msec)</b>	The maximum CPU time that the system needed to process one system NFS call of this type, expressed in milliseconds.
<b>% Tot Time</b>	The total CPU time that the system spent processing the system NFS calls of this type, expressed as a percentage of the total processing time.
<b>% Tot Count</b>	The number of times that a system NFS call of a certain type was made, expressed as a percentage of the total count.
<b>Opcode</b>	The name of the system NFS call.

### Pending NFS calls summary:

The pending NFS calls summary provides a list of all the system NFS calls that have executed on the system during the monitoring period but have not completed. The list is sorted by the **Tid**.

#### Pending NFS Calls Summary

```

-----
Accumulated   Sequence Number  Procname (Pid  Tid)
Time (msec)   Opcode
-----
0.0831  1038711932      nfsd(1007854 331969)
0.0833  1038897247      nfsd(1007854 352459)
0.0317  1038788652      nfsd(1007854 413931)
0.0029  NFS4_ATTRCACHE  kbiod(100098 678934)
..(lines omitted)...

```

The Pending System NFS Calls Summary has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>Accumulated Time (msec)</b>	The accumulated CPU time that the system spent processing the pending system NFS call, expressed in milliseconds.
<b>Sequence Number</b>	The sequence number represents the transaction identifier ( <b>XID</b> ) of an NFS operation. It is used to uniquely identify an operation and is used in the RPC call/reply messages. This number is provided instead of the operation name because the name of the operation is unknown until it completes.
<b>Opcode</b>	The name of pending operation NFS V4.
<b>Procname (Pid Tid)</b>	The name of the process associated with the thread that made the system NFS call, its process ID, and the thread ID.

### Pthread calls summary:

The Pthread calls summary provides a list of all the pthread calls that have completed execution on the system during the monitoring period. The list is sorted by the total CPU time, in milliseconds, consumed by each type of pthread call.

### Pthread Calls Summary

Count	Total Time (msec)	% sys time	Avg Time (msec)	Min Time (msec)	Max Time (msec)	Pthread Routine
62	3.6226	0.04%	0.0584	0.0318	0.1833	pthread_create
10	0.1798	0.00%	0.0180	0.0119	0.0341	pthread_cancel
8	0.0725	0.00%	0.0091	0.0064	0.0205	pthread_join
1	0.0553	0.00%	0.0553	0.0553	0.0553	pthread_detach
1	0.0229	0.00%	0.0229	0.0229	0.0229	pthread_kill

The Pthread Calls Summary report has the following fields:

Item	Descriptor
<b>Count</b>	The number of times that a pthread call of a certain type has been called during the monitoring period.
<b>Total Time (msec)</b>	The total CPU time that the system spent processing all pthread calls of this type, expressed in milliseconds.
<b>% sys time</b>	The total CPU time that the system spent processing all calls of this type, expressed as a percentage of the total processing time.
<b>Avg Time (msec)</b>	The average CPU time that the system spent processing one pthread call of this type, expressed in milliseconds.
<b>Min Time (msec)</b>	The minimum CPU time the system used to process one pthread call of this type, expressed in milliseconds.
<b>Pthread routine</b>	The name of the routine in the pthread library.

### Pending Pthread calls summary:

The pending Pthread calls summary provides a list of all the pthread calls that have been executed on the system during the monitoring period but have not completed. The list is sorted by Pid-Ptid.

#### Pending Pthread Calls Summary

Accumulated Time (msec)	Pthread Routine	Procname (Pid Tid Ptid)
1990.9400	pthread_join	./pth32(245962 1007759 1)

The Pending Pthread System Calls Summary has the following fields:

Item	Descriptor
<b>Accumulated Time (msec)</b>	The accumulated CPU time that the system spent processing the pending pthread call, expressed in milliseconds.
<b>Pthread Routine</b>	The name of the pthread routine of the <b>libpthreads</b> library.
<b>Procname (Pid Tid Ptid)</b>	The name of the process associated with the thread and the pthread which made the pthread call, its process ID, the thread ID and the pthread ID.

### FLIH summary:

The FLIH (First Level Interrupt Handler) summary lists all first level interrupt handlers that were called during the monitoring period.

The Global FLIH Summary lists the total of first level interrupts on the system, while the Per CPU FLIH Summary lists the first level interrupts per CPU.

#### Global Flih Summary

Count	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	Flih Type
2183	203.5524	0.0932	0.0041	0.4576	31(DEC_R_INTR)
946	102.4195	0.1083	0.0063	0.6590	3(DATA_ACC_PG_FLT)
12	1.6720	0.1393	0.0828	0.3366	32(QUEUED_INTR)

```
1058 183.6655 0.1736 0.0039 0.7001 5(IO_INTR)
```

Per CPU Flih Summary

CPU Number 0:

Count	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	Flih Type
635	39.8413	0.0627	0.0041	0.4576	31(DEC_R_INTR)
936	101.4960	0.1084	0.0063	0.6590	3(DATA_ACC_PG_FLT)
9	1.3946	0.1550	0.0851	0.3366	32(QUEUED_INTR)
266	33.4247	0.1257	0.0039	0.4319	5(IO_INTR)

CPU Number 1:

Count	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	Flih Type
4	0.2405	0.0601	0.0517	0.0735	3(DATA_ACC_PG_FLT)
258	49.2098	0.1907	0.0060	0.5076	5(IO_INTR)
515	55.3714	0.1075	0.0080	0.3696	31(DEC_R_INTR)

Pending Flih Summary

Accumulated Time (msec)	Flih Type
0.0123	5(IO_INTR)

...(lines omitted)...

The FLIH Summary report has the following fields:

Item	Descriptor
<b>Count</b>	The number of times that a first level interrupt of a certain type (see Flih Type) occurred during the monitoring period.
<b>Total Time (msec)</b>	The total CPU time that the system spent processing these first level interrupts, expressed in milliseconds.
<b>Avg Time (msec)</b>	The average CPU time that the system spent processing one first level interrupt of this type, expressed in milliseconds.
<b>Min Time (msec)</b>	The minimum CPU time that the system needed to process one first level interrupt of this type, expressed in milliseconds.
<b>Max Time (msec)</b>	The maximum CPU time that the system needed to process one first level interrupt of this type, expressed in milliseconds.
<b>Flih Type</b>	The number and name of the first level interrupt.
<b>Accumulated Time (msec)</b>	The accumulated CPU time that the system spent processing the pending first level interrupt, expressed in milliseconds.

*FLIH types in the example:*

The following are FLIH types that were depicted in the FLIH summary.

Item	Descriptor
DATA_ACC_PG_FLT	Data access page fault
QUEUED_INTR	Queued interrupt
DECR_INTR	Decrementer interrupt
IO_INTR	I/O interrupt

### SLIH summary:

The Second level interrupt handler (SLIH) Summary lists all second level interrupt handlers that were called during the monitoring period.

The Global Slih Summary lists the total of second level interrupts on the system, while the Per CPU Slih Summary lists the second level interrupts per CPU.

Global Slih Summary					
Count	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	Slih Name(Address)
43	7.0434	0.1638	0.0284	0.3763	s_scsiddpin(1a99104)
1015	42.0601	0.0414	0.0096	0.0913	ssapin(1990490)

Per CPU Slih Summary					
CPU Number 0:					
Count	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	Slih Name(Address)
8	1.3500	0.1688	0.0289	0.3087	s_scsiddpin(1a99104)
258	7.9232	0.0307	0.0096	0.0733	ssapin(1990490)
CPU Number 1:					
Count	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	Slih Name(Address)
10	1.2685	0.1268	0.0579	0.2818	s_scsiddpin(1a99104)
248	11.2759	0.0455	0.0138	0.0641	ssapin(1990490)

...(lines omitted)...

The SLIH Summary report has the following fields:

Item	Descriptor
Count	The number of times that each second level interrupt handler was called during the monitoring period.
Total Time (msec)	The total CPU time that the system spent processing these second level interrupts, expressed in milliseconds.
Avg Time (msec)	The average CPU time that the system spent processing one second level interrupt of this type, expressed in milliseconds.
Min Time (msec)	The minimum CPU time that the system needed to process one second level interrupt of this type, expressed in milliseconds.
Max Time (msec)	The maximum CPU time that the system needed to process one second level interrupt of this type, expressed in milliseconds.
Slih Name (Address)	The module name and kernel address of the second level interrupt.

### Reports generated with the -e flag:

The report generated with the -e flag includes the data shown in the default report, and also includes additional information in the System Calls Summary, the Pending System Calls Summary, the Hypervisor Calls Summary, the Pending Hypervisor Calls Summary, the System NFS Calls Summary, the Pending NFS Calls Summary, the Pthread Calls Summary and the Pending Pthread Calls Summary.

The additional information in the System Calls Summary, Hypervisor Calls Summary, System NFS Calls Summary, and the Pthread Calls Summary includes the total, average, maximum, and minimum elapsed time that a call was running. The additional information in the Pending System Calls Summary, Pending Hypervisor Calls Summary, Pending NFS Calls Summary, and the Pending Pthread Calls Summary is the accumulated elapsed time for the pending calls. This additional information is present in all the system call, hypervisor call, NFS call, and pthread call reports: globally, in the process detailed report (-p), the thread detailed report (-t), and the pthread detailed report (-P).

The following is an example of the additional information reported by using the **-e** flag:

```
# curt -e -i trace.r -m trace.nm -n gensyms.out -o curt.out
# cat curt.out
```

...(lines omitted)...

#### System Calls Summary

Count	Total Time (msec)	% sys time	Avg Time (msec)	Min Time (msec)	Max Time (msec)	Tot ETime (msec)	Avg ETime (msec)	Min ETime (msec)	Max ETime (msec)	SVC (Address)
605	355.4475	1.74%	0.5875	0.0482	4.5626	31172.7658	51.5252	0.0482	422.2323	kwrite(4259c4)
733	196.3752	0.96%	0.2679	0.0042	2.9948	12967.9407	17.6916	0.0042	265.1204	kread(4259e8)
3	9.2217	0.05%	3.0739	2.8888	3.3418	57.2051	19.0684	4.5475	40.0557	execve(1c95d8)
38	7.6013	0.04%	0.2000	0.0051	1.6137	12.5002	0.3290	0.0051	3.3120	_loadx(1c9608)
1244	4.4574	0.02%	0.0036	0.0010	0.0143	4.4574	0.0036	0.0010	0.0143	lseek(425a60)
45	4.3917	0.02%	0.0976	0.0248	0.1810	4.6636	0.1036	0.0248	0.3037	access(507860)
63	3.3929	0.02%	0.0539	0.0294	0.0719	5006.0887	79.4617	0.0294	100.4802	select(4e0ee4)
2	2.6761	0.01%	1.3380	1.3338	1.3423	45.5026	22.7513	7.5745	37.9281	kfork(1c95c8)
207	2.3958	0.01%	0.0116	0.0030	0.1135	4494.9249	21.7146	0.0030	499.1363	_poll(4e0ecc)
228	1.1583	0.01%	0.0051	0.0011	0.2436	1.1583	0.0051	0.0011	0.2436	kiotl(4e07ac)
9	0.8136	0.00%	0.0904	0.0842	0.0988	4498.7472	499.8608	499.8052	499.8898	.smtcheckinit(1b245a8)
5	0.5437	0.00%	0.1087	0.0696	0.1777	0.5437	0.1087	0.0696	0.1777	open(4e08d8)
15	0.3553	0.00%	0.0237	0.0120	0.0322	0.3553	0.0237	0.0120	0.0322	.smtcheckinit(1b245cc)
2	0.2692	0.00%	0.1346	0.1339	0.1353	0.2692	0.1346	0.1339	0.1353	statx(4e0950)
33	0.2350	0.00%	0.0071	0.0009	0.0210	0.2350	0.0071	0.0009	0.0210	sigaction(1cada4)
1	0.1999	0.00%	0.1999	0.1999	0.1999	5019.0588	5019.0588	5019.0588	5019.0588	kwaitpid(1cab64)
102	0.1954	0.00%	0.0019	0.0013	0.0178	0.5427	0.0053	0.0013	0.3650	klseek(425a48)

...(lines omitted)...

#### Pending System Calls Summary

Accumulated Time (msec)	Accumulated ETime (msec)	SVC (Address)	Procname (Pid Tid)
0.0855	93.6498	kread(4259e8)	oracle(143984 48841)

...(lines omitted)...

#### Hypervisor Calls Summary

Count	Total Time (msec)	% sys time	Avg Time (msec)	Min Time (msec)	Max Time (msec)	Tot ETime (msec)	Avg ETime (msec)	Min ETime (msec)	Max ETime (msec)	HCALL (Address)
4	0.0077	0.00%	0.0019	0.0014	0.0025	0.0077	0.0019	0.0014	0.0025	H_XIRR(3ada19c)
4	0.0070	0.00%	0.0017	0.0015	0.0021	0.0070	0.0017	0.0015	0.0021	H_E01(3ad6564)

#### Pending Hypervisor Calls Summary

Accumulated Time (msec)	Accumulated ETime (msec)	HCALL (Address)	Procname (Pid Tid)
0.0855	93.6498	H_XIRR(3ada19c)	syncd(3916 5981)

#### System NFS Calls Summary

Count	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	% Tot Time	Total ETime (msec)	Avg ETime (msec)	Min ETime (msec)	Max ETime (msec)	% Tot ETime	% Tot Count	Opcode
6647	456.1029	0.0686	0.0376	0.6267	15.83	9267.7256	1.3943	0.0376	304.9501	14.63	27.88	RFS3_LOOKUP
2694	147.1680	0.0546	0.0348	0.5517	5.11	1474.4267	0.5473	0.0348	25.9402	2.33	11.30	RFS3_GETATTR
1702	85.8328	0.0504	0.0339	0.5793	2.98	146.4281	0.0860	0.0339	5.7539	0.23	7.14	RFS3_READLINK
1552	78.1015	0.0503	0.0367	0.5513	2.71	153.5844	0.0990	0.0367	7.5125	0.24	6.51	RFS3_ACCESS
235	33.3158	0.1418	0.0890	0.3312	1.16	1579.4557	6.7211	0.0890	56.0876	2.49	0.99	RFS3_SETATTR
21	5.5979	0.2666	0.0097	0.8142	82.79	127.2616	6.0601	0.0097	89.0570	99.37	25.00	NFS4_WRITE
59	1.1505	0.0195	0.0121	0.0258	17.01	0.7873	0.0133	0.0093	0.0194	0.61	70.24	NFS4_ATTRCACHE
4	0.0135	0.0034	0.0026	0.0044	0.20	0.0135	0.0034	0.0026	0.0044	0.01	4.76	NFS4_GET_UID_GID

...(line omitted)...

```

Pending NFS Calls Summary
-----
Accumulated   Accumulated   Sequence Number   Procname (Pid Tid)
Time (msec)   ETime (msec)   Opcode
-----
0.0831        15.1581        1038711932        nfsd(1007854 331969)
0.0833        13.8889        1038897247        nfsd(1007854 352459)
0.0087        10.8976        NFS4_ATTRCACHE    kbiod(100098 678934)
...(line omitted)...

```

```

Pthread Calls Summary
-----
Count   Total Time   % sys   Avg Time   Min Time   Max Time   Tot ETime   Avg ETime   Min ETime   Max ETime   Pthread Routine
-----
72      2.0126      0.01%   0.0280    0.0173    0.1222    13.7738     0.1913     0.0975     0.6147    pthread_create
2       0.6948      0.00%   0.3474    0.0740    0.6208    92.3033     46.1517    9.9445    82.3588    pthread_kill
12      0.3087      0.00%   0.0257    0.0058    0.0779    25.0506     2.0876     0.0168    10.0605    pthread_cancel
22      0.0613      0.00%   0.0028    0.0017    0.0104    2329.0179   105.8644   0.0044    1908.3402   pthread_join
2       0.0128      0.00%   0.0064    0.0062    0.0065     0.1528     0.0764     0.0637     0.0891    pthread_detach

```

```

Pending Pthread Calls Summary
-----
Accumulated   Accumulated   Pthread Routine   Procname (pid tid ptid)
Time (msec)   ETime (msec)
-----
3.3102        4946.5433     pthread_join      ./pth32(282718 700515 1)
0.0025        544.4914      pthread_join      ./pth(282720 - 1)

```

The system call, hypervisor call, NFS call, and pthread call reports in the preceding example have the following fields in addition to the default System Calls Summary, Hypervisor Calls Summary, System NFS Calls Summary, and Pthread Calls Summary :

Item	Descriptor
<b>Tot ETime (msec)</b>	The total amount of time from when each instance of the call was started until it completed. This time will include any time spent servicing interrupts, running other processes, and so forth.
<b>Avg ETime (msec)</b>	The average amount of time from when the call was started until it completed. This time will include any time spent servicing interrupts, running other processes, and so forth.
<b>Min ETime (msec)</b>	The minimum amount of time from when the call was started until it completed. This time will include any time spent servicing interrupts, running other processes, and so forth.
<b>Max ETime (msec)</b>	The maximum amount of time from when the call was started until it completed. This time will include any time spent servicing interrupts, running other processes, and so forth.
<b>Accumulated ETime (msec)</b>	The total amount of time from when the pending call was started until the end of the trace. This time will include any time spent servicing interrupts, running other processes, and so forth.

The preceding example report shows that the maximum elapsed time for the **kwwrite** system call was 422.2323 msec, but the maximum CPU time was 4.5626 msec. If this amount of overhead time is unusual for the device being written to, further analysis is needed.

### Reports generated with the -s flag:

The report generated with the -s flag includes the data shown in the default report, and data on errors returned by system calls.

```

# curt -s -i trace.r -m trace.nm -n gensyms.out -o curt.out
# cat curt.out
...(lines omitted)...

```

#### Errors Returned by System Calls

```

Errors (errno : count : description) returned for System Call: kiocntl(4e07ac)
  25 :      15 : "Not a typewriter"
Errors (errno : count : description) returned for System Call: execve(1c95d8)
   2 :       2 : "No such file or directory"
...(lines omitted)...

```

If a large number of errors of a specific type or on a specific system call point to a system or application problem, other debug measures can be used to determine and fix the problem.

## Reports generated with the -t flag:

The report generated with the **-t** flag includes the data shown in the default report, and also includes a detailed report on thread status that includes the amount of time the thread was in application and system call mode, what system calls the thread made, processor affinity, the number of times the thread was dispatched, and to which CPUs it was dispatched.

The report also includes dispatch wait time and details of interrupts:

...(lines omitted)...

-----  
Report for Thread Id: 48841 (hex bec9) Pid: 143984 (hex 23270)

Process Name: oracle  
-----

Total Application Time (ms): 70.324465

Total System Call Time (ms): 53.014910

Total Hypervisor Call Time (ms): 0.077000

### Thread System Call Summary

-----

Count	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	SVC (Address)
69	34.0819	0.4939	0.1666	1.2762	kwrite(169ff8)
77	12.0026	0.1559	0.0474	0.2889	kread(16a01c)
510	4.9743	0.0098	0.0029	0.0467	times(f1e14)
73	1.2045	0.0165	0.0105	0.0306	select(1d1704)
68	0.6000	0.0088	0.0023	0.0445	lseek(16a094)
12	0.1516	0.0126	0.0071	0.0241	getrusage(f1be0)

No Errors Returned by System Calls

### Pending System Calls Summary

-----

Accumulated SVC (Address)  
Time (msec)

-----  
0.1420 kread(16a01c)

### Thread Hypervisor Calls Summary

-----

Count	Total Time (msec)	% sys time	Avg Time (msec)	Min Time (msec)	Max Time (msec)	HCALL (Address)
4	0.0077	0.00%	0.0019	0.0014	0.0025	H_XIRR(3ada19c)

### Pending Hypervisor Calls Summary

-----

Accumulated HCALL (Address)  
Time (msec)

-----  
0.0066 H\_XIRR(3ada19c)

processor affinity: 0.583333

Dispatch Histogram for thread (CPUid : times\_dispatched).

CPU 0 : 23  
CPU 1 : 23  
CPU 2 : 9  
CPU 3 : 9  
CPU 4 : 8  
CPU 5 : 14

```

CPU 6 : 17
CPU 7 : 19
CPU 8 : 1
CPU 9 : 4
CPU 10 : 1
CPU 11 : 4

```

```

total number of dispatches: 131
total number of redispaches due to interrupts being disabled: 1
avg. dispatch wait time (ms): 8.273515

```

```

Data on Interrupts that Occurred while Thread was Running
Type of Interrupt      Count
-----
Data Access Page Faults (DSI): 115
Instr. Fetch Page Faults (ISI): 0
Align. Error Interrupts: 0
IO (external) Interrupts: 0
Program Check Interrupts: 0
FP Unavailable Interrupts: 0
FP Imprecise Interrupts: 0
RunMode Interrupts: 0
Decrementer Interrupts: 18
Queued (Soft level) Interrupts: 15

```

...(lines omitted)...

If the thread belongs to an NFS kernel process, the report will include information on NFS operations instead of System calls:

```

Report for Thread Id: 1966273 (hex 1e00c1) Pid: 1007854 (hex f60ee)
Process Name: nfsd

```

```

-----
Total Kernel Time (ms): 3.198998
Total Operation Time (ms): 28.839927
Total Hypervisor Call Time (ms): 0.000000

```

Thread NFS Call Summary													
Count	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	% Tot Time	Total ETime (msec)	Avg ETime (msec)	Min ETime (msec)	Max ETime (msec)	% Tot ETime	% Tot Count	Opcode	
28	12.2661	0.4381	0.3815	0.4841	42.73	32.0893	1.1460	0.4391	16.6283	11.46	11.52	RFS3_READDIRPLUS	
63	3.8953	0.0618	0.0405	0.1288	13.57	23.1031	0.3667	0.0405	7.0886	8.25	25.93	RFS3_LOOKUP	
49	3.2795	0.0669	0.0527	0.0960	11.42	103.8431	2.1192	0.0534	35.3617	37.09	20.16	RFS3_READ	
18	2.8464	0.1581	0.1099	0.2264	9.91	7.9129	0.4396	0.1258	4.3503	2.83	7.41	RFS3_WRITE	
29	1.3331	0.0460	0.0348	0.0620	4.64	1.4953	0.0516	0.0348	0.0940	0.53	11.93	RFS3_GETATTR	
5	1.2763	0.2553	0.2374	0.3036	4.45	45.0798	9.0160	0.9015	21.7257	16.10	2.06	RFS3_REMOVE	
8	1.1001	0.1375	0.1180	0.1719	3.83	53.6532	6.7067	1.4293	19.9199	19.17	3.29	RFS3_COMMIT	
20	0.9262	0.0463	0.0367	0.0507	3.23	1.2060	0.0603	0.0367	0.1314	0.43	8.23	RFS3_READLINK	
15	0.6798	0.0453	0.0386	0.0519	2.37	0.8015	0.0534	0.0386	0.0788	0.29	6.17	RFS3_ACCESS	
2	0.4033	0.2017	0.1982	0.2051	1.40	0.5355	0.2677	0.2677	0.2677	0.19	0.82	RFS3_READDIR	
1	0.3015	0.3015	0.3015	0.3015	1.05	6.2614	6.2614	6.2614	6.2614	2.24	0.41	RFS3_CREATE	
2	0.2531	0.1265	0.1000	0.1531	0.88	3.7756	1.8878	0.1000	3.6756	1.35	0.82	RFS3_SETATTR	
2	0.0853	0.0426	0.0413	0.0440	0.30	0.1333	0.0667	0.0532	0.0802	0.05	0.82	RFS3_FSINFO	
1	0.0634	0.0634	0.0634	0.0634	0.22	0.0634	0.0634	0.0634	0.0634	0.02	0.41	RFS3_FSSTAT	
-----													
243	28.7094	0.1181				279.9534	1.1521					NFS V3 TOTAL	
4	0.0777	0.0194	0.0164	0.0232	10.00	0.0523	0.0131	0.0115	0.0152	10.00	10.00	LINK	
-----													
4	0.0777	0.0194				0.0523	0.0131					NFS V4 CLIENT TOTAL	

Pending NFS Calls Summary		
Accumulated Time (msec)	Accumulated ETime (msec)	Sequence Number Opcode
0.1305	182.6903	1038932778
0.0123	102.6324	NFS4_ATTRCACHE

The following information is included in the threads summary:

Item	Descriptor
Thread ID	The Thread ID of the thread.
Process ID	The Process ID that the thread belongs to.
Process Name	The process name, if known, that the thread belongs to.
Total Application Time (ms)	The amount of time, expressed in milliseconds, that the thread spent in application mode.
Total System Call Time (ms)	The amount of time, expressed in milliseconds, that the thread spent in system call mode.
Thread System Call Summary	A system call summary for the thread; this has the same fields as the global System Calls Summary. It also includes elapsed time if the <b>-e</b> flag is specified and error information if the <b>-s</b> flag is specified.
Pending System Calls Summary	If the thread was executing a system call at the end of the trace, a pending system call summary will be printed. This has the Accumulated Time and Supervisor Call (SVC Address) fields. It also includes elapsed time if the <b>-e</b> flag is specified.
Thread Hypervisor Calls Summary	The hypervisor call summary for the thread; this has the same fields as the global Hypervisor Calls Summary. It also includes elapsed time if the <b>-e</b> flag is specified.
Pending Hypervisor Calls Summary	If the thread was executing a hypervisor call at the end of the trace, a pending hypervisor call summary will be printed. This has the Accumulated Time and Hypervisor Call fields. It also includes elapsed time if the <b>-e</b> flag is specified.
Thread NFS Calls Summary	An NFS call summary for the thread. This has the same fields as the global System NFS Call Summary. It also includes elapsed time if the <b>-e</b> flag is specified.
Pending NFS Calls Summary	If the thread was executing an NFS call at the end of the trace, a pending NFS call summary will be printed. This has the <b>Accumulated Time</b> and <b>Sequence Number</b> or, in the case of NFS V4, <b>Opcode</b> , fields. It also includes elapsed time if the <b>-e</b> flag is specified.
processor affinity	The process affinity, which is the probability that, for any dispatch of the thread, the thread was dispatched to the same processor on which it last executed.
Dispatch Histogram for thread	Shows the number of times the thread was dispatched to each CPU in the system.
total number of dispatches	The total number of times the thread was dispatched (not including redispatches).
total number of redispatches due to interrupts being disabled	The number of redispatches due to interrupts being disabled, which is when the dispatch code is forced to dispatch the same thread that is currently running on that particular CPU because the thread had disabled some interrupts. This total is only reported if the value is non-zero.
avg. dispatch wait time (ms)	The average dispatch wait time is the average elapsed time for the thread from being undispached and its next dispatch.
Data on Interrupts that occurred while Thread was Running	Count of how many times each type of FLIH occurred while this thread was executing.

### Reports generated with the **-p** flag:

The report generated with the **-p** flag includes the data shown in the default report and also includes a detailed report for each process that includes the Process ID and name, a count and list of the thread IDs, and the count and list of the pthread IDs belonging to the process. The total application time, the system call time, and the application time details for all the threads of the process are given. Lastly, it includes summary reports of all the completed and pending system calls, and pthread calls for the threads of the process.

The following example shows the report generated for the router process (PID 129190):

Process Details for Pid: 129190

Process Name: router

7 Tids for this Pid: 245889 245631 244599 82843 78701 75347 28941  
 9 Ptds for this Pid: 2057 1800 1543 1286 1029 772 515 258 1

Total Application Time (ms): 124.023749  
 Total System Call Time (ms): 8.948695  
 Total Hypervisor Time (ms): 0.000000

Application time details:

Total Pthread Call Time (ms): 1.228271  
 Total Pthread Dispatch Time (ms): 2.760476  
 Total Pthread Idle Dispatch Time (ms): 0.110307  
 Total Other Time (ms): 798.545446

Total number of pthread dispatches: 53  
 Total number of pthread idle dispatches: 3

#### Process System Calls Summary

Count	Total Time (msec)	% sys time	Avg Time (msec)	Min Time (msec)	Max Time (msec)	SVC (Address)
93	3.6829	0.05%	0.0396	0.0060	0.3077	kread(19731c)
23	2.2395	0.03%	0.0974	0.0090	0.4537	kwrite(1972f8)
30	0.8885	0.01%	0.0296	0.0073	0.0460	select(208c5c)
1	0.5933	0.01%	0.5933	0.5933	0.5933	fsync(1972a4)
106	0.4902	0.01%	0.0046	0.0035	0.0105	klseek(19737c)
13	0.3285	0.00%	0.0253	0.0130	0.0387	semctl(2089e0)
6	0.2513	0.00%	0.0419	0.0238	0.0650	semop(2089c8)
3	0.1223	0.00%	0.0408	0.0127	0.0730	statx(2086d4)
1	0.0793	0.00%	0.0793	0.0793	0.0793	send(11e1ec)
9	0.0679	0.00%	0.0075	0.0053	0.0147	fstatx(2086c8)
4	0.0524	0.00%	0.0131	0.0023	0.0348	kfcntl(22aa14)
5	0.0448	0.00%	0.0090	0.0086	0.0096	yield(11dbec)
3	0.0444	0.00%	0.0148	0.0049	0.0219	recv(11e1b0)
1	0.0355	0.00%	0.0355	0.0355	0.0355	open(208674)
1	0.0281	0.00%	0.0281	0.0281	0.0281	close(19728c)

#### Pending System Calls Summary

Accumulated Time (msec)	SVC (Address)	Tid
0.0452	select(208c5c)	245889
0.0425	select(208c5c)	78701
0.0285	select(208c5c)	82843
0.0284	select(208c5c)	245631
0.0274	select(208c5c)	244599
0.0179	select(208c5c)	75347

...(omitted lines)...

#### Pthread Calls Summary

Count	Total Time (msec)	% sys time	Avg Time (msec)	Min Time (msec)	Max Time (msec)	Pthread Routine
19	0.0477	0.00%	0.0025	0.0017	0.0104	pthread_join
1	0.0065	0.00%	0.0065	0.0065	0.0065	pthread_detach
1	0.6208	0.00%	0.6208	0.6208	0.6208	pthread_kill
6	0.1261	0.00%	0.0210	0.0077	0.0779	pthread_cancel
21	0.7080	0.01%	0.0337	0.0226	0.1222	pthread_create

#### Pending Pthread Calls Summary

Accumulated Time (msec)	Pthread Routine	Tid	Ptid
3.3102	pthread_join	78701	1

If the process is an NFS kernel process, the report will include information on NFS operations instead of System and Pthread calls:

Process Details for Pid: 1007854  
 Process Name: nfsd  
 252 Tids for this Pid: 2089213 2085115 2081017 2076919 2072821 2068723  
 2040037 2035939 2031841 2027743 2023645 2019547

```

2015449 2011351 2007253 2003155 1999057 1994959
...(lines omitted)...
454909 434421 413931 397359 364797 352459
340185 331969 315411 303283 299237 266405

```

```

Total Kernel Time (ms): 380.237018
Total Operation Time (ms): 2891.971209

```

Process NFS Calls Summary

Count	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	% Tot Time	Total ETime (msec)	Avg ETime (msec)	Min ETime (msec)	Max ETime (msec)	% Tot ETime	% Tot Count	Opcode
2254	1018.3621	0.4518	0.3639	0.9966	35.34	1800.5708	0.7988	0.4204	16.6283	2.84	9.45	RFS3_READDIRPLUS
6647	456.1029	0.0686	0.0376	0.6267	15.83	9267.7256	1.3943	0.0376	304.9501	14.63	27.88	RFS3_LOOKUP
1993	321.4973	0.1613	0.0781	0.6428	11.16	3006.1774	1.5084	0.0781	121.8822	4.75	8.36	RFS3_WRITE
4409	314.3122	0.0713	0.0425	0.6139	10.91	14052.7567	3.1873	0.0425	313.2698	22.19	18.49	RFS3_READ
1001	177.9891	0.1778	0.0903	8.7271	6.18	23187.1693	23.1640	0.7657	298.0521	36.61	4.20	RFS3_COMMIT
2694	147.1680	0.0546	0.0348	0.5517	5.11	1474.4267	0.5473	0.0348	25.9402	2.33	11.30	RFS3_GETATTR
495	102.0142	0.2061	0.1837	0.7000	3.54	185.8549	0.3755	0.1895	6.1340	0.29	2.08	RFS3_READDIR
1702	85.8328	0.0504	0.0339	0.5793	2.98	146.4281	0.0860	0.0339	5.7539	0.23	7.14	RFS3_READLINK
1552	78.1015	0.0503	0.0367	0.5513	2.71	153.5844	0.0990	0.0367	7.5125	0.24	6.51	RFS3_ACCESS
186	64.4498	0.3465	0.2194	0.7895	2.24	4201.0235	22.5861	1.0235	117.5351	6.63	0.78	RFS3_CREATE
208	56.8876	0.2735	0.1928	0.7351	1.97	4245.4378	20.4108	0.9015	181.0121	6.70	0.87	RFS3_REMOVE
235	33.3158	0.1418	0.0890	0.3312	1.16	1579.4557	6.7211	0.0890	56.0876	2.49	0.99	RFS3_SETATTR
190	13.3856	0.0705	0.0473	0.5495	0.46	19.3971	0.1021	0.0473	0.6827	0.03	0.80	RFS3_FSSTAT
275	12.4504	0.0453	0.0343	0.0561	0.43	16.6542	0.0606	0.0343	0.2357	0.03	1.15	RFS3_FSINFO
23841	2881.8692	0.1209				63336.6621	2.6566					NFS V3 TOTAL
55	1.0983	0.0200	0.0164	0.0258	100.00	0.7434	0.0135	0.0115	0.0194	10.00	10.00	NFS4_ATTRCACHE
55	1.0983	0.0200				0.7434	0.0135					NFS V4 CLIENT TOTAL

Pending NFS Calls Summary

Accumulated Time (msec)	Accumulated ETime (msec)	Sequence Number	Tid
0.1812	48.1456	1039026977	2089213
0.0188	14.8878	1038285324	2085115
0.0484	2.7123	1039220089	2081017
0.1070	49.5471	1039103658	2072821
0.0953	58.8009	1038453491	2035939
0.0533	62.9266	1039037391	2031841
0.1195	14.6817	1038686320	2019547
0.2063	37.1826	1039164331	2015449
0.0140	6.0718	1039260848	2011351
0.0671	8.8971	NFS4_WRITE	2012896

The following information is included in the process detailed report:

Item	Descriptor
Total Application Time (ms)	The amount of time, expressed in milliseconds, that the process spent in application mode.
Total System Call Time (ms)	The amount of time, expressed in milliseconds, that the process spent in system call mode.

The following information is included in the application time details report:

Item	Descriptor
Total Pthread Call Time	The amount of time, expressed in milliseconds, that the process spent in traced pthread library calls.
Total Pthread Dispatch Time	The amount of time, expressed in milliseconds, that the process spent in libpthreads dispatch code.
Total Pthread Idle Dispatch Time	The amount of time, expressed in milliseconds, that the process spent in libpthreads <code>vp_sleep</code> code.
Total Other Time	The amount of time, expressed in milliseconds, that the process spent in non-traced user mode code.
Total number of pthread dispatches	The total number of times a pthread belonging to the process was dispatched by the libpthreads dispatcher.
Total number of pthread idle dispatches	The total number of times a thread belonging to the process was in the libpthreads <code>vp_sleep</code> code.

The following summary information is included in the report:

Item	Descriptor
<b>Process System Calls Summary</b>	A system call summary for the process; this has the same fields as the global System Call Summary. It also includes elapsed time information if the <b>-e</b> flag is specified and error information if the <b>-s</b> flag is specified.
<b>Pending System Calls Summary</b>	If the process was executing a system call at the end of the trace, a pending system call summary will be printed. This has the Accumulated Time and Supervisor Call (SVC Address) fields. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Process Hypervisor Calls Summary</b>	A summary of the hypervisor calls for the process; this has the same fields as the global Hypervisor Calls Summary. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pending Hypervisor Calls Summary</b>	If the process was executing a hypervisor call at the end of the trace, a pending hypervisor call summary will be printed. This has the Accumulated Time and Hypervisor Call fields. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Process NFS Calls Summary</b>	An NFS call summary for the process. This has the same fields as the global System NFS Call Summary. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pending NFS Calls Summary</b>	If the process was executing an NFS call at the end of the trace, a pending NFS call summary will be printed. This has the <b>Accumulated Time</b> and <b>Sequence Number</b> or, in the case of NFS V4, <b>Opcode</b> , fields. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pthread Calls Summary</b>	A summary of the pthread calls for the process. This has the same fields as the global pthread Calls Summary. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pending Pthread Calls Summary</b>	If the process was executing pthread library calls at the end of the trace, a pending pthread call summary will be printed. This has the Accumulated Time and Pthread Routine fields. It also includes elapsed time information if the <b>-e</b> flag is specified.

### Reports generated with the **-P** flag:

The report generated with the **-P** flag includes the data shown in the default report and also includes a detailed report on pthread status.

The report includes the following:

- The amount of time the pthread was in application and system call mode
- The application time details
- The system calls and pthread calls that the pthread made
- The system calls and pthread calls that were pending at the end of the trace
- The processor affinity
- The number of times the pthread was dispatched
- To which CPU(s) the thread was dispatched
- The thread affinity
- The number of times that the pthread was dispatched
- To which kernel thread(s) the pthread was dispatched

The report also includes dispatch wait time and details of interrupts.

The following is an example of a report generated with the **-P** flag:

```
Report for Pthread Id: 1 (hex 1) Pid: 245962 (hex 3c0ca)
Process Name: ./pth32
```

```
-----
Total Application Time      (ms):  3.919091
Total System Call Time     (ms):  8.303156
Total Hypervisor Call Time (ms):  0.000000
```

```
Application time details:
  Total Pthread Call Time (ms):  1.139372
  Total Pthread Dispatch Time (ms):  0.115822
  Total Pthread Idle Dispatch Time (ms):  0.036630
  Total Other Time (ms):  2.627266
```

Pthread System Calls Summary

```

-----
Count    Total Time  Avg Time  Min Time  Max Time  SVC (Address)
=====  =====  =====  =====  =====  =====
1        3.3898      3.3898   3.3898   3.3898   _exit(409e50)
61       0.8138      0.0133   0.0089   0.0254   kread(5ffd78)
11       0.4616      0.0420   0.0262   0.0835   thread_create(407360)
22       0.2570      0.0117   0.0062   0.0373   mprotect(6d5bd8)
12       0.2126      0.0177   0.0100   0.0324   thread_setstate(40a660)
115      0.1875      0.0016   0.0012   0.0037   klseek(5ffe38)
12       0.1061      0.0088   0.0032   0.0134   sbrk(6d4f90)
23       0.0803      0.0035   0.0018   0.0072   trcgent(4078d8)

```

...(lines omitted)...

#### Pending System Calls Summary

```

-----
Accumulated  SVC (Address)
Time (msec)
=====
0.0141  thread_tsleep(40a4f8)

```

#### Pthread Calls Summary

```

-----
Count    Total Time  % sys  Avg Time  Min Time  Max Time  Pthread Routine
=====  =====  =====  =====  =====  =====  =====
11       0.9545      0.01%  0.0868   0.0457   0.1833   pthread_create
8        0.0725      0.00%  0.0091   0.0064   0.0205   pthread_join
1        0.0553      0.00%  0.0553   0.0553   pthread_detach
1        0.0341      0.00%  0.0341   0.0341   pthread_cancel
1        0.0229      0.00%  0.0229   0.0229   pthread_kill

```

#### Pending Pthread Calls Summary

```

-----
Accumulated  Pthread Routine
Time (msec)
=====
0.0025  pthread_join

```

processor affinity: 0.600000

Processor Dispatch Histogram for pthread (CPUid : times\_dispatched):

CPU 0 : 4  
CPU 1 : 1

total number of dispatches : 5  
avg. dispatch wait time (ms): 798.449725

Thread affinity: 0.333333

Thread Dispatch Histogram for pthread (thread id : number dispatches):

Thread id 688279 : 1  
Thread id 856237 : 1  
Thread id 1007759 : 1

total number of pthread dispatches: 3  
avg. dispatch wait time (ms): 1330.749542

Data on Interrupts that Occurred while Pthread was Running  
Type of Interrupt            Count

```

=====
Data Access Page Faults (DSI): 452

```

```

Instr. Fetch Page Faults (ISI): 0
  Align. Error Interrupts: 0
  IO (external) Interrupts: 0
  Program Check Interrupts: 0
  FP Unavailable Interrupts: 0
  FP Imprecise Interrupts: 0
  RunMode Interrupts: 0
  Decrementer Interrupts: 2
  Queued (Soft level) Interrupts: 0

```

The information in the pthreads summary report includes the following:

Item	Descriptor
<b>Pthread ID</b>	The Pthread ID of the thread.
<b>Process ID</b>	The Process ID that the pthread belongs to.
<b>Process Name</b>	The process name, if known, that the pthread belongs to.
<b>Total Application Time (ms)</b>	The amount of time, expressed in milliseconds, that the pthread spent in application mode.
<b>Total System Call Time (ms)</b>	The amount of time, expressed in milliseconds, that the pthread spent in system call mode.

The information in the application time details report includes the following:

Item	Descriptor
<b>Total Pthread Call Time</b>	The amount of time, expressed in milliseconds, that the pthread spent in traced pthread library calls.
<b>Total Pthread Dispatch Time</b>	The amount of time, expressed in milliseconds, that the pthread spent in libpthreads dispatch code.
<b>Total Pthread Idle Dispatch Time</b>	The amount of time, expressed in milliseconds, that the pthread spent in libpthreads <b>vp_sleep</b> code.
<b>Total Other Time</b>	The amount of time, expressed in milliseconds, that the pthread spent in non-traced user mode code.
<b>Total number of pthread dispatches</b>	The total number of times a pthread belonging to the process was dispatched by the libpthreads dispatcher.
<b>Total number of pthread idle dispatches</b>	The total number of times a thread belonging to the process was in the libpthreads <b>vp_sleep</b> code.

The summary information in the report includes the following:

Item	Descriptor
<b>Pthread System Calls Summary</b>	A system call summary for the pthread; this has the same fields as the global System Call Summary. It also includes elapsed time information if the <b>-e</b> flag is specified and error information if the <b>-s</b> flag is specified.
<b>Pending System Calls Summary</b>	If the pthread was executing a system call at the end of the trace, a pending system call summary will be printed. This has the Accumulated Time and Supervisor Call (SVC Address) fields. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pthread Hypervisor Calls Summary</b>	A summary of the hypervisor calls for the pthread. This has the same fields as the global hypervisor calls summary. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pending Hypervisor Calls Summary</b>	If the pthread was executing a hypervisor call at the end of the trace, a pending hypervisor calls summary will be printed. This has the Accumulated Time and Hypervisor Call fields. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pthread Calls Summary</b>	A summary of the pthread library calls for the pthread. This has the same fields as the global pthread Calls Summary. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pending Pthread Calls Summary</b>	If the pthread was executing a pthread library call at the end of the trace, a pending pthread call summary will be printed. This has the Accumulated Time and Pthread Routine fields. It also includes elapsed time information if the <b>-e</b> flag is specified.

The pthreads summary report also includes the following information:

Item	Descriptor
processor affinity	Probability that for any dispatch of the pthread, the pthread was dispatched to the same processor on which it last executed.
Processor Dispatch Histogram for pthread	The number of times that the pthread was dispatched to each CPU in the system.
avg. dispatch wait time	The average elapsed time for the pthread from being undischatched and its next dispatch.
Thread affinity	The probability that for any dispatch of the pthread, the pthread was dispatched to the same kernel thread on which it last executed
Thread Dispatch Histogram for pthread	The number of times that the pthread was dispatched to each kernel thread in the process.
total number of pthread dispatches	The total number of times the pthread was dispatched by the libpthreads dispatcher.
Data on Interrupts that occurred while Pthread was Running	The number of times each type of FLIH occurred while the pthread was executing.

---

## Simple performance lock analysis tool (splat)

The Simple Performance Lock Analysis Tool (splat) is a software tool that generates reports on the use of synchronization locks. These include the simple and complex locks provided by the AIX kernel, as well as user-level mutexes, read and write locks, and condition variables provided by the **PThread** library.

The **splat** tool is not currently equipped to analyze the behavior of the Virtual Memory Manager (VMM) and PMAP locks used in the AIX kernel.

### splat command syntax

Review the **splat** command syntax, flags, and parameters.

The syntax for the **splat** command is as follows:

```
splat [-i file] [-n file] [-o file] [-d [bfta]] [-l address][-c class] [-s [acelmsS]] [-C#] [-S#] [-t start] [-T stop] [-p]
```

```
splat -h [topic]
```

```
splat -j
```

### Flags

The flags of the **splat** command are:

Item	Descriptor
-i <i>inputfile</i>	Specifies the &SWsym.AIX; trace log file input.
-n <i>namefile</i>	Specifies the file containing output of the <b>gensyms</b> command.
-o <i>outputfile</i>	Specifies an output file (default is <b>stdout</b> ).
-d <i>detail</i>	Specifies the level of detail of the report.
-c <i>class</i>	Specifies class of locks to be reported.
-l <i>address</i>	Specifies the address for which activity on the lock will be reported.
-s <i>criteria</i>	Specifies the sort order of the lock, function, and thread.
-C <i>CPUs</i>	Specifies the number of processors on the MP system that the trace was drawn from. The default is 1. This value is overridden if more processors are observed to be reported in the trace.
-S <i>count</i>	Specifies the number of items to report on for each section. The default is 10. This gives the number of locks to report in the Lock Summary and Lock Detail reports, as well as the number of functions to report in the Function Detail and threads to report in the Thread detail (the -s option specifies how the most significant locks, threads, and functions are selected).
-t <i>starttime</i>	Overrides the start time from the first event recorded in the trace. This flag forces the analysis to begin an event that occurs <i>starttime</i> seconds after the first event in the trace.

The flags of the **splat** command are:

Item	Descriptor
<b>-T</b> <i>stoptime</i>	Overrides the stop time from the last event recorded in the trace. This flag forces the analysis to end with an event that occurs <i>stoptime</i> seconds after the first event in the trace.
<b>-j</b>	Prints the list of IDs of the trace hooks used by the <b>splat</b> command.
<b>-h</b> <i>topic</i>	Prints a help message on usage or a specific topic.
<b>-p</b>	Specifies the use of the PURR register to calculate CPU times.

## Parameters

The parameters associated with the **splat** command are:

Item	Descriptor
<b>inputfile</b>	The AIX trace log file input. This file can be a merge trace file generated using the <b>trcrpt -r</b> command.
<b>namefile</b>	File containing output of the <b>gensyms</b> command.
<b>outputfile</b>	File to write reports to.
<b>detail</b>	The detail level of the report, it can be one of the following: <b>basic</b> Lock summary plus lock detail (the default) <b>function</b> Basic plus function detail <b>thread</b> Basic plus thread detail <b>all</b> Basic plus function plus thread detail
<b>class</b>	Activity classes, which is a decimal value found in the <b>/usr/include/sys/lockname.h</b> file.
<b>address</b>	The address to be reported, given in hexadecimal.
<b>criteria</b>	Order the lock, function, and thread reports by the following criteria: <b>a</b> Acquisitions <b>c</b> Percent processor time held <b>e</b> Percent elapsed time held <b>l</b> Lock address, function address, or thread ID <b>m</b> Miss rate <b>s</b> Spin count <b>S</b> Percent processor spin hold time (the default)
<b>CPUs</b>	The number of processors on the MP system that the trace was drawn from. The default is 1. This value is overridden if more processors are observed to be reported in the trace.
<b>count</b>	The number of locks to report in the Lock Summary and Lock Detail reports, as well as the number of functions to report in the Function Detail and threads to report in the Thread detail. (The <b>-s</b> option specifies how the most significant locks, threads, and functions are selected).
<b>starttime</b>	The number of seconds after the first event recorded in the trace that the reporting starts.
<b>stoptime</b>	The number of seconds after the first event recorded in the trace that the reporting stops.
<b>topic</b>	Help topics, which are: all overview input names reports sorting

## Measurement and sampling

The **splat** tool takes as input an AIX trace log file or (for an SMP trace) a set of log files, and preferably a **names** file produced by the **gennames** or **gensyms** command.

The procedure for generating these files is shown in the **trace** section. When you run **trace**, you will usually use the flag **-J splat** to capture the events analyzed by **splat** (or without the **-J** flag, to capture all events). The significant trace hooks are shown in the following table:

Hook ID	Event name	Event explanation
106	HKWD_KERN_DISPATCH	The thread is dispatched from the run queue to a processor.
10C	HKWD_KERN_IDLE	The idle process is been dispatched.
10E	HKWD_KERN_RELOCK	One thread is suspended while another is dispatched; the ownership of a <b>RunQ</b> lock is transferred from the first to the second.
112	HKWD_KERN_LOCK	The thread attempts to secure a kernel lock; the sub-hook shows what happened.
113	HKWD_KERN_UNLOCK	A kernel lock is released.
134	HKWD_SYSC_EXECVE	An exec supervisor call (SVC) has been issued by a (forked) process.
139	HKWD_SYSC_FORK	A fork SVC has been issued by a process.
419	HKWD_CPU_PREEMPT	A process has been preempted.
465	HKWD_SYSC_CRTHREAD	A thread_create SVC has been issued by a process.
46D	HKWD_KERN_WAITLOCK	The thread is enqueued to wait on a kernel lock.
46E	HKWD_KERN_WAKEUPLOCK	A thread has been awakened.
606	HKWD_PTHREAD_COND	Operations on a Condition Variable.
607	HKWD_PTHREAD_MUTEX	Operations on a Mutex.
608	HKWD_PTHREAD_RWLOCK	Operations on a Read/Write Lock.
609	HKWD_PTHREAD_GENERAL	Operations on a <b>PThread</b> .

## Execution, trace, and analysis Intervals

In some cases, you can use the **trace** tool to capture the entire execution of a workload, while in other cases you will capture only an interval of the execution.

The *execution interval* is the entire time that a workload runs. This interval is arbitrarily long for server workloads that run continuously. The *trace interval* is the time actually captured in the trace log file by **trace**. The length of this trace interval is limited by how large a trace log file will fit on the file system.

In contrast, the analysis interval is the portion of the trace interval that is analyzed by the **splat** command. The **-t** and **-T** flags indicate to the **splat** command to start and finish analysis some number of seconds after the first event in the trace. By default, the **splat** command analyzes the entire trace, so this analysis interval is the same as the trace interval.

**Note:** As an optimization, the **splat** command stops reading the trace when it finishes its analysis, so it indicates that the trace and analysis intervals end at the same time even if they do not.

To most accurately estimate the effect of lock activity on the computation, you will usually want to capture the longest trace interval that you can, and analyze that entire interval with the **splat** command. The **-t** and **-T** flags are usually used for debugging purposes to study the behavior of the **splat** command across a few events in the trace.

As a rule, either use large buffers when collecting a trace, or limit the captured events to the ones you need to run the **splat** command.

## Trace discontinuities

The **splat** command uses the events in the trace to reconstruct the activities of threads and locks in the original system.

If part of the trace is missing, it is because one of the following situations exists:

- Tracing was stopped at one point and restarted at a later point.
- One processor fills its trace buffer and stops tracing, while other processors continue tracing.
- Event records in the trace buffer were overwritten before they could be copied into the trace log file.

In any of the above cases, the **splat** command will not be able to correctly analyze all the events across the trace interval. The policy of **splat** is to finish its analysis at the first point of discontinuity in the trace, issue a warning message, and generate its report. In the first two cases, the message is as follows:

```
TRACE OFF record read at 0.567201 seconds. One or more of the CPUs has
stopped tracing. You might want to generate a longer trace using larger
buffers and re-run splat.
```

In the third case, the message is as follows:

```
TRACEBUFFER WRAPAROUND record read at 0.567201 seconds. The input trace
has some records missing; splat finishes analyzing at this point. You
might want to re-generate the trace using larger buffers and re-run splat.
```

Some versions of the AIX kernel or **PThread** library might be incompletely instrumented, so the traces will be missing events. The **splat** command might not provide correct results in this case.

## Address-to-Name resolution in the splat command

The lock instrumentation in the kernel and **PThread** library is what captures the information for each lock event.

Data addresses are used to identify locks; instruction addresses are used to identify the point of execution. These addresses are captured in the event records in the trace, and used by the **splat** command to identify the locks and the functions that operate on them.

However, these addresses are not of much use to the programmer, who would rather know the names of the lock and function declarations so that they can be located in the program source files. The conversion of names to addresses is determined by the compiler and loader, and can be captured in a file using the **gensyms** command. The **gensyms** command also captures the contents of the **/usr/include/sys/lockname.h** file, which declares classes of kernel locks.

The **gensyms** output file is passed to the **splat** command with the **-n** flag. When **splat** reports on a kernel lock, it provides the best identification that it can.

Kernel locks that are declared are resolved by name. Locks that are created dynamically are identified by class if their class name is given when they are created. The **libpthreads.a** instrumentation is not equipped to capture names or classes of **PThread** synchronizers, so they are always identified by address only.

## Examples of generated reports

The report generated by the **splat** command consists of an execution summary, a gross lock summary, and a per-lock summary, followed by a list of lock detail reports that optionally includes a function detail or a thread detail report.

### Execution summary

The execution summary report is generated by default when you use the **splat** command.

The following example shows a sample of the execution summary.

```
*****
splat Cmd: splat -p -sa -da -S100 -i trace.cooked -n gensyms -o splat.out

Trace Cmd:  trace -C all -aj 600,603,605,606,607,608,609 -T 20000000 -L 200000000 -o CONDVAR.raw
Trace Host:  darkwing (0054451E4C00) AIX 5.2
Trace Date:  Thu Sep 27 11:26:16 2002
```

PURR was used to calculate CPU times.

```
Elapsed Real Time:      0.098167
Number of CPUs Traced:  1          (Observed):0
```

Cumulative CPU Time: 0.098167

		start	stop
		-----	-----
trace interval	(absolute tics)	967436752	969072535
	(relative tics)	0	1635783
	(absolute secs)	58.057947	58.156114
	(relative secs)	0.000000	0.098167
analysis interval	(absolute tics)	967436752	969072535
	(trace-relative tics)	0	1635783
	(self-relative tics)	0	1635783
	(absolute secs)	58.057947	58.156114
	(trace-relative secs)	0.000000	0.098167
	(self-relative secs)	0.000000	0.098167

\*\*\*\*\*

From the example above, you can see that the execution summary consists of the following elements:

- The **splat** version and build information, disclaimer, and copyright notice.
- The command used to run **splat**.
- The **trace** command used to collect the trace.
- The host on which the trace was taken.
- The date that the trace was taken.
- A sentence specifying whether the PURR register was used to calculate CPU times.
- The real-time duration of the trace, expressed in seconds.
- The maximum number of processors that were observed in the trace (the number specified in the trace conditions information, and the number specified on the **splat** command line).
- The cumulative processor time, equal to the duration of the trace in seconds times the number of processors that represents the total number of seconds of processor time consumed.
- A table containing the start and stop times of the trace interval, measured in tics and seconds, as absolute timestamps, from the trace records, as well as relative to the first event in the trace
- The start and stop times of the analysis interval, measured in tics and seconds, as absolute timestamps, as well as relative to the beginning of the trace interval and the beginning of the analysis interval.

## Gross lock summary

The gross lock summary report is generated by default when you use the **splat** command.

The following example shows a sample of the gross lock summary report.

```
*****
Total      Unique   Acquisitions   Acq. or Passes   Total System
-----      -         (or Passes)   per Second       Spin   Time
AIX (all) Locks:    523      523          1323045          72175.7768      0.003986
                RunQ:      2         2             487178          26576.9121      0.000000
                Simple:  480      480          824898          45000.4754      0.003986
  Transformed:    22         18             234             352.3452
    Krlock:       50         21             76876           32.6548         0.000458
    Complex:     41         41             10969            598.3894         0.000000
  PThread CondVar: 7         6             160623           8762.4305         0.000000
    Mutex:      128       116          1927771          105165.2585      10.280745 *
    RWLock:      0         0              0                0.0000         0.000000

( spin time goal )
*****
```

The gross lock summary report table consists of the following columns:

<b>Item</b>	<b>Descriptor</b>
<b>Total</b>	The number of AIX Kernel locks, followed by the number of each type of AIX Kernel lock; RunQ, Simple, and Complex. Under some conditions, this will be larger than the sum of the numbers of RunQ, Simple, and Complex locks because we might not observe enough activity on a lock to differentiate its type. This is followed by the number of PThread condition-variables, the number of PThread Mutexes, and the number of PThread Read/Write. The Transformed value represents the number of different simple locks responsible for the allocation (and liberation) of at least one Klock. In this case, two simple locks will be different if they are not created at the same time or they do not have the same address.
<b>Unique Addresses</b>	The number of unique addresses observed for each synchronizer type. Under some conditions, a lock will be destroyed and re-created at the same address; the <b>splat</b> command produces a separate lock detail report for each instance because the usage might be different. The Transformed value represents the number of different simple locks responsible for the allocation (and liberation) of at least one Klock. In this case, simple locks created at different times but with the same address increment the counter only once.
<b>Acquisitions (or Passes)</b>	For locks, the total number of times acquired during the analysis interval; for PThread condition-variables, the total number of times the condition passed during the analysis interval. The Transformed value represents the number of acquisitions made by a thread holding the corresponding Klock.
<b>Acq. or Passes (per Second)</b>	Acquisitions or passes per second, which is the total number of acquisitions or passes divided by the elapsed real time of the trace. The Transformed value represents the acquisition rate for the acquisitions made by threads holding the corresponding klock.
<b>% Total System spin Time</b>	The cumulative time spent spinning on each synchronizer type, divided by the cumulative processor time, times 100 percent. The general goal is to spin for less than 10 percent of the processor time; a message to this effect is printed at the bottom of the table. If any of the entries in this column exceed 10 percent, they are marked with an asterisk (*). For simple locks, the spin time of the Klocks is included.

## Per-lock summary

The pre-locl summary report is generated by default when you use the **splat** command.

The following example shows a sample of the per-lock summary report.

```
*****
100 max entries, Summary sorted by Acquisitions:
```

Lock Names, Class, or Address	T p e	Acqui- sitions Passes	Wait or Trans- form	%Miss	%Total	Locks or Passes / CSec	Percent Real CPU	Holdtime Real Elapse	Comb Spin	
*****	*	*****	****	*****	*****	*****	*****	*****	*****	
PROC_INT_CLASS.0003	Q	486490	0	0	0.0000	36.7705	26539.380	5.3532	100.000	0.0000
THREAD_LOCK_CLASS.0012	S	323277	0	9468	0.0000	24.4343	17635.658	6.8216	6.8216	0.0000
THREAD_LOCK_CLASS.0118	D	323094	0	4568	0.0000	24.4205	17625.674	6.7887	6.7887	0.0000
ELIST_CLASS.003C	S	80453	0	201	0.0000	6.0809	4388.934	1.0564	1.0564	0.0000
ELIST_CLASS.0044	S	80419	0	110	0.0000	6.0783	4387.080	1.1299	1.1299	0.0000
tod_lock	C	10229	0	0	0.0000	0.7731	558.020	0.2212	0.2212	0.0000
LDATA_CONTROL_LOCK.0000	D	1833	0	10	0.0000	0.1385	99.995	0.0204	0.0204	0.0000
U_TIMER_CLASS.0014	S	1514	0	23	0.0000	0.1144	82.593	0.0536	0.0536	0.0000

( ... lines omitted ... )

000000002FF22B70	L	368838	0	N/A	0.0000	100.000	9622.964	99.9865	99.9865	0.0000
00000000F00C3D74	M	160625	0	0	0.0000	14.2831	8762.540	99.7702	99.7702	0.0000
00000000200017E8	M	160625	175	0	0.1088	14.2831	8762.540	42.9371	42.9371	0.1487
0000000020001820	V	160623	0	624	0.0000	100.000	1271.728	N/A	N/A	N/A
00000000F00C3750	M	37	0	0	0.0000	0.0033	2.018	0.0037	0.0037	0.0000
00000000F00C3800	M	30	0	0	0.0000	0.0027	1.637	0.0698	0.0698	0.0000

( ... lines omitted ... )

```
*****
```

The first line indicates the maximum number of locks to report (100 in this case, but we show only 14 of the entries here) as specified by the **-S 100** flag. The report also indicates that the entries are sorted by the total number of acquisitions or passes, as specified by the **-sa** flag. The various Kernel locks and PThread

synchronizers are treated as two separate lists in this report, so the report would produce the top 100 Kernel locks sorted by acquisitions, followed by the top 100 **PThread** synchronizers sorted by acquisitions or passes.

The per-lock summary table consists of the following columns:

<b>Item</b>	<b>Descriptor</b>
<b>Lock Names, Class, or Address</b>	The name, class, or address of the lock, depending on whether the <b>splat</b> command could map the address from a name file.
<b>Type</b>	The type of the lock, identified by one of the following letters: <b>Q</b> A RunQ lock <b>S</b> An enabled simple kernel lock <b>D</b> A disabled simple kernel lock <b>C</b> A complex kernel lock <b>M</b> A <b>PThread</b> mutex <b>V</b> A <b>PThread</b> condition-variable <b>L</b> A <b>PThread</b> read/write lock
<b>Acquisitions or Passes</b>	The number of times that the lock was acquired or the condition passed, during the analysis interval.
<b>Spins</b>	The number of times that the lock (or condition-variable) was spun on during the analysis interval.
<b>Wait or Transform</b>	The number of times that a thread was driven into a wait state for that lock or condition-variable during the analysis interval. When Klocks are enabled, a simple lock never enters the wait state and this value represents the number of Klocks that the simple lock has allocated, which is the transform count of simple locks.
<b>%Miss</b>	The percentage of access attempts that resulted in a spin as opposed to a successful acquisition or pass.
<b>%Total</b>	The percentage of all acquisitions that were made to this lock, out of all acquisitions to all locks of this type. All AIX locks (RunQ, simple, and complex) are treated as being the same type for this calculation. The <b>PThread</b> synchronizers mutex, condition-variable, and read/write lock are all distinct types.
<b>Locks or Passes / CSec</b>	The number of times that the lock (or condition-variable) was acquired (or passed) divided by the cumulative processor time. This is a measure of the acquisition frequency of the lock.
<b>Percent Holdtime</b>	
<b>Real CPU</b>	The percentage of the cumulative processor time that the lock was held by any thread at all, whether running or suspended. Note that this definition is not applicable to condition-variables because they are not held.
<b>Real Elapse</b>	The percentage of the elapsed real time that the lock was held by any thread at all, whether running or suspended. Note that this definition is not applicable to condition-variables because they are not held.
<b>Comb Spin</b>	The percentage of the cumulative processor time that executing threads spent spinning on the lock. The <b>PThreads</b> library uses waiting for condition-variables, so there is no time actually spent spinning.

## AIX kernel lock details

By default, the **splat** command prints a lock detail report for each entry in the summary report. The AIX Kernel locks can be either simple or complex.

The RunQ lock is a special case of the simple lock, although its pattern of usage will differ markedly from other lock types. The **splat** command distinguishes it from the other simple locks to ease its analysis.

### Disabled simple and RunQ lock details:

In an AIX SIMPLE Lock report, the first line starts with either [AIX SIMPLE Lock] or [AIX RunQ lock].



Item	Descriptor
<b>Percent Held</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>Real CPU</b> The percentage of the cumulative processor time that the lock was held by an executing thread.</li> <li><b>Real Elapsed</b> The percentage of the elapsed real time that the lock was held by any thread at all, either running or suspended.</li> <li><b>Comb(ined) Spin</b> The percentage of the cumulative processor time that running threads spent spinning while trying to acquire this lock.</li> <li><b>Real Wait</b> The percentage of elapsed real time that any thread was waiting to acquire this lock. If two or more threads are waiting simultaneously, this wait time will only be charged once. To determine how many threads were waiting simultaneously, look at the WaitQ Depth statistics.</li> </ul>
<b>Total Acquisitions</b>	The number of times that the lock was acquired in the analysis interval. This includes successful <b>simple_lock_try</b> calls.
<b>Acq. holding krlock</b>	The number of acquisitions made by threads holding a Krlock.
<b>Transform count</b>	The number of Krlocks that have been used (allocated and freed) by the simple lock.
<b>SpinQ</b>	The minimum, maximum, and average number of threads spinning on the lock, whether executing or suspended, across the analysis interval.
<b>Krlocks SpinQ</b>	The minimum, maximum, and average number of threads spinning on a Krlock allocated by the simple lock, across the analysis interval.
<b>PROD</b>	The associated Krlocks <b>prod</b> calls count.
<b>CONFER SELF</b>	The confer to self calls count for the simple lock and the associated Krlocks.
<b>CONFER TARGET</b>	The confer to target calls count for the simple lock and the associated Krlocks.
<b>CONFER ALL</b>	The confer to all calls count for the simple lock and the associated Krlocks.
<b>HANDOFF</b>	The associated Krlocks <b>handoff</b> calls count.

The Lock Activity with Interrupts Enabled (milliseconds) and Lock Activity with Interrupts Disabled (milliseconds) sections contain information on the time that each lock state is used by the locks.

The states that a thread can be in (with respect to a given simple or complex lock) are as follows:

Item	Descriptor
<b>(no lock reference)</b>	The thread is running, does not hold this lock, and is not attempting to acquire this lock.
<b>LOCK</b>	The thread has successfully acquired the lock and is currently executing.
<b>LOCK with KRLOCK</b>	The thread has successfully acquired the lock, while holding the associated Krlock, and is currently executing.
<b>SPIN</b>	The thread is executing and unsuccessfully attempting to acquire the lock.
<b>KRLOCK LOCK</b>	The thread has successfully acquired the associated Krlock and is currently executing.
<b>KRLOCK SPIN</b>	The thread is executing and unsuccessfully attempting to acquire the associated Krlock.
<b>TRANSFORM</b>	The thread has successfully allocated a Krlock that it associates itself to and is executing.

The Lock Activity sections of the report measure the intervals of time (in milliseconds) that each thread spends in each of the states for this lock. The columns report the number of times that a thread entered the given state, followed by the maximum, minimum, and average time that a thread spent in the state once entered, followed by the total time that all threads spent in that state. These sections distinguish whether interrupts were enabled or disabled at the time that the thread was in the given state.

A thread can acquire a lock prior to the beginning of the analysis interval and release the lock during the analysis interval. When the **splat** command observes the lock being released, it recognizes that the lock had been held during the analysis interval up to that point and counts the time as part of the state-machine statistics. For this reason, the state-machine statistics might report that the number of times that the lock state was entered might actually be larger than the number of acquisitions of the lock that were observed in the analysis interval.

RunQ locks are used to protect resources in the thread management logic. These locks are acquired a large number of times and are only held briefly each time. A thread need not be executing to acquire or release a RunQ lock. Further, a thread might spin on a RunQ lock, but it will not go into an UNDISP or WAIT state on the lock. You will see a dramatic difference between the statistics for RunQ versus other simple locks.

### Enabled simple lock details:

The Lock Activity sections of the report measure the intervals of time (in milliseconds) that each thread spends in each of the states for this lock. The columns report the number of times that a thread entered the given state, followed by the maximum, minimum, and average time that a thread spent in the state once entered, followed by the total time that all threads spent in that state.

These sections of the report distinguish whether interrupts were enabled or disabled at the time that the thread was in the given state.

The following example is an enabled simple lock detail report:

```
[AIX SIMPLE Lock]                CLASS:    PROC_INT_CLASS.00000004
ADDRESS: 00000000200786C
=====
Type      | Miss Spin  Wait  Busy  |      Secs Held      | Percent Held ( 26.235284s )
Enabled   | Rate Count Count Count | CPU   Elapsed      | Real  Real  Comb Real
          | 0.438 57  2658 12   | 0.022852 0.032960 | 0.04  0.13  0.00  0.00
-----
Total Acquisitions: 2498 | SpinQ  Min  Max  Avg | WaitQ  Min  Max  Avg
                   | Depth 0   1   0   0 | Depth 0   0   0   0
-----
```

#### Lock Activity (mSecs) - Interrupts Enabled

SIMPLE	Count	Minimum	Maximum	Average	Total
LOCK	8027	0.000597	0.022486	0.002847	22.852000
SPIN	45	0.001376	0.008960	0.004738	0.213212
UNDISP	0	0.000000	0.000000	0.000000	0.000000
WAIT	0	0.000000	0.000000	0.000000	0.000000
PREEMPT	4918	0.000811	0.009728	0.001955	9.615807

Function Name	Acqui- sitions	Miss Rate	Spin Count	Wait Count	Busy Count	Percent Held of Total Time				Return Address	Start Address	Offset
						CPU	Elapse	Spin	Wait			
.dispatch	3177	0.63	20	0	0	0.00	0.02	0.00	0.00	000000000039CF4	0000000000000000	00039CF4
.dispatch	6053	0.31	19	0	0	0.03	0.07	0.00	0.00	0000000000398E4	0000000000000000	000398E4
.setrq	3160	0.19	6	0	0	0.01	0.02	0.00	0.00	000000000038E60	0000000000000000	00038E60
.steal_threads	1	0.00	0	0	0	0.00	0.00	0.00	0.00	000000000066A68	0000000000000000	00066A68
.steal_threads	6	0.00	0	0	0	0.00	0.00	0.00	0.00	000000000066CE0	0000000000000000	00066CE0
.dispatch	535	2.19	12	0	12	0.01	0.02	0.00	0.00	000000000039D88	0000000000000000	00039D88
.dispatch	2	0.00	0	0	0	0.00	0.00	0.00	0.00	000000000039D14	0000000000000000	00039D14
.prio_queue	7	0.00	0	0	0	0.00	0.00	0.00	0.00	00000000003B2A4	0000000000000000	0003B2A4
.setnewrq	4	0.00	0	0	0	0.00	0.00	0.00	0.00	000000000038980	0000000000000000	00038980

ThreadID	Acqui- sitions	Miss Rate	Spin Count	Wait Count	Busy Count	Percent Held of Total Time				ProcessID	Process Name
						CPU	Elapse	Spin	Wait		
775	11548	0.34	39	0	0	0.06	0.10	0.00	0.00	774	wait
35619	3	25.00	1	0	0	0.00	0.00	0.00	0.00	18392	sleep
31339	21	4.55	1	0	0	0.00	0.00	0.00	0.00	7364	java
35621	2	0.00	0	0	0	0.00	0.00	0.00	0.00	18394	locktrace

(... lines omitted ...)

The SIMPLE lock report fields are as follows:

<b>Item</b>	<b>Descriptor</b>
<b>Type</b>	If the simple lock was used with interrupts, this field is enabled. Otherwise, this field is disabled.
<b>Total Acquisitions</b>	The number of times that the lock was acquired in the analysis interval. This includes successful <b>simple_lock_try</b> calls.
<b>Miss Rate</b>	The percentage of attempts that failed to acquire the lock.
<b>Spin Count</b>	The number of unsuccessful attempts to acquire the lock.
<b>Wait Count</b>	The number of times that a thread was forced into a suspended wait state, waiting for the lock to come available.
<b>Busy Count</b>	The number of <b>simple_lock_try</b> calls that returned busy.
<b>Seconds Held</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>CPU</b> The total number of processor seconds that the lock was held by an executing thread.</li> <li><b>Elapsed</b> The total number of elapsed seconds that the lock was held by any thread, whether running or suspended.</li> </ul>
<b>Percent Held</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>Real CPU</b> <ul style="list-style-type: none"> <li>The percentage of the cumulative processor time that the lock was held by an executing thread.</li> </ul> </li> <li><b>Real Elapsed</b> <ul style="list-style-type: none"> <li>The percentage of the elapsed real time that the lock was held by any thread at all, either running or suspended.</li> </ul> </li> <li><b>Comb(ined) Spin</b> <ul style="list-style-type: none"> <li>The percentage of the cumulative processor time that running threads spent spinning while trying to acquire this lock.</li> </ul> </li> <li><b>Real Wait</b> <ul style="list-style-type: none"> <li>The percentage of elapsed real time that any thread was waiting to acquire this lock. If two or more threads are waiting simultaneously, this wait time will only be charged once. To determine how many threads were waiting simultaneously, look at the WaitQ Depth statistics.</li> </ul> </li> </ul>
<b>SpinQ</b>	The minimum, maximum, and average number of threads spinning on the lock, whether executing or suspended, across the analysis interval.
<b>WaitQ</b>	The minimum, maximum, and average number of threads waiting on the lock, across the analysis interval.

The Lock Activity with Interrupts Enabled (milliseconds) and Lock Activity with Interrupts Disabled (milliseconds) sections contain information on the time that each lock state is used by the locks.

The states that a thread can be in (with respect to a given simple or complex lock) are as follows:

<b>Item</b>	<b>Descriptor</b>
<b>(no lock reference)</b>	The thread is running, does not hold this lock, and is not attempting to acquire this lock.
<b>LOCK</b>	The thread has successfully acquired the lock and is currently executing.
<b>SPIN</b>	The thread is executing and unsuccessfully attempting to acquire the lock.
<b>UNDISP</b>	The thread has become undispached while unsuccessfully attempting to acquire the lock.
<b>WAIT</b>	The thread has been suspended until the lock comes available. It does not necessarily acquire the lock at that time, but instead returns to a SPIN state.
<b>PREEMPT</b>	The thread is holding this lock and has become undispached.

A thread can acquire a lock prior to the beginning of the analysis interval and release the lock during the analysis interval. When the **splat** command observes the lock being released, it recognizes that the lock had been held during the analysis interval up to that point and counts the time as part of the state-machine statistics. For this reason, the state-machine statistics can report that the number of times that the lock state was entered might actually be larger than the number of acquisitions of the lock that were observed in the analysis interval.

RunQ locks are used to protect resources in the thread management logic. These locks are acquired a large number of times and are only held briefly each time. A thread need not be executing to acquire or

release a RunQ lock. Further, a thread might spin on a RunQ lock, but it will not go into an UNDISP or WAIT state on the lock. You will see a dramatic difference between the statistics for RunQ versus other simple locks.

### Function detail:

The function detail report is obtained by using the **-df** or **-da** options of **splat**.

The columns are defined as follows:

Item	Descriptor
<b>Function Name</b>	The name of the function that acquired or attempted to acquire this lock, if it could be resolved.
<b>Acquisitions</b>	The number of times that the function was able to acquire this lock. For complex lock and read/write, there is a distinction between acquisition for writing, <b>Acquisition Write</b> , and for reading, <b>Acquisition Read</b> .
<b>Miss Rate</b>	The percentage of acquisition attempts that failed.
<b>Spin Count</b>	The number of unsuccessful attempts by the function to acquire this lock. For complex lock and read/write there is a distinction between spin count for writing, <b>Spin Count Write</b> , and for reading, <b>Spin Count Read</b> .
<b>Transf. Count</b>	The number of times that a simple lock has allocated a Klock, while a thread was trying to acquire the simple lock.
<b>Busy Count</b>	The number of times <b>simple_lock_try</b> calls returned busy.
<b>Percent Held of Total Time</b>	Contains the following sub-fields: <ul style="list-style-type: none"> <li><b>CPU</b> Percentage of the cumulative processor time that the lock was held by an executing thread that had acquired the lock through a call to this function.</li> <li><b>Elapse(d)</b> The percentage of the elapsed real time that the lock was held by any thread at all, whether running or suspended, that had acquired the lock through a call to this function.</li> <li><b>Spin</b> The percentage of cumulative processor time that executing threads spent spinning on the lock while trying to acquire the lock through a call to this function.</li> <li><b>Wait</b> The percentage of elapsed real time that executing threads spent waiting for the lock while trying to acquire the lock through a call to this function.</li> </ul>
<b>Return Address</b>	The return address to this calling function, in hexadecimal.
<b>Start Address</b>	The start address to this calling function, in hexadecimal.
<b>Offset</b>	The offset from the function start address to the return address, in hexadecimal.

The functions are ordered by the same sorting criterion as the locks, controlled by the **-s** option of **splat**. Further, the number of functions listed is controlled by the **-S** parameter. The default is the top ten functions.

### Thread Detail:

The Thread Detail report is obtained by using the **-dt** or **-da** options of **splat**.

At any point in time, a single thread is either running or it is not. When a single thread runs, it only runs on one processor. Some of the composite statistics are measured relative to the cumulative processor time when they measure activities that can happen simultaneously on more than one processor, and the magnitude of the measurements can be proportional to the number of processors in the system. In contrast, the thread statistics are generally measured relative to the elapsed real time, which is the amount of time that a single processor spends processing and the amount of time that a single thread spends in an executing or suspended state.

The Thread Detail report columns are defined as follows:

<b>Item</b>	<b>Descriptor</b>
<b>ThreadID</b>	The thread identifier.
<b>Acquisitions</b>	The number of times that this thread acquired the lock.
<b>Miss Rate</b>	The percentage of acquisition attempts by the thread that failed to secure the lock.
<b>Spin Count</b>	The number of unsuccessful attempts by this thread to secure the lock.
<b>Transf. Count</b>	The number of times that a simple lock has allocated a Klock, while a thread was trying to acquire the simple lock.
<b>Wait Count</b>	The number of times that this thread was forced to wait until the lock came available.
<b>Busy Count</b>	The number of <code>simple_lock_try()</code> calls that returned busy.
<b>Percent Held of Total Time</b>	Consists of the following sub-fields: <ul style="list-style-type: none"> <li><b>CPU</b> The percentage of the elapsed real time that this thread executed while holding the lock.</li> <li><b>EI(d)</b> The percentage of the elapsed real time that this thread held the lock while running or suspended.</li> <li><b>Spin</b> The percentage of elapsed real time that this thread executed while spinning on the lock.</li> <li><b>Wait</b> The percentage of elapsed real time that this thread spent waiting on the lock.</li> </ul>
<b>Process ID</b>	The Process identifier (only for simple and complex lock report).
<b>Process Name</b>	Name of the process using the lock (only for simple and complex lock report).

### **Complex-Lock report:**

AIX Complex lock supports recursive locking, where a thread can acquire the lock more than once before releasing it, as well as differentiating between write-locking, which is exclusive, from read-locking, which is not exclusive.

This report begins with [AIX COMPLEX Lock]. Most of the entries are identical to the simple lock report, while some of them are differentiated by read/write/upgrade. For example, the SpinQ and WaitQ statistics include the minimum, maximum, and average number of threads spinning or waiting on the lock. They also include the minimum, maximum, and average number of threads attempting to acquire the lock for reading versus writing. Because an arbitrary number of threads can hold the lock for reading, the report includes the minimum, maximum, and average number of readers in the LockQ that holds the lock.

A thread might hold a lock for writing; this is exclusive and prevents any other thread from securing the lock for reading or for writing. The thread downgrades the lock by simultaneously releasing it for writing and acquiring it for reading; this permits other threads to also acquire the lock for reading. The reverse of this operation is an upgrade; if the thread holds the lock for reading and no other thread holds it as well, the thread simultaneously releases the lock for reading and acquires it for writing. The upgrade operation might require that the thread wait until other threads release their read-locks. The downgrade operation does not.

A thread might acquire the lock to some recursive depth; it must release the lock the same number of times to free it. This is useful in library code where a lock must be secured at each entry-point to the library; a thread will secure the lock once as it enters the library, and internal calls to the library entry-points simply re-secure the lock, and release it when returning from the call. The minimum, maximum, and average recursion depths of any thread holding this lock are reported in the table.

A thread holding a recursive write-lock is not permitted to downgrade it because the downgrade is intended to apply to only the last write-acquisition of the lock, and the prior acquisitions had a real reason to keep the acquisition exclusive. Instead, the lock is marked as being in the downgraded state, which is erased when the this latest acquisition is released or upgraded. A thread holding a recursive read-lock can only upgrade the latest acquisition of the lock, in which case the lock is marked as being upgraded. The thread will have to wait until the lock is released by any other threads holding it for reading. The minimum, maximum, and average recursion-depths of any thread holding this lock in an upgraded or downgraded state are reported in the table.

The Lock Activity report also breaks down the time based on what task the lock is being secured for (reading, writing, or upgrading).

No time is reported to perform a downgrade because this is performed without any contention. The upgrade state is only reported for the case where a recursive read-lock is upgraded. Otherwise, the thread activity is measured as releasing a read-lock and acquiring a write-lock.

The function and thread details also break down the acquisition, spin, and wait counts by whether the lock is to be acquired for reading or writing.

## PThread synchronizer reports

By default, the `splat` command prints a detailed report for each **PThread** entry in the summary report. The **PThread** synchronizers are of the following types: mutex, read/write lock, and condition-variable.

The mutex and read/write lock are related to the AIX complex lock. You can view the similarities in the lock detail reports. The condition-variable differs significantly from a lock, and this is reflected in the report details.

The **PThread** library instrumentation does not provide names or classes of synchronizers, so the addresses are the only way we have to identify them. Under certain conditions, the instrumentation can capture the return addresses of the function call stack, and these addresses are used with the **gensyms** output to identify the call chains when these synchronizers are created. The creation and deletion times of the synchronizer can sometimes be determined as well, along with the ID of the **PThread** that created them.

### Mutex reports:

The **PThread** mutex is similar to an AIX simple lock in that only one thread can acquire the lock, and is like an AIX complex lock in that it can be held recursively.

```
[PThread MUTEX] ADDRESS: 00000000F0154CD0
Parent Thread: 0000000000000001 creation time: 26.232305
Pid: 18396 Process Name: trcstop
Creation call-chain =====
00000000D268606C .pthread_mutex_lock
00000000D268EB88 .pthread_once
00000000D01FE588 .__libc_init
00000000D01EB2FC .__libc_inline_callbacks
00000000D01EB280 .__libc_declare_data_functions
00000000D269F960 .__pth_init_libc
00000000D268A2B4 .pthread_init
00000000D01EAC08 .__modinit
000000001000014C .__start
=====
Acqui- | Miss Spin | Wait | Busy | | Secs Held | Percent Held ( 26.235284s )
sitions | Rate Count | Count | Count | | CPU Elapsed | Real Real Comb Real
1 | 0.000 0 | 0 | 0 | | 0.000006 0.000006 | 0.00 0.00 0.00 0.00
-----
Depth | Min | Max | Avg
SpinQ | 0 | 0 | 0
WaitQ | 0 | 0 | 0
Recursion | 0 | 1 | 0

PThreadID | Acqui- | Miss | Spin | Wait | Busy | | Percent Held of Total Time
sitions | Rate | Count | Count | Count | CPU | Elapse | Spin | Wait
1 | 1 | 0.00 | 0 | 0 | 0 | 0.00 | 0.00 | 0.00 | 0.00

Function Name | Acqui- | Miss | Spin | Wait | Busy | | Percent Held of Total Time
sitions | Rate | Count | Count | Count | CPU | Elapse | Spin | Wait | Return Address | Start Address | Offset
pthread_once | 0 | 0.00 | 0 | 0 | 0 | 99.99 | 99.99 | 0.00 | 0.00 | 00000000D268EC98 | 00000000D2684180 | 0000AB18
pthread_once | 1 | 0.00 | 0 | 0 | 0 | 0.01 | 0.01 | 0.00 | 0.00 | 00000000D268EB88 | 00000000D2684180 | 0000AA08
```

In addition to the common header information and the **[PThread MUTEX]** identifier, this report lists the following lock details:

<b>Item</b>	<b>Descriptor</b>
<b>Parent Thread</b>	Pthread id of the parent pthread.
<b>creation time</b>	Elapsed time in seconds after the first event recorded in trace (if available).
<b>deletion time</b>	Elapsed time in seconds after the first event recorded in trace (if available).
<b>PID</b>	Process identifier.
<b>Process Name</b>	Name of the process using the lock.
<b>Call-chain</b>	Stack of called methods (if available).
<b>Acquisitions</b>	The number of times that the lock was acquired in the analysis interval.
<b>Miss Rate</b>	The percentage of attempts that failed to acquire the lock.
<b>Spin Count</b>	The number of unsuccessful attempts to acquire the lock.
<b>Wait Count</b>	The number of times that a thread was forced into a suspended wait state waiting for the lock to come available.
<b>Busy Count</b>	The number of <b>trylock</b> calls that returned busy.
<b>Seconds Held</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>CPU</b> The total number of processor seconds that the lock was held by an executing thread.</li> <li><b>Elapse(d)</b> The total number of elapsed seconds that the lock was held, whether the thread was running or suspended.</li> </ul>
<b>Percent Held</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>Real CPU</b> The percentage of the cumulative processor time that the lock was held by an executing thread.</li> <li><b>Real Elapsed</b> The percentage of the elapsed real time that the lock was held by any thread, either running or suspended.</li> <li><b>Comb(ined) Spin</b> The percentage of the cumulative processor time that running threads spent spinning while trying to acquire this lock.</li> <li><b>Real Wait</b> The percentage of elapsed real time that any thread was waiting to acquire this lock. If two or more threads are waiting simultaneously, this wait time will only be charged once. To learn how many threads were waiting simultaneously, look at the WaitQ Depth statistics.</li> </ul>
<b>Depth</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>SpinQ</b> The minimum, maximum, and average number of threads spinning on the lock, whether executing or suspended, across the analysis interval.</li> <li><b>WaitQ</b> The minimum, maximum, and average number of threads waiting on the lock, across the analysis interval.</li> <li><b>Recursion</b> The minimum, maximum, and average recursion depth to which each thread held the lock.</li> </ul>

### Mutex Pthread detail:

If the **-dt** or **-da** options are used, the **splat** command reports the following pthread details.

<b>Item</b>	<b>Descriptor</b>
<b>PThreadID</b>	The <b>PThread</b> identifier.
<b>Acquisitions</b>	The number of times that this pthread acquired the mutex.
<b>Miss Rate</b>	The percentage of acquisition attempts by the pthread that failed to secure the mutex.
<b>Spin Count</b>	The number of unsuccessful attempts by this pthread to secure the mutex.
<b>Wait Count</b>	The number of times that this pthread was forced to wait until the mutex came available.
<b>Busy Count</b>	The number of <b>trylock</b> calls that returned busy.

<b>Item</b>	<b>Descriptor</b>
<b>Percent Held of Total Time</b>	This field contains the following sub-fields:
<b>CPU</b>	The percentage of the elapsed real time that this pthread executed while holding the mutex.
<b>Elapse(d)</b>	The percentage of the elapsed real time that this pthread held the mutex while running or suspended.
<b>Spin</b>	The percentage of elapsed real time that this pthread executed while spinning on the mutex.
<b>Wait</b>	The percentage of elapsed real time that this pthread spent waiting on the mutex.

### Mutex function detail:

If the **-df** or **-da** options are used, the **splat** command reports the function details.

The **splat** command reports the following function details:

<b>Item</b>	<b>Descriptor</b>
<b>PThreadID</b>	The <b>PThread</b> identifier.
<b>Acquisitions</b>	The number of times that this function acquired the mutex.
<b>Miss Rate</b>	The percentage of acquisition attempts by the function that failed to secure the mutex.
<b>Spin Count</b>	The number of unsuccessful attempts by this function to secure the mutex.
<b>Wait Count</b>	The number of times that this function was forced to wait until the mutex came available.
<b>Busy Count</b>	The number of <b>trylock</b> calls that returned busy.
<b>Percent Held of Total Time</b>	This field contains the following sub-fields:
<b>CPU</b>	The percentage of the elapsed real time that this function executed while holding the mutex.
<b>Elapse(d)</b>	The percentage of the elapsed real time that this function held the mutex while running or suspended.
<b>Spin</b>	The percentage of elapsed real time that this function executed while spinning on the mutex.
<b>Wait</b>	The percentage of elapsed real time that this function spent waiting for the mutex.
<b>Return Address</b>	The return address to this calling function, in hexadecimal.
<b>Start Address</b>	The start address to this calling function, in hexadecimal.
<b>Offset</b>	The offset from the function start address to the return address, in hexadecimal.

### Read/Write lock reports:

The **PThread** read/write lock is similar to an AIX complex lock in that it can be acquired for reading or writing.

Writing is exclusive in that a single thread can only acquire the lock for writing, and no other thread can hold the lock for reading or writing at that point. Reading is not exclusive, so more than one thread can hold the lock for reading. Reading is recursive in that a single thread can hold multiple read-acquisitions on the lock. Writing is not recursive.

```
[PThread RWLock] ADDRESS: 00000000FF228E0
Parent Thread: 0000000000000001 creation time: 5.236585 deletion time: 6.090511
Pid: 7362 Process Name: /home/testrwlock
Creation call-chain =====
0000000010000458 .main
00000000100001DC .__start
=====
```

Acqui- sitions	Miss Rate	Spin Count	Wait Count	Secs Held		Percent Held ( 26.235284s )			
				CPU	Elapsed	Real CPU	Real Elapsed	Comb Spin	Real Wait
1150	40.568	785	0	21.037942	12.0346	80.19	99.22	30.45	46.29

Depth LockQ	Readers			Writers			Total		
	Min	Max	Avg	Min	Max	Avg	Min	Max	Avg
0	0	2	0	0	1	0	0	2	0

```
SpinQ    0    768 601    0    15  11        0    782 612
WaitQ    0    769 166    0    15   3        0    783 169
```

```

PthreadID  Acquisitions  Miss  Spin  Count  Wait  Count  Busy  Percent Held of Total Time
           Write  Read  Rate  Write  Read  Write  Read  Count  CPU  Elapse Spin  Wait
-----
    772      0    207  78.70    0    765    0    796    0  11.58  15.13 29.69 23.21
    515     765     0   1.80    14     0    14     0     0  80.10  80.19 49.76 23.08
    258      0    178  3.26     0     6     0     5     0  12.56  17.10 10.00 20.02

```

```

Function Name  Acquisitions  Miss  Spin  Count  Wait  Count  Busy  Percent Held of Total Time  Return Address  Start Address  Offset
           Write  Read  Rate  Write  Read  Write  Read  Count  CPU  Elapse Spin  Wait
-----
  _pthread_body  765    385 40.57    14    771     0     0     0  1.55   3.10  1.63  0.00 00000000D268944C 00000000D2684180 000052CC

```

In addition to the common header information and the [PThread RWLock] identifier, this report lists the following lock details:

<b>Item</b>	<b>Descriptor</b>
<b>Parent Thread</b>	Pthread id of the parent pthread.
<b>creation time</b>	Elapsed time in seconds after the first event recorded in trace (if available).
<b>deletion time</b>	Elapsed time in seconds after the first event recorded in trace (if available).
<b>PID</b>	Process identifier.
<b>Process Name</b>	Name of the process using the lock.
<b>Call-chain</b>	Stack of called methods (if available).
<b>Acquisitions</b>	The number of times that the lock was acquired in the analysis interval.
<b>Miss Rate</b>	The percentage of attempts that failed to acquire the lock.
<b>Spin Count</b>	The number of unsuccessful attempts to acquire the lock.
<b>Wait Count</b>	The current PThread implementation does not force pthreads to wait for read/write locks. This reports the number of times a thread, spinning on this lock, is undispatched.
<b>Seconds Held</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>CPU</b> The total number of processor seconds that the lock was held by an executing pthread. If the lock is held multiple times by the same pthread, only one hold interval is counted.</li> <li><b>Elapse(d)</b> The total number of elapsed seconds that the lock was held by any pthread, whether the pthread was running or suspended.</li> </ul>
<b>Percent Held</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>Real CPU</b> The percentage of the cumulative processor time that the lock was held by any executing pthread.</li> <li><b>Real Elapsed</b> The percentage of the elapsed real time that the lock was held by any pthread, either running or suspended.</li> <li><b>Comb(ined) Spin</b> The percentage of the cumulative processor time that running pthreads spent spinning while trying to acquire this lock.</li> <li><b>Real Wait</b> The percentage of elapsed real time that any pthread was waiting to acquire this lock. If two or more threads are waiting simultaneously, this wait time will only be charged once. To learn how many pthreads were waiting simultaneously, look at the WaitQ Depth statistics.</li> </ul>
<b>Depth</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>LockQ</b> The minimum, maximum, and average number of pthreads holding the lock, whether executing or suspended, across the analysis interval. This is broken down by read-acquisitions, write-acquisitions, and total acquisitions.</li> <li><b>SpinQ</b> The minimum, maximum, and average number of pthreads spinning on the lock, whether executing or suspended, across the analysis interval. This is broken down by read-acquisitions, write-acquisitions, and total acquisitions.</li> <li><b>WaitQ</b> The minimum, maximum, and average number of pthreads in a timed-wait state for the lock, across the analysis interval. This is broken down by read-acquisitions, write-acquisitions, and total acquisitions.</li> </ul>



Item	Descriptor
<b>PThreadID</b>	The <b>PThread</b> identifier.
<b>Passes</b>	The number of times that this pthread was notified that the condition passed.
<b>Fail Rate</b>	The percentage of times that the pthread checked the condition and did not find it to be true.
<b>Spin Count</b>	The number of times that the pthread checked the condition and did not find it to be true.
<b>Wait Count</b>	The number of times that this pthread was forced to wait until the condition became true.
<b>Percent Total Time</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>Spin</b> The percentage of elapsed real time that this pthread spun while testing the condition.</li> <li><b>Wait</b> The percentage of elapsed real time that this pthread spent waiting for the condition to hold.</li> </ul>

### Condition-Variable function detail:

If the **-df** or **-da** options are used, the **splat** command reports the following function details.

Item	Descriptor
<b>Function Name</b>	The name of the function that passed or attempted to pass this condition.
<b>Passes</b>	The number of times that this function was notified that the condition passed.
<b>Fail Rate</b>	The percentage of times that the function checked the condition and did not find it to be true.
<b>Spin Count</b>	The number of times that the function checked the condition and did not find it to be true.
<b>Wait Count</b>	The number of times that this function was forced to wait until the condition became true.
<b>Percent Total Time</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>Spin</b> The percentage of elapsed real time that this function spun while testing the condition.</li> <li><b>Wait</b> The percentage of elapsed real time that this function spent waiting for the condition to hold.</li> </ul>
<b>Return Address</b>	The return address to this calling function, in hexadecimal.
<b>Start Address</b>	The start address to this calling function, in hexadecimal.
<b>Offset</b>	The offset from the function start address to the return address, in hexadecimal.

---

## Hardware performance monitor APIs and tools

The **bos.pmapi** fileset contains libraries and tools that are designed to provide access to some of the counting facilities of the Performance Monitor feature included in select IBM® microprocessors.

They include the following:

- The **pmapi** library, which contains a set of low-level application programming interfaces, APIs, includes the following:
  - A set of system-level APIs to permit counting of the activity of a whole machine or of a set of processes with a common ancestor.
  - A set of first party kernel-thread-level APIs to permit threads to count their own activity.
  - A set of third party kernel-thread-level APIs to permit a debug program to count the activity of target threads.
- The **pmcycles** command, which returns the processor clock and decremter speeds.
- The **pmlist** command, which displays information about processors, events, event groups and sets, and derived metrics supported.
- The **hpm** and **hpm\_r** libraries, which contain a set of high-level APIs that enable the following:
  - Nested instrumentation of sections of code
  - Automatic calculation of derived metrics, and gathering of operating system resource-consumption metrics in addition to the raw hardware counter values
- The **hpmstat** command, which collects the hardware performance monitor raw and derived metrics concerning total system activity of a machine.

- The **hpmcount** command, which executes applications and provides the applications' execution wall clock time, the raw and derived hardware performance monitor metrics and the operating system resource-utilization statistics.

**Note:** The APIs and the events available on each of the supported processors have been completely separated by design. The events available, their descriptions, and their current testing status (which are different on each processor) are in separately installable tables, and are not described here because none of the API calls depend on the availability or status of any of the events.

The status of an event, as returned by the **pm\_initialize** API initialization routine, can be *verified*, *unverified*, *caveat*, *broken*, *group-only*, *thresholdable*, or *shared* (see "Performance monitor accuracy" about testing status and event accuracy).

An event filter (which is any combination of the status bits) must be passed to the **pm\_initialize** routine to force the return of events with status matching the filter. If no filter is passed to the **pm\_initialize** routine, no events will be returned.

## Performance monitor accuracy

Only events marked *verified* have gone through full verification. Events marked *caveat* have been verified within the limitations documented in the event description returned by the **pm\_initialize** routine.

Events marked *unverified* have undefined accuracy. Use caution with *unverified* events. The Performance Monitor API is essentially providing a service to read hardware registers that might not have any meaningful content.

Users can experiment with *unverified* event counters and determine for themselves if they can be used for specific tuning situations.

## Performance monitor context and state

To provide Performance Monitor data access at various levels, the AIX operating system supports optional performance monitoring contexts.

These contexts are an extension to the regular processor and thread contexts and include one 64-bit counter per hardware counter and a set of control words. The control words define which events are counted and when counting is on or off.

### System-level context and accumulation

For the system-level APIs, optional Performance Monitor contexts can be associated with each of the processors.

### Thread context

Optional Performance Monitor contexts can also be associated with each thread. The AIX operating system and the Performance Monitor kernel extension automatically maintain sets of 64-bit counters for each of these contexts.

### Thread counting-group and process context

The concept of thread counting-group is optionally supported by the thread-level APIs. All the threads within a group, in addition to their own performance monitor context, share a group accumulation context.

A thread group is defined as all the threads created by a common ancestor thread. By definition, all the threads in a thread group count the same set of events, and, with one exception described below, the group must be created before any of the descendant threads are created. This restriction is due to the fact that, after descendant threads are created, it is impossible to determine a list of threads with a common ancestor.

One special case of a group is the collection of all the threads belonging to a process. Such a group can be created at any time regardless of when the descendant threads are created, because a list of threads belonging to a process can be generated. Multiple groups can coexist within a process, but each thread can be a member of only one Performance Monitor counting-group. Because all the threads within a group must be counting the same events, a process group creation will fail if any thread within the process already has a context.

### Performance monitor state inheritance

The performance monitor is defined as the combination of the Performance Monitor programming (the events being counted), the counting state (on or off), and the optional thread group membership.

A counting state is associated with each group. When the group is created, its counting state is inherited from the initial thread in the group. For thread members of a group, the effective counting state is the result of AND-ing their own counting state with the group counting state. This provides a way to effectively control the counting state for all threads in a group. Simply manipulating the group-counting state will affect the effective counting state of all the threads in the group. Threads inherit their complete Performance Monitor state from their parents when the thread is created. A thread Performance Monitor context data (the value of the 64-bit counters) is not inherited, that is, newly created threads start with counters set to zero.

### Performance monitoring agent

The performance monitoring agent (**perfagent.server** fileset) is a collection of programs that make it possible for a host to act as a provider of performance statistics across a network or locally. The key program is the daemon **xmtopas**.

The following are the main components of the performance monitoring agent:

#### **xmtopas**

The data-supplier daemon, which permits a system where this daemon runs to supply performance statistics to data-consumer programs on the local or remote hosts. This daemon also provides the interface to SNMP.

**Note:** The interface to SNMP is available only on System p Agents.

#### **xmtrend**

A long-term recording daemon. This daemon also provides large metric set trend recordings for post-processing by **jazizo** and **jttopas**.

#### **xmscheck**

A program that lets you pre-check the **xmservd** recording configuration file. This program is useful when you want to start and stop **xmservd** recording at predetermined times.

**filtd** A daemon that can be used to do data reduction of existing statistics and to define alarm conditions and triggering of alarms.

#### **xmpeek**

A program that allows you to display the status of **xmservd** on the local or a remote host and to list all available statistics from the daemon.

#### **iphosts**

A program to initiate monitoring of Internet Protocol performance by specifying which hosts to monitor. The program accepts a list of hosts from the command line or from a file.

#### **armtoleg**

A program that can convert a pre-existing Application Response Management (ARM) library into an ARM library that can be accessed concurrently with the ARM library shipped with PTX. This program is only required and available on operating systems.

### SpmiArmd

A daemon that collects Application Response Management (ARM) data and interfaces to the Spmi library code to allow monitoring of ARM metrics from any PTX manager program.

### SpmiResp

A daemon that polls for IP response times for selected hosts and interfaces to the Spmi library code to allow monitoring of IP response time metrics from any PTX manager program.

### Application Response Management API and Libraries

A header file and two libraries support the PTX implementation of ARM. The implementation allows for coexistence and simultaneous use of the PTX ARM library and one previously installed ARM library.

### System Performance Measurement Interface API and Library

Header files and a library to allow you to develop your own data-supplier and local data-consumer programs.

### Sample Programs

Sample dynamic data-supplier and data-consumer programs that illustrate the use of the API.

### Remote System Performance Measurement Interface API

This API is available for those who want to develop programs that access the statistics available from one or more `xmtpas` daemons.

## POWERCOMPAT events

The POWERCOMPAT events provide a list of hardware events that are available for processor compatibility modes and are used as a subset of the actual processor events.

You can use the processor compatibility modes to move logical partitions between systems that have different processor types without upgrading the operating system environments in the logical partition. The processor compatibility mode allows the destination system to provide the logical partition with a subset of processor capabilities that are supported by the operating systems environment in the logical partition.

The following hardware events are supported in the POWERCOMPAT compatibility mode for different versions of the AIX operating system.

Table 1. POWERCOMPAT events

Counter	Event name	Supported AIX version
1	PM_1PLUS_PPC_CMPL	<ul style="list-style-type: none"><li>• AIX 6.1 with 6100-04, or later</li><li>• AIX 7.1, or later</li></ul>
1	PM_CYC	<ul style="list-style-type: none"><li>• AIX 6.1 with 6100-04, or later</li><li>• AIX 7.1, or later</li></ul>
1	PM_DATA_FROM_L1.5	<ul style="list-style-type: none"><li>• AIX 6 with 6100-07, or earlier</li><li>• AIX 7 with 7100-01, or earlier</li></ul>
1	PM_FLOP	<ul style="list-style-type: none"><li>• AIX 6.1 with 6100-04, or later</li><li>• AIX 7.1, or later</li></ul>
1	PM_GCT_NOSLOT_CYC	<ul style="list-style-type: none"><li>• AIX 6.1 with 6100-04, or later</li><li>• AIX 7.1, or later</li></ul>
1	PM_IERAT_MISS	<ul style="list-style-type: none"><li>• AIX 6.1 with 6100-04, or later</li><li>• AIX 7.1, or later</li></ul>
1	PM_INST_CMPL	<ul style="list-style-type: none"><li>• AIX 6 with 6100-07, or earlier</li><li>• AIX 7 with 7100-01, or earlier</li></ul>

Table 1. POWERCOMPAT events (continued)

Counter	Event name	Supported AIX version
1	PM_INST_IMC_MATCH_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
1	PM_LSU_DERAT_MISS_CYC	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
1	PM_PMC4_OVERFLOW	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
1	PM_SUSPENDED	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
1	PM_ANY_THRD_RUN_CYC	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
1	PM_MRK_INST_DISP	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
1	PM_MRK_BR_TAKEN_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
1	PM_MRK_L1_ICACHE_MISS	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
1	PM_THRESH_EXC_4096	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
1	PM_THRESH_EXC_256	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
1	PM_MRK_L1_RELOAD_VALID	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
1	PM_THRESH_MET	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
2	PM_CYC	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
2	PM_DATA_FROM_L2MISS	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
2	PM_EXT_INT	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
2	PM_INST_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
2	PM_INST_DISP	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
2	PM_L1_ICACHE_MISS	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
2	PM_LSU_DERAT_MISS	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
2	PM_PMC1_OVERFLOW	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
2	PM_RUN_CYC	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>

Table 1. POWERCOMPAT events (continued)

Counter	Event name	Supported AIX version
2	PM_ST_FIN	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
2	PM_SUSPENDED	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
2	PM_MRK_DATA_FROM_MEM	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
2	PM_MRK_LD_MISS_L1	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
2	PM_MRK_DATA_FROM_L3MISS	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
2	PM_THRESH_EXC_32	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
2	PM_THRESH_EXC_512	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
3	PM_CYC	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
3	PM_DATA_FROM_L3MISS	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
3	PM_DTLB_MISS	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
3	PM_INST_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
3	PM_INST_DISP	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
3	PM_L1_DCACHE_RELOAD_VALID	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
3	PM_PMC2_OVERFLOW	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
3	PM_ST_MISS_L1	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
3	PM_SUSPENDED	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
3	PM_TB_BIT_TRANS	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
3	PM_THRD_CONC_RUN_INST	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
3	PM_BR_TAKEN_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
3	PM_MRK_ST_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
3	PM_MRK_BR_MPRED_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>

Table 1. POWERCOMPAT events (continued)

Counter	Event name	Supported AIX version
3	PM_MRK_DERAT_MISS	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
3	PM_THRESH_EXC_64	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
3	PM_THRESH_EXC_1024	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
4	PM_1PLUS_PPC_DISP	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
4	PM_BR_MPRED_CMPL	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
4	PM_CYC	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
4	PM_FLUSH	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
4	PM_INST_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
4	PM_ITLB_MISS	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
4	PM_LD_MISS_L1	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
4	PM_PMC3_OVERFLOW	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
4	PM_RUN_INST_CMPL	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
4	PM_RUN_PURR	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
4	PM_SUSPENDED	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
4	PM_MRK_INST_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
4	PM_MRK_DTLB_MISS	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
4	PM_MRK_INST_FROM_L3MISS	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
4	PM_MRK_DATA_FROM_L2MISS	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
4	PM_THRESH_EXC_128	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
4	PM_THRESH_EXC_2048	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
4	PM_DATA_FROM_MEM	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>

Table 1. POWERCOMPAT events (continued)

Counter	Event name	Supported AIX version
5	PM_RUN_INST_CMPL	<ul style="list-style-type: none"> <li>• AIX 6.1, or later</li> <li>• AIX 7.1, or later</li> </ul>
6	PM_RUN_CYC	<ul style="list-style-type: none"> <li>• AIX 6.1, or later</li> <li>• AIX 7.1, or later</li> </ul>

## Thread accumulation and thread group accumulation

When a thread gets suspended (or redispached), its 64-bit accumulation counters are updated. If the thread is member of a group, the group accumulation counters are updated at the same time.

Similarly, when a thread stops counting or reads its Performance Monitor data, its 64 bit accumulation counters are also updated by adding the current value of the Performance Monitor hardware counters to them. Again, if the thread is a member of a group, the group accumulation counters are also updated, regardless of whether the counter read or stop was for the thread or for the thread group.

The group-level accumulation data is kept consistent with the individual Performance Monitor data for the thread members of the group, whenever possible. When a thread voluntarily leaves a group, that is, deletes its Performance Monitor context, its accumulated data is automatically subtracted from the group-level accumulated data. Similarly, when a thread member in a group resets its own data, the data in question is subtracted from the group level accumulated data. When a thread dies, no action is taken on the group-accumulated data.

The only situation where the group-level accumulation is not consistent with the sum of the data for each of its members is when the group-level accumulated data has been reset, and the group has more than one member. This situation is detected and marked by a bit returned when the group data is read.

## Security considerations

The system-level APIs calls are only available from the root user except when the process tree option is used. In that case, a locking mechanism prevents calls being made from more than one process. This mechanism ensures ownership of the API and exclusive access by one process from the time that the system-level contexts are created until they are deleted.

Enabling the process tree option results in counting for only the calling process and its descendants; the default is to count all activities on each processor.

Because the system-level APIs would report bogus data if thread contexts where in use, system-level API calls are not enabled at the same time as thread-level API calls. The allocation of the first thread context will take the system-level API lock, which will not be released until the last context has been deallocated.

When using first party calls, a thread is only permitted to modify its own Performance Monitor context. The only exception to this rule is when making group level calls, which obviously affect the group context, but can also affect other threads' context. Deleting a group deletes all the contexts associated with the group, that is, the caller context, the group context, and all the contexts belonging to all the threads in the group.

Access to a Performance Monitor context not belonging to the calling thread or its group is available only from the target process's debugger program. The third party API calls are only permitted when the target process is either being **ptraced** by the API caller, that is, the caller is already attached to the target process, and the target process is stopped or the target process is stopped on a **/proc** file system event and the caller has the privilege required to open its control file.

The fact that the debugger program must already have been attached to the debugged thread before any third party call to the API can be made, ensures that the security level of the API will be the same as the one used between debugger programs and process being debugged.

## The pmapi library

Review the rules that are for the pmapi library.

The following rules are common to the Performance Monitor APIs:

- The **pm\_initialize** routine must be called before any other API call can be made, and only events returned by a given **pm\_initialize** call with its associated filter setting can be used in subsequent **pm\_set\_program** calls.
- PM contexts cannot be reprogrammed or reused at any time. This means that none of the APIs support more than one call to a **pm\_set\_program** interface without a call to a **pm\_delete\_program** interface. This also means that when creating a process group, none of the threads in the process is permitted to already have a context.
- All the API calls return 0 when successful or a positive error code (which can be decoded using **pm\_error**) otherwise.

### The pm\_init API initialization routine

The **pm\_init** routine returns (in a structure of type **pm\_info\_t** pointed to by its second parameter) the processor name, the number of counters available, the list of available events for each counter, and the threshold multipliers supported.

Some processor support two threshold multipliers, others none, meaning that thresholding is not supported at all. You can not use the **pm\_init** routine with processors newer than POWER4. You must use the **pm\_initialize** routine for newer processors.

For each event returned, in addition to the testing status, the **pm\_init** routine also returns the identifier to be used in subsequent API calls, a short name, and a long name. The short name is a mnemonic name in the form PM\_MNEMONIC. Events that are the same on different processors will have the same mnemonic name. For instance, PM\_CYC and PM\_INST\_CMPL are respectively the number of processor cycles and instruction completed and should exist on all processors. For each event returned, a thresholdable flag is also returned. This flag indicates whether an event can be used with a threshold. If so, then specifying a threshold defers counting until a number of cycles equal to the threshold multiplied by the processor's selected threshold multiplier has been exceeded.

The Performance Monitoring API enables the specification of event groups instead of individual events. Event groups are predefined sets of events. Rather than each event being individually specified, a single group ID is specified. The interface to the **pm\_init** routine has been enhanced to return the list of supported event groups in a structure of type **pm\_groups\_info\_t** pointed to by a new optional third parameter. To preserve binary compatibility, the third parameter must be explicitly announced by OR-ing the PM\_GET\_GROUPS bitflag into the filter. Some events on some platforms can only be used from within a group. This is indicated in the threshold flag associated with each event returned. The following convention is used:

Item	Descriptor
y	A thresholdable event
g	An event that can only be used in a group
G	A thresholdable event that can only be used in a group
n	A non-thresholdable event that is usable individually

On some platforms, use of event groups is required because all the events are marked **g** or **G**. Each of the event groups that are returned includes a short name, a long name, and a description similar to those associated with events, as well as a group identifier to be used in subsequent API calls and the events contained in the group (in the form of an array of event identifiers).

The testing status of a group is defined as the lowest common denominator among the testing status of the events that it includes. If at least one event has a testing status of *caveat*, the group testing status is at best *caveat*, and if at least one event has a status of *unverified*, then the group status is *unverified*. This is not returned as a group characteristic, but it is taken into account by the filter. Like events, only groups with status matching the filter are returned.

### The `pm_initialize` API initialize routine

The `pm_initialize` routine returns the processor name in a structure of type `pm_info2_t` defined by its second parameter, its characteristics, the number of counters available, and the list of available events for each counter.

For each event a status is returned, indicating the event status: *validated*, *unvalidated*, or *validated with caveat*. The status also indicates if the event can be used in a group or not, if it is a thresholdable event and if it is a shared event.

Some events on some platforms can be used only within a group. In the case where an event group is specified instead of individual events, the events are defined as *grouped only* events.

For each returned event, a thresholdable state is also returned. It indicates whether an event can be used with a threshold. If so, specifying a threshold defers counting until it exceeds a number of cycles equal to the threshold multiplied by the selected processor threshold multiplier.

Some processors support two hardware threads per physical processing unit. Each thread implements a set of counters, but some events defined for those processors are shared events. A shared event, is controlled by a signal not specific to a particular thread's activity and sent simultaneously to both sets of hardware counters, one for each thread. Those events are marked by the *shared* status.

For each returned event, in addition to the testing status, the `pm_initialize` routine returns the identifier to be used in subsequent API calls, as a short name and a long name. The short name is a mnemonic name in the form `PM_MNEMONIC`. The same events on different processors will have the same mnemonic name. For instance, `PM_CYC` and `PM_INST_CMPL` are respectively the number of processor cycles and the number of completed instructions, and should exist on all processors.

The Performance Monitoring API enables the specification of event groups instead of individual events. Event groups are predefined sets of events. Rather than to specify individually each event, a single group ID can be specified. The interface to the `pm_initialize` routine returns the list of supported event groups in a structure of type `pm_groups_info_t` whose address is returned in the third parameter.

On some platforms, the use of event groups is required because all events are marked as group-only. Each event group that is returned includes a short name, a long name, and a description similar to those associated with events, as well as a group identifier to be used in subsequent API calls and the events contained in the group (in the form of an array of event identifiers).

The testing status of a group is defined as the lowest common denominator among the testing status of the events that it includes. If the testing status of at least one event is *caveat*, then the group testing status

is at best *caveat*, and if the status of at least one event is *unverified*, then the group status is *unverified*. This is not returned as a group characteristic, but it is taken into account by the filter. Like events, only groups whose status match the filter are returned.

If the **proctype** parameter is not set to `PM_CURRENT`, the Performance Monitor APIs library is not initialized and the subroutine only returns information about the specified processor in its parameters, **pm\_info2\_t** and **pm\_groups\_info\_t**, taking into account the filter. If the **proctype** parameter is set to `PM_CURRENT`, in addition to returning the information described, the Performance Monitor APIs library is initialized and ready to accept other calls.

## Basic pmapi library calls

Each of the following sections describes a system-wide API call that has variations for first- and third-party kernel thread or group counting. Variations are indicated by suffixes to the function call names, such as **pm\_set\_program**, **pm\_set\_program\_mythread**, and **pm\_set\_program\_group**.

### **pm\_set\_program**

Sets the counting configuration. Use this call to specify the events (as a list of event identifiers, one per counter, or as a single event-group identifier) to be counted, and a mode in which to count. The list of events to choose from is returned by the **pm\_init** routine. If the list includes a thresholdable event, you can also use this call to specify a threshold, and a threshold multiplier.

The mode in which to count can include user-mode and kernel-mode counting, and whether to start counting immediately. For the system-wide API call, the mode also includes whether to turn counting on only for a process and its descendants or for the whole system. For counting group API calls, the mode includes the type of counting group to create, that is, a group containing the initial thread and its future descendants, or a process-level group, which includes all the threads in a process.

By default, the time spent during interrupts handling is counted. It is possible to override this default behavior by modifying the counting mode.

### **pm\_get\_program**

Retrieves the current Performance Monitor settings. This includes mode information and the list of events (or the event group) being counted. If the list includes a thresholdable event, this call also returns a threshold and the multiplier used.

### **pm\_delete\_program**

Deletes the Performance Monitor configuration. Use this call to undo **pm\_set\_program**.

### **pm\_start, pm\_tstart**

Starts Performance Monitor counting. **pm\_tstart** returns a timestamp associated with the time the Performance Monitoring counters started counting. This is a timebase value that can be converted to time using **time\_base\_to\_time**.

### **pm\_stop, pm\_tstop**

Stops Performance Monitor counting. **pm\_tstop** returns a timestamp associated with the time the Performance Monitoring counters stopped counting. This is a timebase value that can be converted to time using **time\_base\_to\_time**.

### **pm\_get\_data, pm\_get\_tdata, pm\_get\_Tdata**

Returns Performance Monitor counting data. The data is a set of 64-bit values, one per hardware counter. For the counting group API calls, the group information is also returned. (See “Thread counting-group information” on page 61.)

**pm\_get\_tdata** is similar to **pm\_get\_data**, but includes a timestamp that indicates the last time that the hardware Performance Monitoring counters were read. This is a timebase value that can be converted to time by using **time\_base\_to\_time**.

**pm\_get\_Tdata** is also similar to **pm\_get\_data** but includes accumulated times corresponding to the interval during which the hardware Performance Monitoring counters were active. The

interval is measured in real time, PURR and SPURR (on processors supporting those) values, and returned in timebase units convertible to time using `time_base_to_time`.

The `pm_get_data_cpu`, `pm_get_tdata_cpu` and `pm_get_Tdata_cpu` interfaces return the Performance Monitor counting data for a single processor. The specified processor number represents a contiguous number going from 0 to `_system_configuration.ncpus`. This number can represent a different processor from call to call if dynamic reconfiguration operations have occurred.

The `pm_get_data_lcpu`, `pm_get_tdata_lcpu` and `pm_get_Tdata_lcpu` interfaces return the Performance Monitor counting data for a single logical processor. The logical processor numbering is not contiguous, and the call to these interfaces returns an error if the specified logical processor has not been on line since the last call to `pm_set_program`. A logical processor number always designates the same processor even if dynamic reconfiguration operations have occurred. To get data for all processors, these interfaces must be called in a loop from 0 to `_system_configuration.max_ncpus`.

#### **pm\_reset\_data**

Resets Performance Monitor counting data. All values are set to 0.

### **Thread counting-group information**

This the following information is returned by the `pm_get_data_mygroup` and `pm_get_data_pgroup` interfaces in a `pm_groupinfo_t` structure.

The following information is associated with each thread counting-group:

#### **member count**

The number of threads that are members of the group. This includes deceased threads that were members of the group when running.

If the consistency flag is on, the count will be the number of threads that have contributed to the group-level data.

#### **process flag**

Indicates that the group includes all the threads in the process.

#### **consistency flag**

Indicates that the group PM data is consistent with the sum of the individual PM data for the thread members.

### **Counter multiplexing mode**

You can set the counting for more events than available hardware counters using counter multiplexing. This mode is meant to be used to analyze workloads with homogenous performance characteristics. This avoids the requirement to run the workload multiple times to collect more events than available hardware counters.

In this mode, the `pmapi` periodically changes the setting of the counting and accumulates values and counting time for multiple sets of events. The time each event set is counted before switching to the next set can be in the range of 10 ms to 30 s. The default value is 100 ms.

The values returned include the number of times all sets of events have been counted, and for each set, the accumulated counter values and the accumulated time the set was counted. The accumulated time is measured up to three different ways: using Time Base, and when available, using the PURR time and one the SPURR time. These times are stored in a timebase format that can be converted to time by using the `time_base_to_time` function. These times are meant to be used to normalize the results across the complete measurement interval.

Several basic `pmapi` calls have the following multiplexing mode variations indicated by the `_mx` suffix:

### **pm\_set\_program\_mx**

Sets the counting configuration. It differs from the **pm\_set\_program** function in that it accepts a set of groups (or event lists) to be counted, and the time each set must be counted before switching to the next set.

### **pm\_get\_program\_mx**

Retrieves the current Performance Monitor settings. It differs from the **pm\_get\_program** function in that it returns a set of groups (or event lists).

### **pm\_get\_data\_mx**

Returns the Performance Monitor counting data. It returns a set of counting data, one per group (or event list) configured. The returned data includes in addition to the accumulated counter values, the number of times all the configured sets have been counted, and for each set, the accumulated time it was counted.

### **pm\_get\_tdata\_mx**

Same as **pm\_get\_data\_mx**, but includes a timestamp indicating the last time that the hardware Performance Monitor counters were read.

### **pm\_get\_data\_cpu\_mx/pm\_get\_tdata\_cpu\_mx**

Same as **pm\_get\_data\_mx** or **pm\_get\_tdata\_mx**, but returns the Performance Monitor counting data for a single processor. The specified processor number must be in the range 0 to **\_system\_configuration.ncpus**. This number might represent different processors from call to call if dynamic reconfiguration operations have occurred.

### **pm\_get\_data\_lcpu\_mx/pm\_get\_tdata\_lcpu\_mx**

Same as **pm\_get\_data\_cpu\_mx** or **pm\_get\_tdata\_cpu\_mx**, but returns the Performance Monitor counting data for a single logical processor. The logical processor numbering is not contiguous, and the call to these interfaces return an error if the specified logical processor has not been online since the last call to **pm\_set\_program\_mx**. A logical processor number always designates the same processor even if dynamic reconfiguration operations have occurred. To get data for all processors, these interfaces must be called in a loop from 0 to **\_system\_configuration.max\_ncpus**.

## **Counter multi-mode**

Counter multi-mode is similar to multiplexing mode. The counting mode in multiplexing mode is common to all the event sets.

The multi-mode allows you to associate a counting mode with each event set, but as the counting mode differs for an event set to another one, the results of the counting cannot be normalized on the complete measurement interval.

Several basic pmapi calls have the following multi-mode variations indicated by the **\_mm** suffix:

### **pm\_set\_program\_mm**

Sets the counting configuration. It differs from the **pm\_set\_program\_mx** function in that it accepts a set of groups and associated counting mode to be counted.

### **pm\_get\_program\_mm**

Retrieves the current Performance Monitor settings. It differs from the **pm\_get\_program\_mx** function in that it accepts a set of groups and associated counting mode.

## **WPAR counting**

It is possible to monitor the system-wide activity of a specific WPAR from the Global WPAR. In this case, only the activity of the processes running in this WPAR will be monitored.

Several basic pmapi calls have the following per-WPAR variations indicated by the **\_wp** suffix:

### **pm\_set\_program\_wp, pm\_set\_program\_wp\_mm**

Same as the **pm\_set\_program** subroutine or the **pm\_set\_program\_mm** subroutine, except that the

programming is set for the specified WPAR only (identified by its WPAR Configured ID). Notice that there is no `pm_set_program_wp_mx` subroutine.

#### **pm\_get\_program, pm\_get\_program\_wp**

Same as the `pm_get_program` subroutine or the `pm_get_program_wp` subroutine, except that it retrieves the programming for the specified WPAR only (identified by its WPAR Configured ID). Notice that there is no `pm_get_program_wp_mx` subroutine.

#### **pm\_start\_wp, pm\_tstart, pm\_start\_wp, pm\_tstart\_wp**

Same as the `pm_start` subroutine or the `pm_tstart` subroutine, except that it targets a specific WPAR (identified by its WPAR Configured ID).

#### **pm\_stop\_wp, pm\_tstop, pm\_stop\_wp, pm\_tstop\_wp**

Same as the `pm_stop` subroutine or the `pm_tstop` subroutine, except that it targets a specific WPAR (identified by its WPAR Configured ID).

#### **pm\_get\_data\_wp, pm\_get\_tdata\_wp, pm\_get\_Tdata**

Same as the `pm_get_data` subroutine or the `pm_get_tdata` subroutine or the `pm_get_Tdata` subroutine, except that it retrieves Performance Monitor counting data for the specified WPAR only (identified by its handle, see the `pm_get_wplist` subroutines).

#### **pm\_reset\_data**

Same as the `pm_get_data` routine or the `pm_get_tdata` subroutine or the `pm_get_Tdata` subroutine, except that it retrieves Performance Monitor counting data for the specified WPAR only (identified by its handle, see the `pm_get_wplist` subroutines).

#### **pm\_get\_wplist**

Retrieves the list of WPARs contexts that were active during the last system-wide counting. A WPAR context includes the WPAR Configured ID, the WPAR name, and a WPAR handle that uniquely identifies the WPAR. The WPAR handle can then be used to retrieve the Performance Monitor counting data for a specified WPAR using one of the `pm_get_data_wp` subroutines.

## **Examples of pmapi library usage**

The following examples demonstrate the use of Performance Monitor APIs in pseudo-code. Functional sample code is available in the `/usr/samples/pmapi` directory.

### **Simple single-threaded program example:**

The following example displays a single-threaded program.

```
# include <pmapi.h>
main()
{
    pm_info_t pminfo;
    pm_prog_t prog;
    pm_data_t data;
    int filter = PM_VERIFIED; /* use only verified events */

    pm_init(filter, &pminfo)

    prog.mode.w      = 0; /* start with clean mode */
    prog.mode.b.user = 1; /* count only user mode */

    for (i = 0; i < pminfo.maxpmcs; i++)
        prog.events[i] = COUNT_NOTHING;

    prog.events[0]   = 1; /* count event 1 in first counter */
    prog.events[1]   = 2; /* count event 2 in second counter */

    pm_set_program_mythread(&prog);
    pm_start_mythread();

(1) ... usefull work ....
```

```

    pm_stop_mythread();
    pm_get_data_mythread(&data);

    ... print results ...
}

```

### Initialization example using an event group:

The following example displays initialization using an event group.

```

#include <pmapi.h>
main()
{
    pm_info2_t      pminfo;
    pm_prog_t      prog;
    pm_groups_info_t pmginfo;

    int filter = PM_VERIFIED; /* get list of verified events */

    pm_initialize(filter, &pminfo, &pmginfo, PM_CURRENT )

    prog.mode.w      = 0; /* start with clean mode */
    prog.mode.b.user = 1; /* count only user mode */
    prog.mode.b.is_group = 1; /* specify event group */

    for (i = 0; i < pminfo.maxpmcs; i++)
        prog.events[i] = COUNT_NOTHING;

    prog.events[0]    = 1; /* count events in group 1 */
    .....
}

```

### Get the information about all the event-groups for a specific processor example:

The following example displays how to obtain all the event-groups that are supported for a specific processor.

```

#include <stdio.h>
#include <stdlib.h>
#include <pmapi.h>

int main()
{
    int rc = 0;
    pm_info2_t events;
    pm_groups_info_t groups;

    pm_events2_t *ev_ptr = NULL;

    int filter = 0;
    /*
    * Get the events and groups supported for POWER4.
    * To get the events and groups supported for the current processor,
    * use PM_CURRENT.
    */
    int processor_type = PM_POWER4;

    int group_idx = 0;
    int counter_idx = 0;
    int ev_count = 0;
    int event_found = 0;

    /*
    * PM_VERIFIED - To get list of verified events
    * PM_UNVERIFIED - To get list of unverified events
    * PM_CAVEAT - To get list of events that are usable but with caveats
    */
}

```

```

filter |= PM_VERIFIED | PM_UNVERIFIED | PM_CAVEAT;

/* Get list of events-groups */
filter |= PM_GET_GROUPS;

if ((rc = pm_initialize(filter, &events, &groups, processor_type)) != 0)
{
    pm_error("pm_initialize", rc);
    exit(-1);
}
for(group_idx = 0; group_idx < groups.maxgroups; group_idx++)
{
    printf("=====\n");
    printf("Group ID: %d.\n", groups.event_groups[group_idx].group_id);
    printf("Group Name: %s.\n", groups.event_groups[group_idx].short_name);
    printf("Group Long Name: %s.\n", groups.event_groups[group_idx].long_name);
    printf("Group Description: %s.\n", groups.event_groups[group_idx].description);
    printf("Events in this Group: \n");
    for(counter_idx = 0; counter_idx < events.maxpmcs; counter_idx++)
    {
        event_found = 0;
        for(ev_ptr = events.list_events[counter_idx], ev_count = 0;
            ev_count < events.maxevents[counter_idx];
            ev_ptr++, ev_count++)
        {
            /* If the event ID in "groups" matches with event ID supported
             * in the counter */
            if(groups.event_groups[group_idx].events[counter_idx] == ev_count)
            {
                printf("\tCounter ID: %d.\n", counter_idx+1);
                printf("\tEvent ID: %d.\n", ev_count);
                printf("\tEvent Name: %s.\n", ev_ptr->short_name);
                event_found = 1;
                break;
            }
            /* We have found the event for this counter. Move on to
             * next counter. */
            if(event_found) break;
        }
    }
    printf("\n");
}
return 0;
}

```

### Debugger program example for initialization program:

The following example illustrates how to look at the performance monitor data while the program is executing.

from a debugger at breakpoint (1)

```

(2) pm_initialize(filter);
    pm_get_program_thread(pid, tid, ptid, &prog);
    ... display PM programming ...

(3) pm_get_data_thread(pid, tid, ptid);
    ... display PM data ...

    pm_delete_program_thread(pid, tid, ptid);
    prog.events[0] = 2; /* change counter 1 to count event number 2 */
    pm_set_program_thread(pid, tid, ptid, &prog);

```

continue program

The preceding scenario would also work if the program being executed under the debugger did not have any embedded Performance Monitor API calls. The only difference would be that the calls at (2) and (3) would fail, and that when the program continues, it will be counting only event number 2 in counter 1, and nothing in other counters.

### Count a single WPAR from the Global WPAR:

The following program is an example of a count of a single WPAR from the global WPAR.

```
main ()
{
    pm_prog_t prog;
    pm_wpar_ctx_info_t wp_list;
    int nwpars = 1;
    cid_t cid;

    /* set programming for WPAR ``wpar1'' */
    getcorralid("wpar1", &cid);
    pm_set_program_wp(cid, &prog);

    pm_start_wp(cid);
    ... workload ...
    pm_stop_wp(cid);

    /* retrieve data for WPAR ``wpar1'' */
    pm_get_wplist("wpar1", &wp_list, &nwpars);
    pm_get_data_wp(wp_list.wp_handle, &data);

    pm_delete_program_wp(cid);
}
```

### Count all active WPARs from the Global WPAR and retrieve per-WPAR data:

The following program is an example of a count of all active WPARS from the global WPAR and also retrieves per-WPAR data.

```
main ()
{
    pm_prog_t prog;
    pm_wpar_ctx_info_t *wp_list;
    int nwpars;

    /* set programming */
    ...
    prog.mode.b.wpar_all = 1; /* collect per-WPAR data */
    pm_set_program(&prog);

    pm_start();
    ... workload ...
    pm_stop();

    /* retrieve the number of WPARs that were active during the counting */
    nwpars = 0;
    pm_get_wplist(NULL, NULL, &nwpars);
    /* allocate an array large enough to retrieve WPARs contexts */
    wp_list = malloc(nwpars * sizeof (pm_wpar_ctx_info_t));
    /* retrieve WPARs contexts */
    pm_get_wplist(NULL, wp_list, &nwpars);

    /* retrieve and print data for each WPAR */
    for (i = 0; i < nwpars; i++) {
        printf("WPAR: %s (CID=%d)\n", wp_list[i].name, wp_list[i].cid);
        pm_get_data_wp(wp_list[i].hwpar, &data);
    }
}
```

```

        free(wp_list);
        pm_delete_program();
    }

```

### Simple multi-threaded example:

The following is a simple multi-threaded example with independent threads counting the same set of events.

```

#include <pmapi.h>
pm_data_t data2;

void *
doit(void *)
{
    (1)    pm_start_mythread();
           ... usefull work ....

           pm_stop_mythread();
           pm_get_data_mythread(&data2);
}

main()
{
    pthread_t threadid;
    pthread_attr_t attr;
    pthread_addr_t status;

    ... same initialization as in previous example ...

    pm_program_mythread(&prog);

    /* setup 1:1 mode */
    pthread_attr_init(&attr);
    pthread_attr_setscope(&attr, PTHREAD_SCOPE_SYSTEM);
    pthread_create(&threadid, &attr, doit, NULL);

    (2)    pm_start_mythread();
           ... usefull work ....

           pm_stop_mythread();
           pm_get_data_mythread(&data);

           ... print main thread results (data )...

           pthread_join(threadid, &status);

           ... print auxiliary thread results (data2) ...
}

```

In the preceding example, counting starts at (1) and (2) for the main and auxiliary threads respectively because the initial counting state was off and it was inherited by the auxiliary thread from its creator.

### Simple thread counting-group example:

The following example has two threads in a counting-group. The body of the auxiliary thread's initialization routine is the same as in the previous example.

```

main()
{
    ... same initialization as in previous example ...
}

```

```

(1) pm_set_program_mygroup(&prog); /* create counting group */
    pm_start_mygroup()

    pthread_create(&threadid, &attr, doit, NULL)

(2) pm_start_mythread();

    ... usefull work ....

    pm_stop_mythread();
    pm_get_data_mythread(&data)

    ... print main thread results ...

    pthread_join(threadid, &status);

    ... print auxiliary thread results ...

    pm_get_data_mygroup(&data)

    ... print group results ...
}

```

In the preceding example, the call in (2) is necessary because the call in (1) only turns on counting for the group, not the individual threads in it. At the end, the group results are the sum of both threads results.

### Simple thread counting-group with counter-multiplexing example:

The following example has two threads in a counting-group. The body of the auxiliary thread's initialization routine is the same as in the previous example.

```

main()
{
    pm_info2_t      pminfo;
    pm_groups_info_t pmginfo;
    pm_prog_mx_r    prog;
    pm_events_prog_t event_set[2];
    pm_data_mx_t    data;
    int filter = PM_VERIFIED; /* get list of verified events */
    pm_initialize(filter, &pminfo, &pmginfo, PM_CURRENT )
    prog.mode.w      = 0; /* start with clean mode */
    prog.mode.b.user = 1; /* count only user mode */
    prog.mode.b.is_group = 1; /* specify event group */
    prog.events_set  = event_set;
    prog.nb_events_prog = 2; /* two event group counted */
    prog.slice_duration = 200; /* slice duration for each event group is 200ms */
    for (i = 0; i < pminfo.maxpmcs; i++) {
        event_set[0][i] = COUNT_NOTHING;
        event_set[1][i] = COUNT_NOTHING;
    }

    event_set[0][0] = 1; /* count events in group 1 in the first set */
    event_set[1][0] = 3; /* count events in group 3 in the first set */
    pm_set_program_mygroup_mx(&prog); /* create counting group */
    pm_start_mygroup()
    pthread_create(&threadid, &attr, doit, NULL)
    pm_start_mythread();
    ... usefull work ....
    pm_stop_mythread();
    pm_get_data_mythread_mx(&data)
    printf ("Main thread results:\n");
    for (i = 0; i < 2 ; i++) {
        group_number = event_set[i][0];
        printf ("Group #%d: %s\n", group_number, pmginfo.event_groups[group_number].short_name);
    }
}

```

```

        printf ("    counting time: %d ms\n", data.accu_set[i].accu_time);
        printf ("    counting values:\n");

        for (counter = 0; counter < pminfo.maxpmcs; counter++) {
            printf ("event %d: %d\n", counter, data.accu_set[i].accu_data[counter]);
        }
    }
(1) free(data.accu_set); /* free the memory allocated for the main thread results */
pthread_join(threadid, &status);
... print auxiliary thread results ...
free(data.accu_set); /* free the memory allocated for the thread results */
pm_get_data_mygroup_mx(&data)
... print group results ...
free(data.accu_set); /* free the memory allocated for the group results */
pm_delete_program()
}
(1) Each time data are got in time slice mode, the buffer allocated to return the counters */
must be freed after used.

```

### Simple thread counting-group with counter-multiplexing and multi-mode example:

The following example has two threads in a counting-group. The body of the auxiliary thread's initialization routine is the same as in the previous example.

This example is similar to the previous one except that it uses the multi-mode functionality, and associates a mode with each group counted.

```

main()
{
    pm_info2_t      pminfo;
    pm_groups_info_t pmginfo;
    pm_prog_mm_t   prog;
    pm_data_mx_t   data;
    pm_prog_t      prog_set[2];
    int filter = PM_VERIFIED; /* get list of verified events */
    pm_initialize(filter, &pminfo, &pmginfo, PM_CURRENT );
    prog.prog_set = prog_set;
    prog.nb_set_prog = 2; /* two groups counted */
    prog.slice_duration = 200; /* slice duration for each event group is 200ms */
    prog_set[0].mode.w = 0; /* start with clean mode */
    prog_set[0].mode.b.user = 1; /* grp 0: count only user mode */
    prog_set[0].mode.b.is_group = 1; /* specify event group */
    prog_set[0].mode.b.proctree = 1; /* turns process tree counting on:
                                     this option is common to all counted groups */
    prog_set[1].mode.w = 0; /* start with clean mode */
    prog_set[1].mode.b.kernel = 1; /* grp 1: count only kernel mode */
    prog_set[1].mode.b.is_group = 1; /* specify event group */
    for (i = 0; i < pminfo.maxpmcs; i++) {
        prog_set[0].events[i] = COUNT_NOTHING;
        prog_set[1].events[i] = COUNT_NOTHING;
    }
    prog_set[0].events[0] = 1; /* count events in group 1 in the first set */
    prog_set[1].events[0] = 3; /* count events in group 3 in the first set */
    pm_set_program_mygroup_mm(&prog); /* create counting group */
    pm_start_mygroup();
    pthread_create(&threadid, &attr, doit, NULL);
    pm_start_mythread();
    ... usefull work ....
    pm_stop_mythread();
    pm_get_data_mythread_mx(&data);
    printf ("Main thread results:\n");
    for (i = 0; i < 2 ; i++) {
        group_number = prog_set[i].events[0];
        printf ("Group #d: %s\n", group_number, pmginfo.event_groups[group_number].short_name);
        printf ("    counting time: %d ms\n", data.accu_set[i].accu_time);
        printf ("    counting values:\n");
    }
}

```

```

        for (counter = 0; counter < pminfo.maxpmcs; counter++) {
            printf ("event %d: %d\n", counter, data.accu_set[i].accu_data[counter]);
        }
    }
(1) free(data.accu_set); /* free the memory allocated for the main thread results */
pthread_join(threadid, &status);
... print auxiliary thread results ...
free(data.accu_set); /* free the memory allocated for the thread results */
pm_get_data_mygroup_mx(&data)
... print group results ...
free(data.accu_set); /* free the memory allocated for the group results */
pm_delete_program();
}
(1) Each time data are got in time slice mode, the buffer allocated to return the
counters must be freed after used.
}

```

### Thread counting example with reset:

The following example with a reset call illustrates the impact on the group data. The body of the auxiliary thread is the same as before, except for the **pm\_start\_mythread** call, which is not necessary in this case.

```

main()
{
    ... same initialization as in previous example...

    prog.mode.b.count = 1; /* start counting immediately */
    pm_set_program_mygroup(&prog);

    pthread_create(&threadid, pthread_attr_default, doit, NULL)

    ... usefull work ....

    pm_stop_mythread()
    pm_reset_data_mythread()

    pthread_join(threadid, &status);

    ...print auxiliary thread results...

    pm_get_data_mygroup(&data)

    ...print group results...
}

```

In the preceding example, the main thread and the group counting state are both on before the auxiliary thread is created, so the auxiliary thread will inherit that state and start counting immediately.

At the end, **data1** is equal to **data** because the **pm\_reset\_data\_mythread** automatically subtracted the main thread data from the group data to keep it consistent. In fact, the group data remains equal to the sum of the auxiliary and the main thread data, but in this case, the main thread data is null.

## The hpm library and associated tools

The hpm libraries are higher-level instrumentation libraries based on the pmapi library. They support multiple instrumentation sections, nested instrumentation, and each instrumented section can be called multiple times.

When nested instrumentation is used, exclusive duration is generated for the outer sections. Average and standard deviation is provided when an instrumented section is activated multiple times.

The libraries support OpenMP and threaded applications, which requires linking with the thread-safe version of the library, `libhpm_r`. Both 32-bit and 64-bit library modules are provided.

The libraries collect information and hardware Performance Monitor summarization during run-time. So, there could be considerable overhead if instrumentation sections are inserted inside inner loops.

## Compiling and linking

The functionality of the `libhpm_r` library depends upon the corresponding functions in the `libpmap` and `libm` libraries. Therefore, the `lpmap -lm` flag must be specified when compiling applications using the hpm libraries.

By default, argument passing from Fortran applications to the hpm libraries is done by reference, or pointer, not by value. Also, there is an extra length argument following character strings. You can modify the default argument passing method by using the `%VAL` and `%REF` built-in functions.

## Overhead and measurement error issues

It is expected for any software instrumentation to incur some overhead. Since it is not possible to eliminate the overhead, the goal is to minimize it. In the hpm library, most of the overhead is due to time measurement, which tends to be an expensive operation in most systems.

A second source of overhead is due to run-time accumulation and storage of performance data. The hpm libraries collect information and perform summarization during run-time. Hence, there could be a considerable amount of overhead if instrumentation sections are inserted inside inner loops.

The hpm library uses hardware counters during the initialization and finalization of the library, retaining the minimum of the two for each counter as an estimate of the cost of one call to the start and stop functions. The estimated overhead is subtracted from the values obtained on each instrumented code section, which ensures that the measurement of error becomes close to zero. However, since this is a statistical approximation, in some situations where estimated overhead is larger than a measured count for the application, the approach fails. When the approach fails, you might get the following error message, which indicates that the estimated overhead was not subtracted from the measured values:

```
WARNING: Measurement error for <event name> not removed
```

You can deactivate the procedure that attempts to remove measurement errors by setting the `HPM_WITH_MEASUREMENT_ERROR` environment variable to `TRUE (1)`.

## Common hpm library rules

Review common hpm library rules.

The following rules are common to the hpm library APIs:

- The `hpmInit()` or `f_hpmInit()` function must be called before any other function in the API.
- The initialization function can only be called once in an application.
- Performance Monitor contexts, like the event set, event group, or counter/event pairs, cannot be reprogrammed at any time.
- All functions of the API are specified as `void` and return no value or status.

## Overview of the hpm library API calls

The following table lists the hpm library API calls.

API Call	Purpose
<b>hpmInit</b> or <b>f_hpminit</b>	Performs initialization for a specified node ID and program name.
<b>hpmStart</b> or <b>f_hpmstart</b>	Indicates the beginning of an instrumented code segment, which is identified by an instrumentation identifier, InstID.
<b>hpmStop</b> or <b>f_hpmstop</b>	Indicates the end of an instrumented code segment. For each call to the <b>hpmStart()</b> or <b>f_hpmstart()</b> function, there should be a corresponding call to the <b>hpmStop()</b> or <b>f_hpmstop()</b> function with the matching instrumentation identifier.
<b>hpmTstart</b> or <b>f_hpmtstart</b>	Performs the same function as the <b>hpmStart()</b> and <b>f_hpmstart()</b> functions, but they are used in threaded applications.
<b>hpmTstop</b> or <b>f_hpmtstop</b>	Performs the same function as the <b>hpmStop()</b> and <b>f_hpmstop()</b> functions, but they are used in threaded applications.
<b>hpmGetTimeAndCounters</b> or <b>f_hpmgetttimeandcounters</b>	Returns the time, in seconds, and the accumulated counts since the call to the <b>hpmInit()</b> or <b>f_hpminit()</b> initialization function.
<b>hpmGetCounters</b> or <b>f_hpmgetcounter</b>	Returns all the accumulated counts since the call to the <b>hpmInit()</b> or <b>f_hpminit()</b> initialization function.
<b>hpmTerminate</b> or <b>f_hpmterminate</b>	Performs termination and generates output. If an application exits without calling the <b>hpmTerminate()</b> or <b>f_hpmterminate()</b> function, no performance information is generated.

## Threaded applications

The **T/tstart** and **T/tstop** functions respectively start and stop the counters independently on each thread. If two distinct threads use the same **instID** parameter, the output indicates multiple calls. However, the counts are accumulated.

The **instID** parameter is always a constant variable or integer. It cannot be an expression because the declarations in the **libhpm.h**, **f\_hpm.h**, and **f\_hpm\_i8.h** header files that contain **#define** statements are evaluated during the compiler pre-processing phase, which permits the collection of line numbers and source file names.

## Selecting events when using the hpm libraries and tools

The **hpm** libraries use the same set of hardware counters and events used by the **hpmcount** and **hpmstat** tools. The events are selected by sets. Sets are specially marked event groups for whichever derived metrics are available.

For the **hpm** libraries, you can select the event set to be used by any of the following methods:

- The **HPM\_EVENT\_SET** environment variable, which is either explicitly set in the environment or specified in the **HPM\_flags.env** file.
- The content of the **libHPMevents** file.

For the **hpmcount** and **hpmstat** commands, you can specify which event types you want to be monitored and the associated hardware performance counters by any of the following methods:

- Using the **-s** option
- The **HPM\_EVENT\_SET** environment variable, which you can set directly or define in the **HPM\_flags.env** file
- The content of the **libHPM\_events** file

In all cases, the **HPM\_flags.env** file takes precedence over the explicit setting of the **HPM\_EVENT\_SET** environment variable and the content of the **libHPMevents** or **libHPM\_events** file takes precedence over the **HPM\_EVENT\_SET** environment variable.

An event group can be specified instead of an event set, using any of the following methods:

- The **-g** option
- The **HPM\_EVENT\_GROUP** environment variable that you can set directly or define in the **HPM\_flags.env** file

In all cases, the **HPM\_flags.env** file takes precedence over the explicit setting of the **HPM\_EVENT\_GROUP** environment variable. The **HPM\_EVENT\_GROUP** environment variable takes precedence over the explicit setting of the **HPM\_EVENT\_SET** environment variable. The **HPM\_EVENT\_GROUP** is a comma separated list of group names or group numbers.

A list of derived metric groups to be evaluated can be specified, using any of the following methods:

- The **-m** option
- The **HPM\_PMD\_GROUP** environment variable that you can set directly or define in the **HPM\_flags.env** file

In all cases, the **HPM\_flags.env** file take precedence over the explicit setting of the **HPM\_PMD\_GROUP** environment variable. The **HPM\_PMD\_GROUP** is a comma-separated list of derived metric group names.

Each set, group or derived metric group can be qualified by a counting mode. The allowed counting modes are:

- u: user mode
- k: kernel mode
- h: hypervisor mode
- r: runlatch mode
- n: nointerrupt mode

The counting mode qualifier is separated from the set or group by a colon ":". For example:

```
HPM_EVENT_GROUP=pm_utilization:uk,pm_completion:u
```

To use the time slice functionality, specify a comma-separated list of sets instead of a single set number. By default, the time slice duration for each set is 100 ms, but this can be modified with the **HPM\_MX\_DURATION** environment variable. This value must be expressed in ms, and in the range 10 ms to 30000 ms.

#### The libHPMevents and libHPM\_events files:

The **libHPMevents** and **libHPM\_events** files are both supplied by the user and have the same format.

For POWER3 or PowerPC 604 RISC Microprocessor systems, the file contains the counter number and the event name, like in the following example:

```
0 PM_LD_MISS_L2HIT
1 PM_TAG_BURSTRD_L2MISS
2 PM_TAG_ST_MISS_L2
3 PM_FPU0_DENORM
4 PM_LSU_IDLE
5 PM_LQ_FULL
6 PM_FPU_FMA
7 PM_FPU_IDLE
```

For POWER4 and later systems, the file contains the event group name, like in the following example:

```
pm_hpmcount1
```

#### The HPM\_flags.env file:

The **HPM\_flags.env** file contains environment variables that are used to specify the event set and for the computation of derived metrics

## Example

```
HPM_L2_LATENCY 12
HPM_EVENT_SET 5
```

## Output files of the hpm library

When the `hpmTerminate` function is called, a summary report is written to the `<progName>_<pid>_<taskID>.hpm` file, by default. The `taskID` and `progName` values are the first and second parameters of the `hpmInit()` function, respectively.

You can define the name of the output file with the `HPM_OUTPUT_NAME` environment variable. The `hpm` libraries always add the `_<taskID>.hpm` suffix to the specified value. You can also include the date and time in the file name using the `HPM_OUTPUT_NAME` environment variable. For example, if you use the following code:

```
MYDATE=$(date +"m%d:2/2/06M%S")
export HPM_OUTPUT_NAME=myprogram_$MYDATE
```

the output file for task 27 is named `myprogram_yyyymmdd:HHMMSS_0027.hpm`.

You can also generate an XML output file by setting the `HPM_VIZ_OUTPUT=TRUE` environment variable. The generated output files are named either `<progName>_<pid>_<taskID>.viz` or `HPM_OUTPUT_NAME_<taskID>.viz`.

## Output files of the hpmcount command

The output file for the `hpmcount` command depend on the environment variables set and the execution environment.

The following are the output files of the `hpmcount` command:

### File name

#### Description

#### `file_<myID>.<pid>`

The value for *file* is specified with the `-o` option and the *myID* value is assigned the value of the `MP_CHILD` environment variable, which has a default value of 0000.

#### `HPM_LOG_DIR/hpm_log.<pid>`

When the `HPM_LOG_DIR` environment variable is set to an existing directory, results are additionally written to the `hpm_log.<pid>` file.

#### `HPM_LOG_DIR/hpm_log.MP_PARTITION`

The `MP_PARTITION` environment variable is provided in POE environments. The `hpm_log.MP_PARTITION` file contains the aggregate counts.

An XML output can be provided by using the `-x` option.

An alternative time base for the result normalization can be selected using any of the following methods:

- The `-b time|purr|spurr` option
- The `HPM_NORMALIZE` environment variable that you can set directly or define in the `HPM_flags.env` file

## Derived metrics and related environment variables

In relation to the hardware events that are selected to be counted and the hardware platform that is used, the output for the `hpm` library tools and the `hpmterminate` function includes derived metrics.

You can list the globally supported metrics for a given processor with the `pmlist -D -1 [-p Processor_name]` command.

You can supply the following environment variables to specify estimations of memory, cache, and TLB miss latencies for the computation of related derived metrics:

- HPM\_MEM\_LATENCY
- HPM\_L3\_LATENCY
- HPM\_L35\_LATENCY
- HPM\_AVG\_L3\_LATENCY
- HPM\_AVG\_L2\_LATENCY
- HPM\_L2\_LATENCY
- HPM\_L25\_LATENCY
- HPM\_L275\_LATENCY
- HPM\_L1\_LATENCY
- HPM\_TLB\_LATENCY

Precedence is given to variables that are defined in the **HPM\_flags.env** file.

You can use the **HPM\_DIV\_WEIGHT** environment variable to compute the weighted flips on systems that are POWER4 and later.

## Examples of the hpm tools

The examples in this section demonstrate the usage of the following hpm library commands:

### The pmlist command:

The following is an example of the **pmlist** command on a POWER5 processor-based system.

```
# pmlist -s

POWER5 supports 6 counters

Number of groups      : 144
Number of sets       : 8

Threshold multiplier (lower): 1
Threshold multiplier (upper): 32
Threshold multiplier (hyper): 64
Hypervisor counting mode is supported
Runlatch counting mode is supported
```

The following is another example of the **pmlist** command:

```
# pmlist -D -1 -p POWER5
Derived metrics supported:
PMD_UTI_RATE           Utilization rate
PMD_MIPS               MIPS
PMD_INST_PER_CYC      Instructions per cycle
PMD_HW_FP_PER_CYC     HW floating point instructions per Cycle
PMD_HW_FP_PER_UTIME   HW floating point instructions / user time
PMD_HW_FP_RATE        HW floating point rate
PMD_FX                Total Fixed point operations
PMD_FX_PER_CYC        Fixed point operations per Cycle
PMD_FP_LD_ST          Floating point load and store operations
PMD_INST_PER_FP_LD_ST Instructions per floating point load/store
PMD_PRC_INST_DISP_CMPL % Instructions dispatched that completed
PMD_DATA_L2           Total L2 data cache accesses
PMD_PRC_L2_ACCESS     % accesses from L2 per cycle
PMD_L2_TRAF           L2 traffic
PMD_L2_BDW            L2 bandwidth per processor
PMD_L2_LD_EST_LAT_AVG Estimated latency from loads from L2 (Average)
PMD_UTI_RATE_RC       Utilization rate (versus run cycles)
PMD_INST_PER_CYC_RC   Instructions per run cycle
PMD_LD_ST             Total load and store operations
```

PMD_INST_PER_LD_ST	Instructions per load/store
PMD_LD_PER_LD_MISS	Number of loads per load miss
PMD_LD_PER_DTLB	Number of loads per DTLB miss
PMD_ST_PER_ST_MISS	Number of stores per store miss
PMD_LD_PER_TLB	Number of loads per TLB miss
PMD_LD_ST_PER_TLB	Number of load/store per TLB miss
PMD_TLB_EST_LAT	Estimated latency from TLB miss
PMD_MEM_LD_TRAFF	Memory load traffic
PMD_MEM_BDW	Memory bandwidth per processor
PMD_MEM_LD_EST_LAT	Estimated latency from loads from memory
PMD_LD_LMEM_PER_LD_RMEM	Number of loads from local memory per loads from remote memory
PMD_PRC_MEM_LD_RC	% loads from memory per run cycle

## The hpmcount command:

The following is example output from the of the **hpmcount** command.

```
# hpmcount -m cpi_breakdown ls
bar      foo
Workload context: ls (pid:42234)
Execution time (wall clock time): 0.004222 seconds
##### Resource Usage Statistics #####
Total amount of time in user mode      : 0.001783 seconds
Total amount of time in system mode    : 0.000378 seconds
Maximum resident set size              : 220 Kbytes
Average shared memory use in text segment : 0 Kbytes*sec
Average unshared memory use in data segment : 0 Kbytes*sec
Number of page faults without I/O activity : 63
Number of page faults with I/O activity  : 0
Number of times process was swapped out  : 0
Number of times file system performed INPUT : 0
Number of times file system performed OUTPUT : 0
Number of IPC messages sent             : 0
Number of IPC messages received         : 0
Number of signals delivered              : 0
Number of voluntary context switches    : 0
Number of involuntary context switches   : 0
##### End of Resource Statistics #####
Counting mode: user
PM_1PLUS_PPC_CMPL (One or more PPC instruction completed) : 143749896
PM_GCT_EMPTY_CYC (Cycles GCT empty) : 12905400
PM_GRP_CMPL (Group completed) : 144626424
PM_CYC (Processor cycles) : 434717274
PM_INST_CMPL (Instructions completed) : 193121895
PM_RUN_CYC (Run cycles) : 378397903
PM_GCT_NOSLOT_CYC (Cycles no GCT slot allocated) : 87592746
PM_GCT_NOSLOT_IC_MISS : 16066248
  (No slot in GCT caused by I cache miss)
PM_GCT_NOSLOT_SRQ_FULL (No slot in GCT caused by SRQ full) : 0
PM_GCT_NOSLOT_BR_MPRED : 27869700
  (No slot in GCT caused by branch mispredict)
PM_GRP_MRK (Group marked in IDU) : 6041616
PM_CMPLU_STALL_LSU : 117973392
  (Completion stall caused by LSU instruction)
PM_IOPS_CMPL (Internal operations completed) : 162398665
PM_CMPLU_STALL_REJECT (Completion stall caused by reject) : 24318036
PM_CMPLU_STALL_DCACHE_MISS : 25055262
  (Completion stall caused by D cache miss)
PM_CMPLU_STALL_ERAT_MISS : 17332764
  (Completion stall caused by ERAT miss)
PM_GRP_IC_MISS_BR_REDIR_NONSPEC : 2551038
  (Group experienced non-speculative I cache miss or branch redirect)
PM_CMPLU_STALL_FXU : 69575412
  (Completion stall caused by FXU instruction)
PM_CMPLU_STALL_DIV : 45664068
  (Completion stall caused by DIV instruction)
PM_FPU_FULL_CYC (Cycles FPU issue queue full) : 27660
```

```

PM_CMPLU_STALL_FDIV                               :          319104
  (Completion stall caused by FDIV or FQRT instruction)
PM_CMPLU_STALL_FPU                               :          500274
  (Completion stall caused by FPU instruction)
Derived metric group: cpi_breakdown
Total cycles                                     : 2.250999
  Completion cycles                             : 0.748887
  Completion Table empty (GCT empty)           : 0.266825
    I-Cache Miss Penalty                       : 0.083192
    Branch Mispredication Penalty              : 0.144311
    Others GCT stalls                          : 0.039322
  Completion Stall cycles                       : 1.435288
    Stall by LSU instruction                   : 0.610875
      Stall by LSU Reject                     : 0.125921
        Stall by LSU Translation Reject        : 0.089750
        Stall by LSU Other Reject              : 0.036170
      Stall by LSU D-cache miss                : 0.129738
        Stall by LSU basic latency, LSU Flush penalty : 0.355217
    Stall by FXU instruction                   : 0.360267
      Stall by any form of DIV/MTSPR/MFSPR instruction : 0.236452
      Stall by FXU basic latency               : 0.123815
    Stall by FPU instruction                   : 0.002590
      Stall by any form of FDIV/FSQRT instruction : 0.001652
      Stall by FPU basic latency               : 0.000938
    Stall by others                           : 0.462493

```

### The hpmstat command:

The following is an example output from the **hpmstat** command.

```

# hpmstat -s 7
Execution time (wall clock time): 1.003946 seconds
Counting mode: user
PM_TLB_MISS (TLB misses)                       :          260847
PM_CYC (Processor cycles)                       :       3013964331
PM_ST_REF_L1 (L1 D cache store references)     :       161377371
PM_LD_REF_L1 (L1 D cache load references)      :       255317480
PM_INST_CMPL (Instructions completed)          :       1027391919
PM_RUN_CYC (Run cycles)                        :       1495147343
Derived metric group: default
Utilization rate                               :          181.243 %
Total load and store operations                 :          416.695 M
Instructions per load/store                     :           2.466
MIPS                                           :          1023.354
Instructions per cycle                         :           0.341

```

The following is an example of the **hpmstat** command with counter multiplexing:

```

# hpmstat -s 1,2 -d
Execution time (wall clock time): 2.129755 seconds
Set: 1
Counting duration: 1.065 seconds
PM_INST_CMPL (Instructions completed)           :          244687
PM_FPU1_CMPL (FPU1 produced a result)         :              0
PM_ST_CMPL (Store instruction completed)       :          31295
PM_LD_CMPL (Loads completed)                  :          67414
PM_FPU0_CMPL (Floating-point unit produced a result) :          19
PM_CYC (Processor cycles)                     :          295427
PM_FPU_FMA (FPU executed multiply-add instruction) :              0
PM_TLB_MISS (TLB misses)                     :           788
Set: 2
Counting duration: 1.064 seconds
PM_TLB_MISS (TLB misses)                       :          379472
PM_ST_MISS_L1 (L1 D cache store misses)       :          79943
PM_LD_MISS_L1 (L1 D cache load misses)        :          307338
PM_INST_CMPL (Instructions completed)          :          848578245
PM_LSU_IDLE (Cycles LSU is idle)              :          229922845

```

```

PM_CYC (Processor cycles) : 757442686
PM_ST_DISP (Store instructions dispatched) : 125440562
PM_LD_DISP (Load instr dispatched) : 258031257
Counting mode: user
PM_TLB_MISS (TLB misses) : 380260
PM_ST_MISS_L1 (L1 D cache store misses) : 160017
PM_LD_MISS_L1 (L1 D cache load misses) : 615182
PM_INST_CMPL (Instructions completed) : 848822932
PM_LSU_IDLE (Cycles LSU is idle) : 460224933
PM_CYC (Processor cycles) : 757738113
PM_ST_DISP (Store instructions dispatched) : 251088030
PM_LD_DISP (Load instr dispatched) : 516488120
PM_FPU1_CMPL (FPU1 produced a result) : 0
PM_ST_CMPL (Store instruction completed) : 62582
PM_LD_CMPL (Loads completed) : 134812
PM_FPU0_CMPL (Floating-point unit produced a result) : 38
PM_FPU_FMA (FPU executed multiply-add instruction) : 0
Derived metric group: default
Utilization rate : 189.830 %
% TLB misses per cycle : 0.050 %
number of loads per TLB miss : 0.355
Total L2 data cache accesses : 0.775 M
% accesses from L2 per cycle : 0.102 %
L2 traffic : 47.276 MBytes
L2 bandwidth per processor : 44.431 MBytes/sec
Total load and store operations : 0.197 M
Instructions per load/store : 4300.145
number of loads per load miss : 839.569
number of stores per store miss : 1569.133
number of load/stores per D1 miss : 990.164
L1 cache hit rate : 0.999 %
% Cycles LSU is idle : 30.355 %
MIPS : 199.113
Instructions per cycle : 1.120

```

## Examples of hpm library usage

The following are examples of hpm library usage:

### A C programming language example:

The following C program contains two instrumented sections which perform a trivial floating point operation, print the results, and then launch the command interpreter to execute the `ls -R / 2>&1 >/dev/null` command.

```

#include <sys/wait.h>
#include <unistd.h>
#include <stdio.h>
#include <libhpm.h>

void
do_work()
{
    pid_t p, wpid;
    int i, status;
    float f1 = 9.7641, f2 = 2.441, f3 = 0.0;

    f3 = f1 / f2;
    printf("f3=%f\n", f3);

    p = fork();

    if (p == -1) {
        perror("Mike fork error");
        exit(1);
    }
}

```

```

    if (p == 0) {
        i = execl("/usr/bin/sh", "sh", "-c", "ls -R / 2>&1 >/dev/null", 0);
        perror("Mike execl error");
        exit(2);
    }
    else
        wpid = waitpid(p, &status, WUNTRACED | WCONTINUED);

    if (wpid == -1) {
        perror("Mike waitpid error");
        exit(3);
    }

    return;
}

main(int argc, char **argv)
{
    int taskID = 999;

    hpmInit(taskID, "my_program");
    hpmStart(1, "outer call");
    do_work();
    hpmStart(2, "inner call");
    do_work();
    hpmStop(2);
    hpmStop(1);
    hpmTerminate(taskID);
}

```

### A Fortran programming language example:

The following declaration is required on all source files that have instrumentation calls.

```
#include "f_hpm.h"
```

Fortran programs call functions that include the `f_` prefix, as you can see in the following example:

```

call f_hpminit( taskID, "my_program" )
call f_hpmstart( 1, "Do Loop" )
do ...
    call do_work()
    call f_hpmstart( 5, "computing meaning of life" );
    call do_more_work();
    call f_hpmstop( 5 );
end do
call f_hpmstop( 1 )
call f_hpmterminate( taskID )

```

### Multithreaded application instrumentation example:

When placing instrumentation inside of parallel regions, you should use a different ID for each thread.

The following is an example multithreaded application instrumentation:

```

!$OMP PARALLEL
!$OMP&PRIVATE (instID)
    instID = 30+omp_get_thread_num()
    call f_hpmtstart( instID, "computing meaning of life" )
!$OMP DO
    do ...
        do_work()
    end do
    call f_hpmtstop( instID )
!$OMP END PARALLEL

```

The library accepts the use of the same `instID` for different threads, but the counters are accumulated for all instances with the same `instID`.

---

## Perfstat API programming

The **perfstat** application programming interface (API) is a collection of C programming language subroutines that is used in user space. It uses the **perfstat** kernel extension to extract various AIX performance metrics.

System component information is also retrieved from the Object Data Manager (ODM) and returned with the performance metrics.

The **perfstat** API is thread-safe, and does not require root authority.

The API supports extensions so binary compatibility is maintained across all releases of AIX. This interface is accomplished by using one of the parameters in all the API calls to specify the size of the data structure to be returned. The interface permits the library to determine the version it is using, using the structures that are growing. It helps the user from being dependent on the different versions. For the list of extensions in earlier versions of AIX, see the Change History section.

The **perfstat** API subroutines are present in the **libperfstat.a** library that are part of the **bos.perf.libperfstat** file set, which is installable from the AIX base installation media and requires that the **bos.perf.perfstat** file set is installed. The latter contains the kernel extension and is automatically installed with AIX.

The `/usr/include/libperfstat.h` file contains the interface declarations and type definitions of the data structures to use when calling the interfaces. The `include` file is also part of the **bos.perf.libperfstat** file set. Sample source code is provided with **bos.perf.libperfstat** file set and is present in the `/usr/samples/libperfstat` directory.

### Related information:

`libperfstat.h` command

## API characteristics

Five types of APIs are available. Global types return global metrics related to a set of components, while individual types return metrics related to individual components. Both types of interfaces have similar signatures, but slightly different behavior.

AIX supports different types of APIs such as WPAR and RSET. WPAR types return usage metrics related to a set of components or individual components specific to a workload partition (WPAR). RSET types return usage metrics of processors that belong to an RSET. With AIX Version 6.1 Technology Level (TL) 6, a new type of APIs, called as NODE is available. The NODE types return usage metrics that are related to a set of components or individual components specific to a remote node in a cluster. The `perfstat_config` (`PERFSTAT_ENABLE | PERFSTAT_CLUSTER_STATS, NULL`) must be used to enable the remote node statistics collection (that is available in a cluster environment).

All the interfaces return raw data; that is, values of running counters. Multiple calls must be made at regular intervals to calculate rates.

Several interfaces return data retrieved from the ODM (object data manager) database. This information is automatically cached into a dictionary that is assumed to be "frozen" after it is loaded. The **perfstat\_reset** subroutine must be called to clear the dictionary whenever the system configuration has changed. In order to do a more selective reset, you can use the **perfstat\_partial\_reset** function. For more details, see the "Cached metrics interfaces" on page 200 section.

Most types returned are unsigned long long; that is, unsigned 64 bit data.

Excessive and redundant calls to Perfstat APIs in a short time span can have a performance impact because time-consuming statistics collected by them are not cached.

For examples of API characteristics, see the sample programs in the `/usr/samples/libperfstat` directory. All of the sample programs can be compiled using the provided makefile (`/usr/samples/libperfstat/Makefile.samples`).

## Global interfaces

Global interfaces report metrics related to a set of components on a system (such as processors, disks, or memory).

The following are the global interfaces:

Item	Descriptor
<code>perfstat_cpu_total</code>	Retrieves global processor usage metrics
<code>perfstat_memory_total</code>	Retrieves global memory usage metrics
<code>perfstat_disk_total</code>	Retrieves global disk usage metrics <b>Note:</b> This API does not return any data when started from an application running inside WPAR.
<code>perfstat_netinterface_total</code>	Retrieves global network interfaces metrics <b>Note:</b> This API does not return any data when started from an application running inside WPAR.
<code>perfstat_partition_config</code>	Retrieves Operating System and partition related information
<code>perfstat_partition_total</code>	Retrieves global partition metrics
<code>perfstat_tape_total</code>	Retrieves global tape usage metrics <b>Note:</b> This API does not return any data when started from an application running inside WPAR.

The common signature used by all of the global interfaces is as follows:

```
int perfstat_subsystem_total(perfstat_id_t *name,
                           perfstat_subsystem_total_t *userbuff,
                           int sizeof_struct,
                           int desired_number);
```

The usage of the parameters for all of the interfaces is as follows:

Item	Descriptor
<code>perfstat_id_t *name</code>	Reserved for future use, must be NULL
<code>perfstat_subsystem_total_t *userbuff</code>	A pointer to a memory area with enough space for the returned structure
<code>int sizeof_struct</code>	Should be set to <code>sizeof(perfstat_subsystem_t)</code>
<code>int desired_number</code>	Reserved for future use, must be set to 0 or 1

The return value is -1 in case of errors. Otherwise, the number of structures copied is returned. This is always 1.

The following sections provide examples of the type of data returned and code using each of the interfaces.

The following code shows an example of how `perfstat_netinterface_total` is used:

```
#include <stdio.h>
#include <libperfstat.h>

int main(int argc, char* argv[]) {
    perfstat_netinterface_total_t ninfo;
    int rc;
    rc = perfstat_netinterface_total(NULL, &ninfo, sizeof(perfstat_netinterface_total_t), 1);
    if (rc != 1)
    {
        perror("perfstat_netinterface_total");
        exit(-1);
    }
}
```

```

perfstat_netinterface_total(NULL, &ninfo, sizeof(perfstat_netinterface_total_t), 1);

printf("Network interfaces statistics\n");
printf("-----\n");
printf("number of interfaces : %d\n", ninfo.number);
printf("\ninput statistics:\n");
printf("number of packets   : %llu\n", ninfo.ipackets);
printf("number of errors     : %llu\n", ninfo.ierrors);
printf("number of bytes      : %llu\n", ninfo.ibytes);
printf("\noutput statistics:\n");
printf("number of packets   : %llu\n", ninfo.opackets);
printf("number of bytes      : %llu\n", ninfo.obytes);
printf("number of errors     : %llu\n", ninfo.oerrors);
}

```

The program produces output similar to the following:

```

Network interfaces statistics
-----
number of interfaces : 2

input statistics:
number of packets   : 306688
number of errors     : 0
number of bytes      : 24852688

output statistics:
number of packets   : 63005
number of bytes      : 11518591
number of errors     : 0

```

The preceding program emulates **ifstat's** behavior and also shows how **perfstat\_netinterface\_total** is used.

## perfstat\_cpu\_total Interface

The **perfstat\_cpu\_total** interface returns a **perfstat\_cpu\_total\_t** structure, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_cpu\_total\_t** structure include:

Item	Descriptor
<b>purrr_coalescing</b>	PURR cycles consumes coalescing data if the calling partition is authorized to see pool wide statistics, else set to zero.
<b>spurr_coalescing</b>	SPURR cycles consumes coalescing data if the calling partition is authorized to see pool wide statistics, else set to zero.
<b>processorHz</b>	Processor speed in Hertz (from ODM)
<b>description</b>	Processor type (from ODM)
<b>CPUs</b>	Current number of active processors
<b>ncpus_cfg</b>	Number of configured processors; that is, the maximum number of processors that this copy of AIX can handle simultaneously
<b>ncpus_high</b>	Maximum number of active processors; that is, the maximum number of active processors since the last reboot
<b>user</b>	Number of clock ticks spent in user mode
<b>sys</b>	Number of clock ticks spent in system (kernel) mode
<b>idle</b>	Number of clock ticks spent idle with no I/O pending
<b>wait</b>	Number of clock ticks spent idle with I/O pending

**Note:** Page coalescing is a transparent operation wherein the hypervisor detects duplicate pages, directs all user reads to a single copy, and reclaims the other duplicate physical memory pages. Several other processor-related counters (such as number of system calls, number of reads, write, forks, execs, and load average) are also returned. For a complete list, see the **perfstat\_cpu\_total\_t** section of the **libperfstat.h** header file.

The following program emulates **Iparstat's** behavior and also shows an example of how the **perfstat\_cpu\_total** interface is used:

```

#include <stdio.h>
#include <sys/time.h>
#include <sys/errno.h>
#include <sys/proc.h>
#include <wpar/wparcfg.h>
#include <libperfstat.h>
#include <stdlib.h>

/* default values for interval and count */
#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1

/* values for wpar status */
#define ACTIVE 0
#define NOTACTIVE 1

/* Check value returned by malloc for NULL */
#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
    perror ("malloc");\
    exit(2);\
}\
}

/* Non zero WPAR ID indicates WPAR */
#define IS_WPAR(X) ((X))

/* stores wpar id for perfstat library */
perfstat_id_wpar_t wparid;
perfstat_wpar_total_t wparinfo;
perfstat_wpar_total_t *wparlist;

/*Corral id for WPAR */
cid_t cid;

int interval = INTERVAL_DEFAULT, count = COUNT_DEFAULT;
int totalwpar, activewpar; /* to store and number of wpars available and active wpars */

/*
 *Name: do_cleanup
 * free all allocated data structures
 */
void do_cleanup(void)
{
    if (wparlist)
        free(wparlist);
}

/*
 *Name: display_global_sysinfo_stat
 * Function used when called from global.
 * Gets all the system metrics using perfstat APIs and displays them
 */
void display_global_sysinfo_stat(void)
{
    perfstat_cpu_total_t *cpustat, *cpustat_last;
    perfstat_id_t first;

    /* allocate memory for data structures and check for any error */
    cpustat = (perfstat_cpu_total_t *)malloc(sizeof(perfstat_cpu_total_t));
    CHECK_FOR_MALLOC_NULL(cpustat);

    cpustat_last = (perfstat_cpu_total_t *)malloc(sizeof(perfstat_cpu_total_t));
    CHECK_FOR_MALLOC_NULL(cpustat_last);

    /* get the system wide statistics */
    if (perfstat_cpu_total(NULL, cpustat_last, sizeof(perfstat_cpu_total_t), 1) <= 0){
        perror("perfstat_cpu_total ");
        exit(1);
    }

    printf ("%10s %10s %10s\n", "cswch", "scalls", "sread", "swrite", "fork", "exec",
        "rchar", "wchar", "deviceint", "bwrite", "bread", "phread");
    printf ("%10s %10s %10s\n", "====", "====", "====", "====", "====", "====",
        "====", "====", "====", "====", "====", "====");
    while (count > 0){
        sleep(interval);
        if (perfstat_cpu_total(NULL, cpustat, sizeof(perfstat_cpu_total_t), 1) <= 0){
            perror("perfstat_cpu_total ");
            exit(1);
        }
        /* print the difference between the old structure and new structure */
        printf("%10llu %10llu %10llu\n", (cpustat->pswitch - cpustat_last->pswitch),
            (cpustat->syscall - cpustat_last->syscall), (cpustat->sysread - cpustat_last->sysread),
            (cpustat->syswrite - cpustat_last->syswrite), (cpustat->sysfork - cpustat_last->sysfork),
            (cpustat->sysexec - cpustat_last->sysexec), (cpustat->readch - cpustat_last->readch),
            (cpustat->writch - cpustat_last->writch), (cpustat->devintrs - cpustat_last->devintrs),
            (cpustat->bwrite - cpustat_last->bwrite), (cpustat->bread - cpustat_last->bread),
            (cpustat->phread - cpustat_last->phread));
        count--;
    }
}

```

```

        /*copy the present structure to the old structure */
        memcpy(cpustat_last , cpustat , sizeof(perfststat_cpu_total_t));
    }
    /* free the memory allocated for the data structures */
    free(cpustat);
    free(cpustat_last);
}

/*
 *Name: display_wpar_sysinfo_stat
 *   Displays both wpar and global metrics
 */

void display_wpar_sysinfo_stat(void)
{
    perfstat_wpar_total_t wparinfo;
    perfstat_cpu_total_wpar_t cinfo_wpar, cinfo_wpar_last;
    perfstat_cpu_total_t sysinfo, sysinfo_last;

    /* ste the spec and pass the wparname */
    wparid.spec = WPARNAME;
    strcpy(wparid.u.wparname, NULL);

    /* save the number of wpars which are active */
    activewpar = perfstat_wpar_total( NULL , &wparinfo ,sizeof(perfststat_wpar_total_t), 1);

    /* if the activewpar is less than zero exit with a perror */
    if (activewpar < 0){
        perror("perfstat_wpar_total :");
        exit(1);
    }

    /* if the wpar is not active exit with a message */
    if (activewpar == 0){
        printf("wpar not active \n");
        exit(1);
    }

    /* get the wpar wide cpu information */
    if (perfstat_cpu_total_wpar(NULL, &cinfo_wpar_last, sizeof(perfststat_cpu_total_wpar_t), 1) <=0){
        perror("perfstat_cpu_total_wpar :");
        exit(1);
    }
    if (perfstat_cpu_total(NULL , &sysinfo_last, sizeof(perfststat_cpu_total_t), 1) <=0){
        perror("perfstat_cpu_total_wpar :");
        exit(1);
    }
    printf("%10s %10s %10s %10s %10s %10s %10s %10s\n",wparname , "cswch" , "syscalls", "fork","runque" , "swpque" , "runocc" , "swpocc" );
    printf("%10s %10s %10s %10s %10s %10s %10s %10s\n","=====" , "=====" , "=====" , "=====" , "=====" , "=====" , "=====" , "=====" );

    while (count > 0){
        sleep(interval);
        if (perfstat_cpu_total_wpar( NULL,&cinfo_wpar, sizeof(perfststat_cpu_total_wpar_t), 1) <=0){
            perror("perfstat_cpu_total_wpar :");
            exit(1);
        }
        if (perfstat_cpu_total(NULL, &sysinfo, sizeof(perfststat_cpu_total_t), 1) <=0){
            perror("perfstat_cpu_total :");
            exit(1);
        }

        /* display the difference between the current and old structure for the current wpar and system wide values*/
        printf("%10s %10llu %10llu %10llu %10llu %10llu %10llu %10llu\n",wparinfo.name, (cinfo_wpar.pswitch - cinfo_wpar_last.pswitch),
        (cinfo_wpar.syscall - cinfo_wpar_last.syscall), (cinfo_wpar.sysfork - cinfo_wpar_last.sysfork),
        (cinfo_wpar.runque - cinfo_wpar_last.runque), (cinfo_wpar.swpque - cinfo_wpar_last.swpque),
        (cinfo_wpar.runocc - cinfo_wpar_last.runocc), (cinfo_wpar.swpocc - cinfo_wpar_last.swpocc));

        printf("%10s %10llu %10llu %10llu %10llu %10llu %10llu %10llu\n", "Global", (sysinfo.pswitch - sysinfo_last.pswitch),
        (sysinfo.syscall - sysinfo_last.syscall), (sysinfo.sysfork - sysinfo_last.sysfork),
        (sysinfo.runque - sysinfo_last.runque), (sysinfo.swpque - sysinfo_last.swpque),
        (sysinfo.runocc - sysinfo_last.runocc), (sysinfo.swpocc - sysinfo_last.swpocc));
        count--;

        /* copy the data to the old structure */
        memcpy(&cinfo_wpar_last, &cinfo_wpar, sizeof(perfststat_wpar_total_t));
        memcpy(&sysinfo_last , &sysinfo , sizeof(perfststat_cpu_total_t));
    }
}

/* Name: display_wpar_total_sysinfo_stat
 *   displays statistics of individual wpar
 */

int display_wpar_total_sysinfo_stat(void)
{
    int i, *status;
    perfstat_wpar_total_t *wparinfo;
    perfstat_cpu_total_wpar_t *cinfo_wpar, *cinfo_wpar_last;

    /* allocate memory for the datastructures and check for any error */
    status = (int *) calloc(totalwpar ,sizeof(int));
    CHECK_FOR_MALLOC_NULL(status);

    cinfo_wpar = (perfstat_cpu_total_wpar_t *) malloc(sizeof (perfstat_cpu_total_wpar_t) * totalwpar);
    CHECK_FOR_MALLOC_NULL(cinfo_wpar);

    cinfo_wpar_last = (perfstat_cpu_total_wpar_t *) malloc(sizeof (perfstat_cpu_total_wpar_t) * totalwpar);
    CHECK_FOR_MALLOC_NULL(cinfo_wpar_last);

    wparlist = (perfstat_wpar_total_t *) malloc(sizeof(perfststat_wpar_total_t) * totalwpar);
    CHECK_FOR_MALLOC_NULL(wparlist);
}

```

```

activewpar = perfstat_wpar_total(&wparid, wparlist, sizeof(perfstat_wpar_total_t), totalwpar);

if (activewpar < 0){
    perror("perfstat_wpar_total :");
    exit(1);
}

/* If no active wpars exit with a message */
if (activewpar == 0){
    printf("no active wpars found \n");
    exit(1);
}
for (i = 0; i < activewpar; i++){
    /* copy the wparname into wparid and collect the data for all active wpars */
    strcpy(wparid.u.wparname, wparlist[i].name);
    if (perfstat_cpu_total_wpar(&wparid, &cinfo_wpar_last[i], sizeof(perfstat_cpu_total_wpar_t), 1) <= 0){
        status[i] = NOTACTIVE;
        continue;
    }
}
/*print the headers */
printf("%20s %12s %12s %12s %12s %12s %12s %12s\n", "wparname", "cswitch", "fork", "runque", "swpque", "runocc", "swpocc", "syscalls");
printf("%20s %12s %12s %12s %12s %12s %12s %12s\n", "=====", "=====", "=====", "=====", "=====", "=====", "=====", "=====");

while (count > 0){
    sleep(interval);
    for (i = 0; i < activewpar; i++){
        strcpy(wparid.u.wparname, wparlist[i].name);
        if (perfstat_cpu_total_wpar(&wparid, &cinfo_wpar[i], sizeof(perfstat_cpu_total_wpar_t), 1) <= 0){
            status[i] = NOTACTIVE;
            continue;
        }
    }
    /* print the data for all active wpars */
    for (i = 0; i < activewpar; i++){
        if(status[i] == ACTIVE)
            printf("%20s %12llu %12llu %12llu %12llu %12llu %12llu\n", wparlist[i].name,
                (cinfo_wpar[i].pswitch - cinfo_wpar_last[i].pswitch), (cinfo_wpar[i].sysfork - cinfo_wpar_last[i].sysfork),
                (cinfo_wpar[i].runque - cinfo_wpar_last[i].runque), (cinfo_wpar[i].swpque - cinfo_wpar_last[i].swpque),
                (cinfo_wpar[i].runocc - cinfo_wpar_last[i].runocc), (cinfo_wpar[i].swpocc - cinfo_wpar_last[i].swpocc),
                (cinfo_wpar[i].syscall - cinfo_wpar_last[i].syscall));
        }
        printf("\n");
        count--;
        memcpy(cinfo_wpar_last, cinfo_wpar, (totalwpar * sizeof(perfstat_cpu_total_wpar_t)));
    }
    /* free all the memory structures */
    free(cinfo_wpar);
    free(cinfo_wpar_last);
    free(status);
}

/*
*Name: showusage
* displays the usage message
*/

void showusage()
{
    if (!cid)
        printf("Usage:simplesysinfo [-@ { ALL | WPARNAME }] [interval] [count]\n ");
    else
        printf("Usage:simplesysinfo [interval] [count]\n");
}

exit(1);
}

/* NAME: main
* This function determines the interval, iteration count.
* Then it calls the corresponding functions to display
* the corresponding metrics
*/

int main(int argc, char* argv[])
{
    int rc, atflag = 0, c;
    char wpar[MAXCORRALNAMELEN+1];
    strcpy(wpar, NULL);
    cid = corral_getcid();

    while((c = getopt(argc, argv, "0:")) != EOF){
        if (c == '0'){
            if (IS_WPAR(cid))
                showusage();
            atflag = 1;
            strcpy(wpar, optarg);
        }
    }
    argc -= optind;
    argv += optind;

    if (argc > 2)
        showusage();

    if (argc){
        if ((interval = atoi(argv[0])) <= 0)
            showusage();
        argc--;
    }

    if (argc){
        if ((count = atoi(argv[1])) <= 0)
            showusage();
    }
}

```

```

}

/* If no -@ flag call display_global_sysinfo_stat function */
if (!atflag){
    if (!cid)
        /*display global values */
        display_global_sysinfo_stat();
    else
        /* display wpar values */
        display_wpar_sysinfo_stat();
}
else{
    /* if the argument to -@ is not ALL set the totalwpars to 1 */
    if (strcmp(wpar, "ALL")) {
        strcpy(wparid.u.wparname, wpar);
        wparid.spec = WPARNAME;
        totalwpar = 1;
    }
    else{
        totalwpar = perfstat_wpar_total(NULL, NULL, sizeof(perfstat_wpar_total_t), 0);

        if (totalwpar < 0){
            perror("perfstat_wpar_total : ");
            exit(1);
        }
        if (totalwpar == 0){
            printf("No wpars found");
            exit(1);
        }
        wparid.spec = WPARNAME;
        strcpy(wparid.u.wparname, NULL);
    }
    display_wpar_total_sysinfo_stat();
}
do_cleanup();
return(0);
}

```

The program displays an output that is similar to the following example output:

```

cswch   scalls   sread   swrite   fork     exec     rchar   wchar   deviceint  bwrite   bread   phread
=====
83      525      133     2        0        1       1009462  264    27         0        0        0

```

## perfstat\_memory\_total Interface

The `perfstat_memory_total` interface returns a `perfstat_memory_total_t` structure, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_memory_total_t` structure include:

Item	Descriptor
<code>bytes_coalesced</code>	Number of bytes of the calling partition's logical real memory coalesced
<code>bytes_coalesced_mempool</code>	Number of bytes of logical real memory coalesced in the calling partition's memory pool if the calling partition is authorized to see pool wide statistics else, set to zero.
<code>virt_total</code>	Amount of virtual memory (in units of 4 KB pages)
<code>real_total</code>	Amount of real memory (in units of 4 KB pages)
<code>real_free</code>	Amount of free real memory (in units of 4 KB pages)
<code>real_pinned</code>	Amount of pinned memory (in units of 4 KB pages)
<code>pgins</code>	Number of pages paged in
<code>pgouts</code>	Number of pages paged out
<code>pgsp_total</code>	Total amount of paging space (in units of 4 KB pages)
<code>pgsp_free</code>	Amount of free paging space (in units of 4 KB pages)
<code>pgsp_rsvd</code>	Amount of reserved paging space (in units of 4 KB pages)

**Note:** Page coalescing is a transparent operation wherein the hypervisor detects duplicate pages, directs all user reads to a single copy, and can reclaim other duplicate physical memory pages. Several other memory-related metrics (such as amount of paging space paged in and out, and amount of system memory) are also returned. For a complete list, see the `perfstat_memory_total_t` section of the `libperfstat.h` header file in *Files Reference*.

The preceding program emulates `vmstat`'s behavior and also shows an example of how the `perfstat_memory_total` interface is used:

```

#include <stdio.h>
#include <libperfstat.h>

int main(int argc, char* argv[]) {
    perfstat_memory_total_t minfo;

```

```

int rc;
rc = perfstat_memory_total(NULL, &minfo, sizeof(perfstat_memory_total_t), 1);
if (rc != 1) {
    perror("perfstat_memory_total");
    exit(-1);
}
printf("Memory statistics\n");
printf("-----\n");
printf("real memory size           : %llu MB\n",
       minfo.real_total*4096/1024/1024);
printf("reserved paging space      : %llu MB\n",minfo.pgsp_rsvd);
printf("virtual memory size         : %llu MB\n",
       minfo.virt_total*4096/1024/1024);
printf("number of free pages         : %llu\n",minfo.real_free);
printf("number of pinned pages       : %llu\n",minfo.real_pinned);
printf("number of pages in file cache : %llu\n",minfo.numperm);
printf("total paging space pages     : %llu\n",minfo.pgsp_total);
printf("free paging space pages      : %llu\n", minfo.pgsp_free);
printf("used paging space           : %3.2f%%\n",
       (float)(minfo.pgsp_total-minfo.pgsp_free)*100.0/
       (float)minfo.pgsp_total);
perfstat_memory_total(NULL, &minfo, sizeof(perfstat_memory_total_t), 1);
printf("Memory statistics\n");
printf("-----\n");
printf("real memory size           : %llu MB\n",
       minfo.real_total*4096/1024/1024);
printf("reserved paging space      : %llu MB\n",minfo.pgsp_rsvd);
printf("virtual memory size         : %llu MB\n",
       minfo.virt_total*4096/1024/1024);
printf("number of free pages         : %llu\n",minfo.real_free);
printf("number of pinned pages       : %llu\n",minfo.real_pinned);
printf("number of pages in file cache : %llu\n",minfo.numperm);
printf("total paging space pages     : %llu\n",minfo.pgsp_total);
printf("free paging space pages      : %llu\n", minfo.pgsp_free);
printf("used paging space           : %3.2f%%\n",
       (float)(minfo.pgsp_total-minfo.pgsp_free)*100.0/
       (float)minfo.pgsp_total);
printf("number of paging space page ins : %llu\n",minfo.pgspins);
printf("number of paging space page outs : %llu\n",minfo.pgspouts);
printf("number of page ins           : %llu\n",minfo.pgins);
printf("number of page outs          : %llu\n",minfo.pgouts);
}

```

The preceding program produces output such as the following:

```

Memory statistics
-----
real memory size           : 256 MB
reserved paging space      : 512 MB
virtual memory size         : 768 MB
number of free pages       : 32304
number of pinned pages     : 6546
number of pages in file cache : 12881
total paging space pages   : 131072
free paging space pages    : 129932
used paging space          : 0.87%
number of paging space page ins : 0
number of paging space page outs : 0
number of page ins         : 20574
number of page outs        : 92508

```

The preceding program emulates **vmstat**'s behavior and also shows how **perfstat\_memory\_total** is used.

### **perfstat\_disk\_total Interface**

The **perfstat\_disk\_total** interface returns a **perfstat\_disk\_total\_t** structure, which is defined in the **libperfstat.h** file.

Selected fields from the `perfstat_disk_total_t` structure include:

Item	Descriptor
<code>number</code>	Number of disks
<code>size</code>	Total disk size (in MB)
<code>free</code>	Total free disk space (in MB)
<code>xfers</code>	Total transfers to and from disk (in KB)

Several other disk-related metrics, such as number of blocks read from and written to disk, are also returned. For a complete list, see the `perfstat_disk_total_t` section in the `libperfstat.h` header file in *Files Reference*.

The following code shows an example of how `perfstat_disk_total` is used:

```
#include <stdio.h>
#include <libperfstat.h>

int main(int argc, char* argv[]) {
    perfstat_disk_total_t dinfo;
    int rc;
    rc = perfstat_disk_total(NULL, &dinfo, sizeof(perfstat_disk_total_t), 1);
    if (rc != 1)
    {
        perror("perfstat_disk_total");
        exit(-1);
    }
    perfstat_disk_total(NULL, &dinfo, sizeof(perfstat_disk_total_t), 1);
    printf("Total disk statistics\n");
    printf("-----\n");
    printf("number of disks      : %d\n",   dinfo.number);
    printf("total disk space     : %llu\n",  dinfo.size);
    printf("total free space     : %llu\n",  dinfo.free);
    printf("number of transfers  : %llu\n",  dinfo.xfers);
    printf("number of blocks written : %llu\n", dinfo.wblks);
    printf("number of blocks read  : %llu\n", dinfo.rblks);
}
```

This program produces output such as the following:

```
Total disk statistics
-----
number of disks      : 3
total disk space     : 4296
total free space     : 2912
number of transfers  : 77759
number of blocks written : 738016
number of blocks read  : 363120
```

The preceding program emulates `iostat's` behavior and also shows how `perfstat_disk_total` is used.

### **perfstat\_netinterface\_total Interface**

The `perfstat_netinterface_total` interface returns a `perfstat_netinterface_total_t` structure, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_netinterface_total_t` structure include:

Item	Descriptor
<b>number</b>	Number of network interfaces
<b>ipackets</b>	Total number of input packets received on all network interfaces
<b>opackets</b>	Total number of output packets sent on all network interfaces
<b>ierror</b>	Total number of input errors on all network interfaces
<b>oerror</b>	Total number of output errors on all network interfaces

Several other network interface-related metrics (such as number of bytes sent and received). For a complete list, see the **perfstat\_netinterface\_total\_t** section in the **libperfstat.h** header file in *Files Reference*.

## perfstat\_partition\_total Interface

The **perfstat\_partition\_total** interface returns a **perfstat\_partition\_total\_t** structure, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_partition\_total\_t** structure include:

Item	Descriptor
<b>purrr_coalescing</b>	PURR cycles consumes coalescing data if the calling partition is authorized to see pool wide statistics, else set to zero
<b>spurr_coalescing</b>	SPURR cycles consumes coalescing data if the calling partition is authorized to see pool wide statistics, else set to zero
<b>type</b>	Partition type
<b>online_cpus</b>	Number of virtual processors currently allocated to the partition
<b>online_memory</b>	Amount of memory currently allocated to the partition

**Note:** Page coalescing is a transparent operation wherein the hypervisor detects duplicate pages, directs all user reads to a single copy, and reclaims duplicate physical memory pages  
For a complete list, see the **perfstat\_partition\_total\_t** section in the **libperfstat.h** header file.

The following code shows examples of how to use the **perfstat\_partition\_total** function.

The following example demonstrates how to emulate the **lpartstat -i** command:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(int argc, char* argv[])
{
    perfstat_partition_total_t pinfo;
    int rc;

    rc = perfstat_partition_total(NULL, &pinfo, sizeof(perfstat_partition_total_t), 1);
    if (rc != 1) {
        perror("Error in perfstat_partition_total");
        exit(-1);
    }
    printf("Partition Name           : %s\n", pinfo.name);
    printf("Partition Number            : %u\n", pinfo.lpar_id);
    printf("Type                         : %s\n", pinfo.type.b.shared_enabled ? "Shared" : "Dedicated");
    printf("Mode                         : %s\n", pinfo.type.b.donate_enabled ? "Donating" :
        pinfo.type.b.capped ? "Capped" : "Uncapped");

    printf("Entitled Capacity           : %u\n", pinfo.entitled_proc_capacity);
    printf("Partition Group-ID          : %u\n", pinfo.group_id);
    printf("Shared Pool ID              : %u\n", pinfo.pool_id);
    printf("Online Virtual CPUs         : %u\n", pinfo.online_cpus);
    printf("Maximum Virtual CPUs        : %u\n", pinfo.max_cpus);
    printf("Minimum Virtual CPUs        : %u\n", pinfo.min_cpus);
    printf("Online Memory                : %llu MB\n", pinfo.online_memory);
    printf("Maximum Memory              : %llu MB\n", pinfo.max_memory);
    printf("Minimum Memory              : %llu MB\n", pinfo.min_memory);
    printf("Variable Capacity Weight    : %u\n", pinfo.var_proc_capacity_weight);
}
```

```

printf("Minimum Capacity           : %u\n", pinfo.min_proc_capacity);
printf("Maximum Capacity           : %u\n", pinfo.max_proc_capacity);
printf("Capacity Increment         : %u\n", pinfo.proc_capacity_increment);
printf("Maximum Physical CPUs in system: %u\n", pinfo.max_phys_cpus_sys);
printf("Active Physical CPUs in system : %u\n", pinfo.online_phys_cpus_sys);
printf("Active CPUs in Pool          : %u\n", pinfo.phys_cpus_pool);
printf("Unallocated Capacity        : %u\n", pinfo.unalloc_proc_capacity);
printf("Physical CPU Percentage      : %4.2f%%\n",
      (double)pinfo.entitled_proc_capacity / (double)pinfo.online_cpus);
printf("Unallocated Weight          : %u\n", pinfo.unalloc_var_proc_capacity_weight);
}

```

The program displays an output that is similar to the following example output:

```

Partition Name           : perfdev10
Partition Number        : 23
Type                    : Shared
Mode                    : Capped
Entitled Capacity       : 100
Partition Group-ID      : 32791
Shared Pool ID         : 0
Online Virtual CPUs     : 2
Maximum Virtual CPUs    : 4
Minimum Virtual CPUs    : 1
Online Memory           : 4096 MB
Maximum Memory          : 8192 MB
Minimum Memory          : 2048 MB
Variable Capacity Weight : 0
Minimum Capacity       : 100
Maximum Capacity       : 400
Capacity Increment     : 1
Maximum Physical CPUs in system: 64
Active Physical CPUs in system : 64
Active CPUs in Pool    : 59
Unallocated Capacity   : 0
Physical CPU Percentage : 50.00%
Unallocated Weight     : 0

```

The following example demonstrates emulating the **lparstat** command in default mode:

```

#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <libperfstat.h>
#include <sys/systemcfg.h>

#define XINTFRAC ((double)(_system_configuration.Xint)/(double)(_system_configuration.Xfrac))
/* convert physical processor tics to seconds */
#define HTIC2SEC(x) ((double)x * XINTFRAC)/(double)1000000000.0

#define INTERVAL_DEFAULT 2
#define COUNT_DEFAULT 10

/*simplelparstat.c file can be used in two modes:-
1) Auto Mode:It makes use of perfstat_cpu_util API to calculate utilization values,enable 'UTIL_AUTO' macro for execution in auto mode.
2) Manual Mode: Calculations are done in the current code.
*/

/*#define UTIL_AUTO 1*/

#ifdef UTIL_AUTO
#define UTIL_MS 1
#define UTIL_PCT 0
#define UTIL_CORE 2
#define UTIL_PURR 0
#define UTIL_SPURR 1
void display_lpar_util_auto(int mode,int cpumode,int count,int interval);
#endif

static int disp_util_header = 1;
static u_longlong_t last_time_base;
static u_longlong_t last_pcpu_user, last_pcpu_sys, last_pcpu_idle, last_pcpu_wait;
static u_longlong_t last_lcpu_user, last_lcpu_sys, last_lcpu_idle, last_lcpu_wait;
static u_longlong_t last_busy_donated, last_idle_donated;
static u_longlong_t last_busy_stolen, last_idle_stolen;
static u_longlong_t last_phint = 0, last_vcsw = 0, last_pit = 0;

/* support for remote node statistics collection in a cluster environment */
perfstat_id_node_t nodeid;
static char nodename[MAXHOSTNAMELEN] = "";
static int collect_remote_node_stats = 0;

```

```

void display_lpar_util(void);

int main(int argc, char* argv[])
{
    int interval = INTERVAL_DEFAULT;
    int count = COUNT_DEFAULT;
    int i, rc;
    char *optlist = "i:c:n:";
    int mode=0, cpumode=0;

    /* Process the arguments */
    while ((i = getopt(argc, argv, optlist)) != EOF)
    {
        switch(i)
        {
            case 'i':          /* Interval */
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c':          /* Number of iterations */
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'n':          /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                collect_remote_node_stats = 1;
                break;
            default:
                /* Invalid arguments. Print the usage and terminate */
                fprintf (stderr, "usage: %s [-i <interval in seconds> ] [-c <number of iterations> ] [-n <node name in the cluster> ]\n", argv[0]);
                return(-1);
        }
    }

    if(collect_remote_node_stats)
    {
        /* perfstat_config needs to be called to enable cluster statistics collection */
        rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
        if (rc == -1)
        {
            perror("cluster statistics collection is not available");
            exit(-1);
        }
    }

#ifdef UTIL_AUTO
    printf("Enter CPU mode.\n");
    printf(" 0 PURR \n 1 SPURR \n");
    scanf("%d",&cpumode);
    printf("Enter print mode.\n");
    printf(" 0 PERCENTAGE\n 1 MILLISECONDS\n 2 CORES \n");
    scanf("%d",&mode);

    if((mode>2)&& (cpumode>1))
    {
        printf("Error: Invalid Input\n");
        exit(0);
    }
    display_lpar_util_auto(mode, cpumode, count, interval);
#else
    /* Iterate "count" times */
    while (count > 0)
    {
        display_lpar_util();
        sleep(interval);
        count--;
    }
#endif

    if(collect_remote_node_stats)
    {
        /* Now disable cluster statistics by calling perfstat_config */
        perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
    }

    return(0);
}

/* Save the current values for the next iteration */
void save_last_values(perfstat_cpu_total_t *cpustats, perfstat_partition_total_t *lparstats)
{
    last_vcsw      = lparstats->vol_virt_cswitch + lparstats->invol_virt_cswitch;
    last_time_base = lparstats->timebase_last;
    last_phint     = lparstats->phantintrs;
    last_pit      = lparstats->pool_idle_time;

    last_pcpu_user = lparstats->puser;
    last_pcpu_sys  = lparstats->psys;
    last_pcpu_idle = lparstats->pidle;
    last_pcpu_wait = lparstats->pwait;

    last_lcpu_user = cpustats->user;
    last_lcpu_sys  = cpustats->sys;
    last_lcpu_idle = cpustats->idle;
    last_lcpu_wait = cpustats->wait;

    last_busy_donated = lparstats->busy_donated_purr;
    last_idle_donated = lparstats->idle_donated_purr;

    last_busy_stolen = lparstats->busy_stolen_purr;
    last_idle_stolen = lparstats->idle_stolen_purr;
}

```

```

}

/* retrieve metrics using perfstat API */
void collect_metrics(perfstat_cpu_total_t *cpustats, perfstat_partition_total_t *lparstats)
{
    if (collect_remote_node_stats)
    {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;

        if (perfstat_partition_total_node(&nodeid, lparstats, sizeof(perfstat_partition_total_t), 1) <= 0) {
            perror("perfstat_partition_total_node");
            exit(-1);
        }
        if (perfstat_cpu_total_node(&nodeid, cpustats, sizeof(perfstat_cpu_total_t), 1) <= 0) {
            perror("perfstat_cpu_total_node");
            exit(-1);
        }
    }
    else
    {
        if (perfstat_partition_total(NULL, lparstats, sizeof(perfstat_partition_total_t), 1) <= 0) {
            perror("perfstat_partition_total");
            exit(-1);
        }

        if (perfstat_cpu_total(NULL, cpustats, sizeof(perfstat_cpu_total_t), 1) <= 0) {
            perror("perfstat_cpu_total");
            exit(-1);
        }
    }
}

/* print header informations */
void print_header(perfstat_partition_total_t *lparstats)
{
    if (lparstats->type.b.shared_enabled) { /* partition is a SPLPAR */
        if (lparstats->type.b.pool_util_authority) { /* partition has PUA access */
            printf("\n%5s %5s %6s %6s %5s %5s %5s %4s %5s",
                "user", "%sys", "%wait", "%idle", "phyc", "%entc", "lbusy", "app", "vcsw", "phint");

            printf("\n%5s %5s %6s %6s %5s %5s %5s %4s %5s",
                "----", "----", "----", "----", "----", "----", "----", "----");
        } else {
            printf("\n%5s %5s %6s %6s %5s %5s %5s %4s %5s",
                "user", "%sys", "%wait", "%idle", "phyc", "%entc", "lbusy", "vcsw", "phint");

            printf("\n%5s %5s %6s %6s %5s %5s %5s %4s %5s",
                "----", "----", "----", "----", "----", "----", "----", "----");
        }
    } else { /* partition is a DLPAR */
        printf("\n%5s %5s %6s %6s", "user", "%sys", "%wait", "%idle");
        printf("\n%5s %5s %6s %6s", "----", "----", "----", "----");
        if (lparstats->type.b.donate_enabled) { /* if donation is enabled for this DLPAR */
            printf(" %6s %6s", "%physc", "%vcsw");
            printf(" %6s %6s", "----", "----");
        }
    }
    fprintf(stdout, "\n");
}

/* Gather and display lpar utilization metrics */
void display_lpar_util(void)
{
    u_longlong_t delta_pcpu_user, delta_pcpu_sys, delta_pcpu_idle, delta_pcpu_wait;
    u_longlong_t delta_lcpu_user, delta_lcpu_sys, delta_lcpu_idle, delta_lcpu_wait;
    u_longlong_t delta_busy_stolen, delta_busy_donated, delta_idle_stolen, delta_idle_donated;
    u_longlong_t vcsw, lcpstime, pcpstime;
    u_longlong_t entitled_purr, unused_purr;
    u_longlong_t delta_purr, delta_time_base;
    double phys_proc_consumed, entitlement, percent_ent, delta_sec;
    perfstat_partition_total_t lparstats;
    perfstat_cpu_total_t cpustats;

    /* retrieve the metrics */
    collect_metrics(&cpustats, &lparstats);

    /* Print the header for utilization metrics (only once) */
    if (disp_util_header) {
        print_header(&lparstats);

        disp_util_header = 0;

        /* first iteration, we only read the data, print the header and save the data */
        save_last_values(&cpustats, &lparstats);
        return;
    }

    /* calculate physical processor tics during the last interval in user, system, idle and wait mode */
    delta_pcpu_user = lparstats.puser - last_pcpu_user;
    delta_pcpu_sys = lparstats.psys - last_pcpu_sys;
    delta_pcpu_idle = lparstats.pidle - last_pcpu_idle;
    delta_pcpu_wait = lparstats.pwait - last_pcpu_wait;

    /* calculate total physical processor tics during the last interval */
    delta_purr = pcpstime = delta_pcpu_user + delta_pcpu_sys + delta_pcpu_idle + delta_pcpu_wait;

    /* calculate clock tics during the last interval in user, system, idle and wait mode */
    delta_lcpu_user = cpustats.user - last_lcpu_user;
    delta_lcpu_sys = cpustats.sys - last_lcpu_sys;
    delta_lcpu_idle = cpustats.idle - last_lcpu_idle;
    delta_lcpu_wait = cpustats.wait - last_lcpu_wait;

    /* calculate total clock tics during the last interval */
    lcpstime = delta_lcpu_user + delta_lcpu_sys + delta_lcpu_idle + delta_lcpu_wait;
}

```

```

/* calculate entitlement for this partition - entitled physical processors for this partition */
entitlement = (double)lparstats.entitled_proc_capacity / 100.0 ;

/* calculate delta time in terms of physical processor tics */
delta_time_base = lparstats.timebase_last - last_time_base;

if (lparstats.type.b.shared_enabled) { /* partition is a SPLPAR */
/* calculate entitled physical processor tics for this partitions */
entitled_purr = delta_time_base * entitlement;
if (entitled_purr < delta_purr) { /* for uncapped SPLPAR */
/* in case of uncapped SPLPAR, consider entitled physical processor tics or
* consumed physical processor tics, which ever is greater */
entitled_purr = delta_purr;
}
/* calculate unused physical processor tics out of the entitled physical processor tics */
unused_purr = entitled_purr - delta_purr;

/* distributed unused physical processor tics among wait and idle proportionally to wait and idle in clock tics */
delta_pcpu_wait += unused_purr * ((double)delta_lcpu_wait / (double)(delta_lcpu_wait + delta_lcpu_idle));
delta_pcpu_idle += unused_purr * ((double)delta_lcpu_idle / (double)(delta_lcpu_wait + delta_lcpu_idle));

/* far SPLPAR, consider the entitled physical processor tics as the actual delta physical processor tics */
pcputime = entitled_purr;
}
else if (lparstats.type.b.donate_enabled) { /* if donation is enabled for this DLPAR */
/* calculate busy stolen and idle stolen physical processor tics during the last interval */
/* these physical processor tics are stolen from this partition by the hypervisor
* which will be used by wanting partitions */
delta_busy_stolen = lparstats.busy_stolen_purr - last_busy_stolen;
delta_idle_stolen = lparstats.idle_stolen_purr - last_idle_stolen;

/* calculate busy donated and idle donated physical processor tics during the last interval */
/* these physical processor tics are voluntarily donated by this partition to the hypervisor
* which will be used by wanting partitions */
delta_busy_donated = lparstats.busy_donated_purr - last_busy_donated;
delta_idle_donated = lparstats.idle_donated_purr - last_idle_donated;

/* add busy donated and busy stolen to the kernel bucket, as cpu
* cycles were donated / stolen when this partition is busy */
delta_pcpu_sys += delta_busy_donated;
delta_pcpu_sys += delta_busy_stolen;

/* distribute idle stolen to wait and idle proportionally to the logical wait and idle in clock tics, as
* cpu cycles were stolen when this partition is idle or in wait */
delta_pcpu_wait += delta_idle_stolen *
((double)delta_lcpu_wait / (double)(delta_lcpu_wait + delta_lcpu_idle));
delta_pcpu_idle += delta_idle_stolen *
((double)delta_lcpu_idle / (double)(delta_lcpu_wait + delta_lcpu_idle));

/* distribute idle donated to wait and idle proportionally to the logical wait and idle in clock tics, as
* cpu cycles were donated when this partition is idle or in wait */
delta_pcpu_wait += delta_idle_donated *
((double)delta_lcpu_wait / (double)(delta_lcpu_wait + delta_lcpu_idle));
delta_pcpu_idle += delta_idle_donated *
((double)delta_lcpu_idle / (double)(delta_lcpu_wait + delta_lcpu_idle));

/* add donated to the total physical processor tics for CPU usage calculation, as they were
* distributed to respective buckets accordingly */
pcputime += (delta_idle_donated + delta_busy_donated);

/* add stolen to the total physical processor tics for CPU usage calculation, as they were
* distributed to respective buckets accordingly */
pcputime += (delta_idle_stolen + delta_busy_stolen);
}

/* Processor Utilization - Applies for both SPLPAR and DLPAR*/
printf("%5.1f ", (double)delta_pcpu_user * 100.0 / (double)pcputime);
printf("%5.1f ", (double)delta_pcpu_sys * 100.0 / (double)pcputime);
printf("%6.1f ", (double)delta_pcpu_wait * 100.0 / (double)pcputime);
printf("%6.1f ", (double)delta_pcpu_idle * 100.0 / (double)pcputime);

if (lparstats.type.b.shared_enabled) { /* print SPLPAR specific stats */
/* Physical Processor Consumed by this partition */
phys_proc_consumed = (double)delta_purr / (double)delta_time_base;
printf("%5.2f ", (double)phys_proc_consumed);

/* Percentage of Entitlement Consumed - percentage of entitled physical processor tics consumed */
percent_ent = (double)((phys_proc_consumed / entitlement) * 100);
printf("%5.1f ", percent_ent);

/* Logical Processor Utilization of this partition */
printf("%5.1f ", (double)(delta_lcpu_user+delta_lcpu_sys) * 100.0 / (double)lcpu_time);

if (lparstats.type.b.pool_util_authority) {
/* Available physical Processor units available in the shared pool (app) */
printf("%5.2f ", (double)(lparstats.pool_idle_time - last_pit) /
XINTFRAC*(double)delta_time_base);
}

/* Virtual CPU Context Switches per second */
vcsw = lparstats.vol_virt_cswitch + lparstats.invol_virt_cswitch;
delta_sec = HTIC2SEC(delta_time_base);
printf("%4.0f ", (double)(vcsw - last_vcsw) / delta_sec);

/* Phantom Interrupts per second */
printf("%5.0f", (double)(lparstats.phantintrs - last_phint) / delta_sec);
}
else if (lparstats.type.b.donate_enabled) { /* print donation-enabled DLPAR specific stats */
/* Physical Processor Consumed by this partition
* (excluding donated and stolen physical processor tics). */
phys_proc_consumed = (double)delta_purr / (double)delta_time_base;
printf("%5.2f ", (double)phys_proc_consumed);
}

```

```

    /* Virtual CPU Context Switches per second */
    vcsw = lparstats.vol_virt_cswitch + lparstats.invol_virt_cswitch;
    delta_sec = HTIC2SEC(delta_time_base);
    printf("%5.0f ", (double)(vcsw - last_vcsw) / delta_sec);
}
printf("\n");
}
save_last_values(&cpustats, &lparstats);
}

#ifdef UTIL_AUTO
void display_lpar_util_auto(int mode,int cpumode,int count,int interval)
{
    float user_core_purr,kern_core_purr,wait_core_purr,idle_core_purr;
    float user_core_spurr,kern_core_spurr,wait_core_spurr,idle_core_spurr,sum_core_spurr;
    u_longlong_t user_ms_purr,kern_ms_purr,wait_ms_purr,idle_ms_purr,sum_ms;
    u_longlong_t user_ms_spurr,kern_ms_spurr,wait_ms_spurr,idle_ms_spurr;
    perfstat_rawdata_t data;
    u_longlong_t delta_purr, delta_time_base;
    double phys_proc_consumed, entitlement, percent_ent, delta_sec;
    perfstat_partition_total_t lparstats;
    static perfstat_cpu_total_t oldt,newt;
    perfstat_cpu_util_t util;
    int rc;

    /* retrieve the metrics */

    /* Print the header for utilization metrics (only once) */
    if (disp_util_header) {
        if(mode==UTIL_PCT)
            printf("\n%5s %5s %6s %6s %5s \n",
                "user", "sys", "wait", "idle", "physc");
        else if(mode==UTIL_MS)
            printf("\n%5s %5s %6s %6s %5s \n",
                "user(ms)", "sys(ms)", "wait(ms)", "idle(ms)", "physc");
        else if(mode==UTIL_CORE)
            printf("\n%5s %5s %6s %6s %5s \n",
                "user", "sys", "wait", "idle", "physc");

        disp_util_header = 0;
    }

    /* first iteration, we only read the data, print the header and save the data */
}

while(count)
{
    collect_metrics (&oldt, &lparstats);
    sleep(interval);
    collect_metrics (&newt, &lparstats);

    data.type = UTIL_CPU_TOTAL;
    data.curstat = &newt; data.prevstat= &oldt;
    data.sizeof_data = sizeof(perfstat_cpu_util_t);
    data.cur_elems = 1;
    data.prev_elems = 1;
    rc = perfstat_cpu_util(&data, &util,sizeof(perfstat_cpu_util_t), 1);
    if(rc <= 0)
    {
        perror("Error in perfstat_cpu_util");
        exit(-1);
    }
    delta_time_base = util.delta_time;

    switch(mode)
    {
    case UTIL_PCT:
        printf(" %5.1f %5.1f %5.1f %5.1f %5.4f \n",util.user_pct,util.kern_pct,util.wait_pct,util.idle_pct,util.physical_consumed);
        break;

    case UTIL_MS:
        user_ms_purr=((util.user_pct*delta_time_base)/100.0);
        kern_ms_purr=((util.kern_pct*delta_time_base)/100.0);
        wait_ms_purr=((util.wait_pct*delta_time_base)/100.0);
        idle_ms_purr=((util.idle_pct*delta_time_base)/100.0);

        if(cpumode==UTIL_PURR)
        {
            printf(" %11u %11u %11u %11u %5.4f\n",user_ms_purr,kern_ms_purr,wait_ms_purr,idle_ms_purr,util.physical_consumed);
        }
        else if(cpumode==UTIL_SPURR)
        {
            user_ms_spurr=(user_ms_purr*util.freq_pct)/100.0;
            kern_ms_spurr=(kern_ms_purr*util.freq_pct)/100.0;
            wait_ms_spurr=(wait_ms_purr*util.freq_pct)/100.0;
            sum_ms=user_ms_spurr+kern_ms_spurr+wait_ms_spurr;
            idle_ms_spurr=delta_time_base-sum_ms;

            printf(" %11u %11u %11u %11u %5.4f \n",user_ms_spurr,kern_ms_spurr,wait_ms_spurr,idle_ms_spurr,util.physical_consumed);
        }
        break;

    case UTIL_CORE:
        user_core_purr=((util.user_pct*util.physical_consumed)/100.0);
        kern_core_purr=((util.kern_pct*util.physical_consumed)/100.0);
        wait_core_purr=((util.wait_pct*util.physical_consumed)/100.0);
        idle_core_purr=((util.idle_pct*util.physical_consumed)/100.0);

        user_core_spurr=((user_core_purr*util.freq_pct)/100.0);
        kern_core_spurr=((kern_core_purr*util.freq_pct)/100.0);

```

```

wait_core_spurr=((wait_core_purr*util.freq_pct)/100.0);

if(cpumode==UTIL_PURR)
{
printf("%.4f %.4f %.4f %.4f %.4f\n",user_core_purr,kern_core_purr,wait_core_purr,idle_core_purr,util.physical_consumed);
}
else if(cpumode==UTIL_SPURR)
{
sum_core_spurr=user_core_spurr+kern_core_spurr+wait_core_spurr;
idle_core_spurr=util.physical_consumed-sum_core_spurr;

printf("%.4f %.4f %.4f %.4f %.4f\n",user_core_spurr,kern_core_spurr,wait_core_spurr,idle_core_spurr,util.physical_consumed);
}
break;

default:
printf("In correct usage\n");
return;
}
count--;
}
}
#endif

```

The program displays an output that is similar to the following example output:

```

%user  %sys  %wait  %idle  physc  %entc  lbusy  vcsw  phint
-----
 0.1   0.4   0.0   99.5   0.01   1.2    0.2   278   0
 0.0   0.3   0.0   99.7   0.01   0.8    0.2   271   0
 0.0   0.2   0.0   99.8   0.01   0.5    0.1   180   0
 0.0   0.2   0.0   99.8   0.01   0.6    0.1   184   0
 0.0   0.2   0.0   99.7   0.01   0.6    0.1   181   0
 0.0   0.2   0.0   99.8   0.01   0.6    0.1   198   0
 0.0   0.2   0.0   99.8   0.01   0.7    0.2   189   0
 2.1   3.3   0.0   94.6   0.09   8.7    2.1   216   0
 0.0   0.2   0.0   99.8   0.01   0.7    0.1   265   0

```

## perfstat\_tape\_total Interface

The `perfstat_tape_total` interface returns a `perfstat_tape_total_t` structure, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_tape_total_t` structure include:

Item	Descriptor
<code>number</code>	Total number of tapes
<code>size</code>	Total size of all tapes(in MB)
<code>free</code>	Total free portion of all tapes (in MB)
<code>rxfers</code>	Total number of read transfers from/to tape
<code>xfers</code>	Total number of transfers from/to tape

Several other tape-related metrics (such as number of bytes sent and received). For a complete list, see the `perfstat_tape_total` section in the `libperfstat.h` header file.

The following code shows examples of how to use the `perfstat_tape_total` function.

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfstat_tape_total_t *tinfo;
    int rc,i;

    rc = perfstat_tape_total(NULL, NULL, sizeof(perfstat_tape_total_t), 0);
    if(rc<=0){
        perror("perfstat_tape_total");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    tinfo = calloc(rc, sizeof(perfstat_tape_t));
    if(tinfo==NULL){

```

```

        printf("No sufficient memory\n");
        exit(-1);
    }

    rc = perfstat_tape_total(NULL, tinfo, sizeof(perfstat_tape_total_t), rc);
    if (rc < 0)
    {
        perror("perfstat_tape_total");
        exit(-1);
    }

    if(rc==0){
        printf("No tape found on the system\n");
        exit(-1);
    }

    for(i=0;i<rc;i++){
        printf("Total number of tapes=%d\n",tinfo[i].number);
        printf("Total size of all tapes (in MB)=%lld\n",tinfo[i].size);
        printf("Free portion of all tapes(in MB)=%lld\n",tinfo[i].free);
        printf("Number of read transfers to/from tape=%lld\n",tinfo[i].rxfers);
        printf("Total number of transfers to/from tape=%lld\n",tinfo[i].xfers);
        printf("Blocks written to all tapes=%lld\n",tinfo[i].wblks);
        printf("Blocks read from all tapes=%lld\n",tinfo[i].rblks);
        printf("Amount of time tapes are active=%lld\n",tinfo[i].time);
    }

    return(0);
}

```

The preceding program emulates **diskstat** behavior and also shows how **perfstat\_tape\_total** is used.

## perfstat\_partition\_config interface

The **perfstat\_partition\_config** interface returns a **perfstat\_partition\_config\_t** structure, which is defined in the **libperfstat.h** file.

The selected fields from the **perfstat\_partition\_config\_t** structure include:

Item	Descriptor
<b>partitionname</b>	Partition name
<b>processorFamily</b>	Processor type
<b>processorModel</b>	Processor model
<b>machineID</b>	Machine ID
<b>processorMHz</b>	Processor clock speed in megahertz
<b>numProcessors</b>	Number of configured physical processors in frame
<b>OSName</b>	Name of operating system
<b>OSVersion</b>	Version of operating system
<b>OSBuild</b>	Build of operating system
<b>lcpus</b>	Number of logical CPUs
<b>smtthreads</b>	Number of SMT threads
<b>drives</b>	Total number of drives
<b>nw_adapters</b>	Total number of network adapters
<b>vcpus</b>	Minimum, maximum, and online virtual CPUs
<b>cpucap</b>	Minimum, maximum, and online CPU capacity
<b>entitled_proc_capacity</b>	Number of processor units that this partition is entitled to receive
<b>cpucap_weightage</b>	Variable processor capacity weightage
<b>mem_weightage</b>	Variable memory capacity weightage
<b>cpupool_weightage</b>	Pool weightage
<b>activecpusinpool</b>	Count of physical CPUs in the shared processor pool to which the partition belongs
<b>sharedpcpu</b>	Number of physical processors allocated for the use of the shared processor
<b>maxpoolcap</b>	Maximum processor capacity of partition's pool
<b>entpoolcap</b>	Entitled processor capacity of partition's pool

Item	Descriptor
<b>mem</b>	Minimum, maximum, and online memory
<b>totiement</b>	I/O memory entitlement of the partition in bytes
<b>mempoolid</b>	AMS pool ID of the pool to which the logical partition (LPAR) belongs
<b>hyperpgsize</b>	Hypervisor page size in kilobytes
<b>exp_mem</b>	Minimum, maximum, and online expanded memory
<b>targetmemexpfactor</b>	Target memory expansion factor scaled by 100
<b>targetmemexpsize</b>	Expanded memory size in megabytes
<b>Subprocessormode</b>	Subprocessor mode for the partition

For a complete list, see the `perfstat_partition_config_t` section in the **libperfstat.h** header file.

The usage of the code for the `perfstat_partition_config` API is as follows:

```
#include <libperfstat.h>
```

```
int main(int argc, char *argv[])
{
    perfstat_partition_config_t pinfo;
    int rc;

    rc = perfstat_partition_config(NULL, &pinfo, sizeof(perfstat_partition_config_t), 1);
    if(rc != 1)
    {
        perror("Error in perfstat_partition_config");
        exit(-1);
    }
    printf("====Configuration Information of Partition====\n");
    printf("Partition Name = %s\n",pinfo.partitionname);
    printf("Node Name = %s\n",pinfo.nodename);
    printf("Partition Number = %u\n",pinfo.partitionnum);
    printf("Group ID = %u\n",pinfo.groupid);
    printf("\n\n====General Partition Properties(1=YES, 0=NO)====\n");
    printf("SMT Capable = %u\n",pinfo.conf.b.smt_capable);
    /* 1, if OS supports SMT mode */
    printf("SMT Enabled = %u\n",pinfo.conf.b.smt_enabled);
    /* 1, if SMT mode is on */
    printf("LPAR Capable = %u\n",pinfo.conf.b.lpar_capable);
    /* 1, if OS supports logical partitioning */
    printf("LPAR Enabled = %u\n",pinfo.conf.b.lpar_enabled);
    /* 1, if logical partitioning is on */
    printf("Shared Capable = %u\n",pinfo.conf.b.shared_capable);
    /* 1, if OS supports shared processor LPAR */
    printf("Shared Enabled = %u\n",pinfo.conf.b.shared_enabled);
    /* 1, if partition runs in shared mode */
    printf("DLPAR Capable = %u\n",pinfo.conf.b.dlpar_capable);
    /* 1, if OS supports dynamic LPAR */
    printf("Capped = %u\n",pinfo.conf.b.capped);
    /* 1, if partition is capped */
    printf("64-Bit Kernel = %u\n",pinfo.conf.b.kernel_is_64);
    /* 1, if kernel is 64 bit */
    printf("Pool Util Authority = %u\n",pinfo.conf.b.pool_util_authority);
    /* 1, if pool utilization available */
    printf("Donate Capable = %u\n",pinfo.conf.b.donate_capable);
    /* 1, if capable of donating cycles */
    printf("Donate Enabled = %u\n",pinfo.conf.b.donate_enabled);
    /* 1, if capable of donating cycles */
    printf("AMS Capable = %u\n",pinfo.conf.b.ams_capable);
    /* 1, if AMS(Active Memory Sharing) capable */
    printf("AMS Enabled = %u\n",pinfo.conf.b.ams_enabled);
    /* 1, if AMS(Active Memory Sharing) enabled */
    printf("Power Saving Mode = %u\n",pinfo.conf.b.power_save);
    /* 1, if Power saving mode is enabled */
    printf("AME Enabled = %u\n",pinfo.conf.b.ame_enabled);
    /* 1, if Active Memory Expansion is enabled */
    printf("Shared Extended = %u\n",pinfo.conf.b.shared_extended);
}
```

```

        /* 1, if Shared Extended */
printf("\n\n====Hardware Configuration=====\n");
printf("Processor Type =           %s\n",pinfo.processorFamily);
printf("Processor Model =           %s\n",pinfo.processorModel);
printf("Machine ID =                 %s\n",pinfo.machineID);
printf("Processor Clock Speed =       %lf MHz\n",pinfo.processorMHz);
printf("Online Configured Processors = %lld\n",pinfo.numProcessors.online);
printf("Max Configured Processors =    %lld\n",pinfo.numProcessors.max);
printf("\n\n====Software Configuration=====\n");
printf("OS Name =                       %s\n",pinfo.OSName);
printf("OS Version =                     %s\n",pinfo.OSVersion);
printf("OS Build =                        %s\n",pinfo.OSBuild);
printf("\n\n====LPAR Configuration=====\n");
printf("Number of Logical CPUs =        %u\n",pinfo.lcpus);
printf("Number of SMT Threads =         %u\n",pinfo.smtthreads);
printf("Number of Drives =              %u\n",pinfo.drives);
printf("Number of NW Adapters =         %u\n",pinfo.nw_adapters);
printf("\n\n====Physical CPU Related Configuration=====\n");
printf("Minimum CPU Capacity =          %.2f\n", (float)pinfo.cpucap.min/100.0);
printf("Maximum CPU Capacity =          %.2f\n", (float)pinfo.cpucap.max/100.0);
printf("CPU Capacity Weightage =        %u\n",pinfo.cpucap_weightage);
printf("Entitled Proc Capacity =        %.2f\n",pinfo.entitled_proc_capacity/100.0);
printf("\n\n====Virtual CPU Related Configuration=====\n");
printf("Minimum Virtual CPUs =          %lld\n",pinfo.vcpus.min);
printf("Maximum Virtual CPUs =          %lld\n",pinfo.vcpus.max);
printf("Online Virtual CPUs =           %lld\n",pinfo.vcpus.online);
printf("\n\n====Processor Pool Related Configuration=====\n");
printf("Processor Pool Id =              %u\n",pinfo.processor_poolid);
printf("Active CPUs in pool =           %u\n",pinfo.activecpusinpool);
printf("Pool Weightage =                 %u\n",pinfo.cpuspool_weightage);
printf("Shared processors Count =        %u\n",pinfo.sharedpcpu);
printf("Max pool Capacity =              %u\n",pinfo.maxpoolcap);
printf("Entitled pool Capacity =         %u\n",pinfo.entpoolcap);
printf("\n\n====Memory Related Configuration=====\n");
printf("Minimum Memory =                 %lld\n",pinfo.mem.min);
printf("Maximum memory =                 %lld\n",pinfo.mem.max);
printf("Online memory =                  %lld\n",pinfo.mem.online);
printf("Memory capacity Weightage =      %u\n",pinfo.mem_weightage);
printf("\n\n====AMS Related Configuration=====\n");
printf("I/O memory Entitlement =         %lld\n",pinfo.totiomement);
printf("AMS Pool ID =                    %d\n",pinfo.mempoolid);
printf("Hypervisor Page Size =           %f\n",pinfo.hyperpgsize);
printf("\n\n====AME Related Configuration=====\n");
printf("Minimum Expanded memory =        %lld\n",pinfo.exp_mem.min);
printf("Maximum Expanded Memory =        %lld\n",pinfo.exp_mem.max);
printf("Online Expanded memory =         %lld\n",pinfo.exp_mem.online);
printf("Target memory Expansion factor = %lld\n",pinfo.targetmemexpfactor);
printf("Target Memory Expansion Size =   %lld\n",pinfo.targetmemexpsize);
printf("\n\n====");
}

```

The output of the program is as follows:

```

====Configuration Information of Partition====
Partition Name = clock15
Node Name = clock15
Partition Number = 9
Group ID = 0

====General Partition Properties(1=YES, 0=NO)====
SMT Capable = 1
SMT Enabled = 1
LPAR Capable = 1
LPAR Enabled = 1
Shared Capable = 1
Shared Enabled = 1

```

DLPAR Capable = 1  
Capped = 0  
64-Bit Kernel = 1  
Pool Util Authority = 0  
Donate Capable = 0  
Donate Enabled = 0  
AMS Capable = 0  
AMS Enabled = 0  
Power Saving Mode = 1  
AME Enabled = 0  
Shared Extended = 0

=====**Hardware Configuration**=====

Processor Type = POWER\_5  
Processor Model = IBM,9133-55A  
Machine ID = 061500H  
Processor Clock Speed = 1648.350000 MHz  
Online Configured Processors = 8  
Max Configured Processors = 8

=====**Software Configuration**=====

OS Name = AIX  
OS Version = 7.1  
OS Build = Feb 17 2011 15:57:15 1107A\_71D

=====**LPAR Configuration**=====

Number of Logical CPUs = 2  
Number of SMT Threads = 2  
Number of Drives = 2  
Number of NW Adapters = 2

=====**Physical CPU Related Configuration**=====

Minimum CPU Capacity = 0.10  
Maximum CPU Capacity = 8.00  
CPU Capacity Weightage = 128  
Entitled Proc Capacity = 0.75

=====**Virtual CPU Related Configuration**=====

Minimum Virtual CPUs = 1  
Maximum Virtual CPUs = 8  
Online Virtual CPUs = 1

=====**Processor Pool Related Configuration**=====

Processor Pool Id = 0  
Active CPUs in pool = 3  
Pool Weightage = 128  
Shared processors Count = 0  
Max pool Capacity = 0  
Entitled pool Capacity = 0

=====**Memory Related Configuration**=====

Minimum Memory = 256  
Maximum memory = 4096  
Online memory = 2048  
Memory capacity Weightage = 0

=====**AMS Related Configuration**=====

I/O memory Entitlement = 0  
AMS Pool ID = 0

```

Hypervisor Page Size = 0.000000
=====AME Related Configuration=====
Minimum Expanded memory = 0
Maximum Expanded Memory = 0
Online Expanded memory = 0
Target memory Expansion factor = 0
Target Memory Expansion Size = 0
=====

```

## Component-Specific interfaces

Component-specific interfaces report metrics related to individual components on a system (such as a processor, disk, network interface, or paging space).

All of the following AIX interfaces use the naming convention **perfstat\_subsystem**, and use a common signature:

Item	Descriptor
<b>perfstat_cpu</b>	Retrieves individual processor usage metrics <b>Note:</b> This interface returns global values when called by an application running inside WPAR.
<b>perfstat_disk</b>	Retrieves individual disk usage metrics <b>Note:</b> This interface does not return any data when called by an application running inside WPAR.
<b>perfstat_diskpath</b>	Retrieves individual disk path metrics <b>Note:</b> This interface does not return any data when called by an application running inside WPAR.
<b>perfstat_diskadapter</b>	Retrieves individual disk adapter metrics <b>Note:</b> This interface does not return any data when called by an application running inside WPAR.
<b>perfstat_netinterface</b>	Retrieves individual network interfaces metrics <b>Note:</b> This interface returns WPAR-specific data when called by an application running inside WPAR.
<b>perfstat_protocol</b>	Retrieves individual network protocol-related metrics <b>Note:</b> This interface returns WPAR-specific data when called by an application running inside WPAR.
<b>perfstat_netbuffer</b>	Retrieves individual network buffer allocation metrics <b>Note:</b> This interface returns WPAR-specific data when called by an application running inside WPAR.
<b>perfstat_pagingspace</b>	Retrieves individual paging space metrics <b>Note:</b> This interface does not return any data when called by an application running inside WPAR.
<b>perfstat_memory_page</b>	Retrieves multiple page size usage metrics <b>Note:</b> This interface returns global values when it is called by an application running inside a WPAR.
<b>perfstat_tape</b>	Retrieves individual tape usage metrics <b>Note:</b> This interface does not return any data when it is called by an application running inside a WPAR.
<b>perfstat_logicalvolume</b>	Retrieves individual logical volume usage metrics <b>Note:</b> This interface does not return any data when called it is by an application running inside a WPAR.
<b>perfstat_volume group</b>	Retrieves individual volume group usage metrics <b>Note:</b> This interface does not return any data when it is called by an application running inside a WPAR.
<b>perfstat_hfistat</b>	Retrieves individual host fabric interface (HFI) statistics.
<b>perfstat_hfistat_window</b>	Retrieves individual window-based HFI statistics.
<b>perfstat_cpu_util</b>	Calculates CPU utilization
<b>perfstat_process</b>	Retrieves process utilization metrics
<b>perfstat_process_util</b>	Calculates process utilization metrics
<b>perfstat_thread</b>	Retrieves kernel thread utilization metrics
<b>perfstat_thread_util</b>	Calculates kernel thread utilization metrics

The common signature used by all the component interfaces except **perfstat\_memory\_page** and **perfstat\_hfistat\_window** is as follows:

```
int perfstat_subsystem(perfstat_id *name,
                      perfstat_subsystem_t * userbuff,
                      int sizeof_struct,
                      int desired_number);
```

The `perfstat_memory_page` uses the following signature:

```
int perfstat_memory_page(perfstat_psize_t *psize ,
                        perfstat_subsystem_t * userbuff,
                        int sizeof_struct,
                        int desired_number);
```

The `perfstat_hfistat_window` uses the following signature:

```
int perfstat_hfistat_window(perfstat_id_window_t *name,
                            perfstat_hfistat_window_t *userbuff,
                            int sizeof_struct,
                            int desired_number);
```

The usage of the parameters for all of the interfaces is as follows:

Item	Descriptor
<code>perfstat_id_t *name</code>	Enter the name of the first component (for example <code>hdisk2</code> for <code>perfstat_disk()</code> ) to obtain the statistics. A structure containing a <code>char *</code> field is used instead of directly passing a <code>char *</code> argument to the function to avoid allocation errors and to prevent the user from giving a constant string as parameter. To start from the first component of a subsystem, set the <code>char*</code> field of the name parameter to "" (empty string). You can use macros such as <code>FIRST_SUBSYSTEM</code> (for example, <code>FIRST_CPU</code> ) defined in the <code>libperfstat.h</code> file.
<code>perfstat_id_window_t *name</code>	Enter the Host Fabric Interface name (for example, <code>hfi0</code> or <code>hfi1</code> or <code>FIRST_HFI</code> ) in the "name->name" field, and the HFI window number in "name->windowid" field.
<code>perfstat_subsystem_t *userbuff</code>	Specifies a pointer to a memory area with enough space for the returned structures.
<code>int sizeof_struct</code>	Set the parameter to <code>sizeof(perfstat_subsystem_t)</code> .
<code>int desired_number</code>	Specifies the number of structures of type <code>perfstat_subsystem_t</code> to return in <code>userbuff</code> .

The return value is -1 in case of error. Otherwise, the number of structures copied is returned. The field name is either set to `NULL` or to the name of the next structure available.

An exception to this scheme is when `name=NULL`, `userbuff=NULL` and `desired_number=0`, the total number of structures available is returned.

To retrieve all structures of a given type, find the number of structures and allocate the required memory to hold the structures. You must then call the appropriate API to retrieve all structures in one call. Another method is to allocate a fixed set of structures and repeatedly call the API to get the next set of structures, each time passing the name returned by the previous call. Start the process with the name set to "" or `FIRST_SUBSYSTEM`, and repeat the process.

Minimizing the number of API calls, and the number of system calls, leads to more efficient code, so the two-call approach is preferred. Some of the examples shown in the following sections illustrate the API usage using the two-call approach. The two-call approach causes large amount of memory allocation, the multiple-call approach is sometimes used, and is illustrated in the following examples.

The following sections provide examples of the type of data returned and the code used for each of the interfaces.

## perfstat\_cpu interface

The `perfstat_cpu` interface returns a set of structures of type `perfstat_cpu_t`, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_cpu_t` structure include:

Item	Descriptor
<b>name</b>	Logical processor name (cpu0, cpu1, ...)
<b>user</b>	Number of clock ticks spent in user mode
<b>sys</b>	Number of clock ticks spent in system (kernel) mode
<b>idle</b>	Number of clock ticks spent idle with no I/O pending
<b>wait</b>	Number of clock ticks spent idle with I/O pending
<b>syscall</b>	Number of system call executed

Several other CPU-related metrics (such as number of forks, read, write, and execs) are also returned. For a complete list, see the **perfstat\_cpu\_t** section in the **libperfstat.h** header.

The following code shows an example of how the **perfstat\_cpu** interface is used:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(int argc, char *argv[]) {
    int i, retcode, cputotal;
    perfstat_id_t firstcpu;
    perfstat_cpu_t *statp;

    /* check how many perfstat_cpu_t structures are available */
    cputotal = perfstat_cpu(NULL, NULL, sizeof(perfstat_cpu_t), 0);

    /* check for error */
    if (cputotal <= 0)
    {
        perror("perfstat_cpu");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    statp = calloc(cputotal, sizeof(perfstat_cpu_t));
    if (statp == NULL) {
        printf("No sufficient memory\n");
        exit(-1);
    }

    /* set name to first cpu */
    strcpy(firstcpu.name, FIRST_CPU);

    /* ask to get all the structures available in one call */
    retcode = perfstat_cpu(&firstcpu, statp, sizeof(perfstat_cpu_t), cputotal);

    /* check for error */
    if (retcode <= 0)
    {
        perror("perfstat_cpu");
        exit(-1);
    }

    /* return code is number of structures returned */

    for (i = 0; i < retcode; i++) {
        printf("\nStatistics for CPU : %s\n", statp[i].name);
        printf("-----\n");
        printf("CPU user time (raw ticks) : %llu\n", statp[i].user);
        printf("CPU sys time (raw ticks) : %llu\n", statp[i].sys);
        printf("CPU idle time (raw ticks) : %llu\n", statp[i].idle);
        printf("CPU wait time (raw ticks) : %llu\n", statp[i].wait);
        printf("number of syscalls : %llu\n", statp[i].syscall);
        printf("number of readings : %llu\n", statp[i].sysread);
        printf("number of writings : %llu\n", statp[i].syswrite);
        printf("number of forks : %llu\n", statp[i].sysfork);
        printf("number of execs : %llu\n", statp[i].sysexec);
    }
}
```

```

        printf("number of char read      : %llu\n", statp[i].readch);
        printf("number of char written  : %llu\n", statp[i].writech);
    }
}

```

The program displays an output that is similar to the following example output:

```

Statistics for CPU : cpu0
-----
CPU user time (raw ticks) : 2585
CPU sys time (raw ticks) : 25994
CPU idle time (raw ticks) : 7688458
CPU wait time (raw ticks) : 3207
number of syscalls       : 6051122
number of readings       : 436595
number of writings       : 1284469
number of forks          : 4804
number of execs          : 5420
number of char read      : 1014077004
number of char written   : 56464273

```

```

Statistics for CPU : cpu1
-----
CPU user time (raw ticks) : 23
CPU sys time (raw ticks) : 794
CPU idle time (raw ticks) : 7703901
CPU wait time (raw ticks) : 42
number of syscalls       : 66064
number of readings       : 3432
number of writings       : 20620
number of forks          : 412
number of execs          : 51
number of char read      : 7068025
number of char written   : 217425

```

```

Statistics for CPU : cpu2
-----
CPU user time (raw ticks) : 0
CPU sys time (raw ticks) : 720
CPU idle time (raw ticks) : 7704041
CPU wait time (raw ticks) : 0
number of syscalls       : 0
number of readings       : 0
number of writings       : 0
number of forks          : 0
number of execs          : 0
number of char read      : 0
number of char written   : 0

```

```

Statistics for CPU : cpu3
-----
CPU user time (raw ticks) : 0
CPU sys time (raw ticks) : 810
CPU idle time (raw ticks) : 7703950
CPU wait time (raw ticks) : 0
number of syscalls       : 0
number of readings       : 0
number of writings       : 0
number of forks          : 0
number of execs          : 0
number of char read      : 0
number of char written   : 0

```

```

Statistics for CPU : cpu4
-----
CPU user time (raw ticks) : 243
CPU sys time (raw ticks) : 1799

```

```

CPU idle time (raw ticks) : 7702802
CPU wait time (raw ticks) : 62
number of syscalls       : 722482
number of readings       : 34416
number of writings       : 2994
number of forks          : 597
number of execs          : 453
number of char read      : 128511349
number of char written   : 2352602

```

Statistics for CPU : cpu5

```

-----
CPU user time (raw ticks) : 0
CPU sys time (raw ticks) : 209834
CPU idle time (raw ticks) : 7676489
CPU wait time (raw ticks) : 0
number of syscalls       : 729
number of readings       : 42
number of writings       : 0
number of forks          : 16
number of execs          : 1
number of char read      : 14607
number of char written   : 0

```

Statistics for CPU : cpu6

```

-----
CPU user time (raw ticks) : 0
CPU sys time (raw ticks) : 210391
CPU idle time (raw ticks) : 7677505
CPU wait time (raw ticks) : 0
number of syscalls       : 0
number of readings       : 0
number of writings       : 0
number of forks          : 0
number of execs          : 0
number of char read      : 0
number of char written   : 0

```

Statistics for CPU : cpu7

```

-----
CPU user time (raw ticks) : 0
CPU sys time (raw ticks) : 209884
CPU idle time (raw ticks) : 7675736
CPU wait time (raw ticks) : 0
number of syscalls       : 0
number of readings       : 0
number of writings       : 0
number of forks          : 0
number of execs          : 0
number of char read      : 0
number of char written   : 0

```

In an environment where dynamic logical partitioning is used, the number of **perfstat\_cpu\_t** structures available is equal to the **ncpus\_high** field in the **perfstat\_cpu\_total\_t**. This number represents the highest index of any active processor since the last reboot. Kernel data structures holding performance metrics for processors are not deallocated when processors are turned offline or moved to a different partition and it stops updating the information. The **CPUs** field of the **perfstat\_cpu\_total\_t** structure represents the number of active processors, but the **perfstat\_cpu** interface returns **ncpus\_high** structures.

Applications can detect offline or moved processors by checking clock-tick increments. If the sum of the user, sys, idle, and wait fields is identical for a given processor between two **perfstat\_cpu** calls, that processor has been offline for the complete interval. If the sum multiplied by 10 ms (the value of a clock tick) does not match the time interval, the processor has not been online for the complete interval.

The preceding program emulates **mpstat** behavior and also shows how **perfstat\_cpu** is used.

## perfstat\_cpu\_util interface

The `perfstat_cpu_util` interface returns a set of structures of type `perfstat_cpu_util_t`, which is defined in the `libperfstat.h` file

The `perfstat_cpu_util` interface includes the following fields:

Item	Descriptor
<code>cpu_id</code>	Holds CPU ID
<code>entitlement</code>	Partition's entitlement
<code>user_pct</code>	Percentage of utilization in user mode
<code>kern_pct</code>	Percentage of utilization in kernel mode
<code>idle_pct</code>	Percentage of utilization in idle mode
<code>wait_pct</code>	Percentage of utilization in wait mode
<code>physical_busy</code>	Physical CPU is busy
<code>physical_consumed</code>	Total CPUs consumed by the partition
<code>freq_pct</code>	Average frequency over the last interval in percentage
<code>entitlement_pct</code>	Percentage of entitlement used
<code>busy_pct</code>	Percentage of entitlement busy
<code>idle_donated_pct</code>	Percentage of idle cycles donated
<code>busy_donated_pct</code>	Percentage of busy cycles donated
<code>idle_stolen_pct</code>	Percentage of idle cycles stolen
<code>busy_stolen_pct</code>	Percentage of busy cycles stolen
<code>float_l_user_pct</code>	Percentage of utilization in user mode in terms of the logical processor ticks
<code>float_l_kern_pct</code>	Percentage of utilization in kernel mode in terms of the logical processor ticks
<code>float_l_idle_pct</code>	Percentage of utilization in idle mode in terms of the logical processor ticks
<code>float_l_wait_pct</code>	Percentage of utilization in wait mode in terms of the logical processor ticks
<code>u_longlong_t delta_time</code>	Percentage of the delta time in milliseconds for which the utilization is evaluated

Both system utilization and per CPU utilization can be obtained by using `theperfstat_cpu_util` by mentioning the type field of the `perfstat_rawdata_t` data structure as `UTIL_CPU_TOTAL` or `UTIL_CPU` respectively. `UTIL_CPU_TOTAL` and `UTIL_CPU` are the macros, which can be referred in the definition of the `perfstat_rawdata_t` data structure.

The use of the `perfstat_cpu_util` API for system-level utilization follows:

```
#include <libperfstat.h>
#define PERIOD 5
void main()
{
    perfstat_cpu_total_t *newt, *oldt;
    perfstat_cpu_util_t *util;
    perfstat_rawdata_t data;
    int rc;

    oldt = (perfstat_cpu_total_t*)malloc(sizeof(perfstat_cpu_total_t)*1);
    if(oldt==NULL){
        perror ("malloc");
        exit(-1);
    }

    newt = (perfstat_cpu_total_t*)malloc(sizeof(perfstat_cpu_total_t)*1);
    if(newt==NULL){
        perror ("malloc");
        exit(-1);
    }

    util = (perfstat_cpu_util_t*)malloc(sizeof(perfstat_cpu_util_t)*1);
    if(util==NULL){
        perror ("malloc");
        exit(-1);
    }
}
```

```

}

rc = perfstat_cpu_total(NULL, oldt, sizeof(perfstat_cpu_total_t), 1);
if(rc <= 0)
{
perror("Error in perfstat_cpu_total");
exit(-1);
}
sleep(PERIOD);
rc = perfstat_cpu_total(NULL, newt, sizeof(perfstat_cpu_total_t), 1);
if(rc <= 0)
{
perror("Error in perfstat_cpu_total");
exit(-1);
}
data.type = UTIL_CPU_TOTAL;
data.curstat = newt; data.prevstat= oldt;
data.sizeof_data = sizeof(perfstat_cpu_total_t);
data.cur_elems = 1;
data.prev_elems = 1;
rc = perfstat_cpu_util(&data, util, sizeof(perfstat_cpu_util_t), 1);
if(rc <= 0)
{
perror("Error in perfstat_cpu_util");
exit(-1);
}
printf("====Overall CPU Utilization Metrics====\n");
printf("Utilization Metrics for a period of %d seconds\n",PERIOD);
printf("User Percentage = %f\n",util->user_pct);
printf("System Percentage = %f\n",util->kern_pct);
printf("Idle Percentage = %f\n",util->idle_pct);
printf("Wait Percentage = %f\n",util->wait_pct);
printf("Physical Busy = %f\n",util->physical_busy);
printf("Physical Consumed = %f\n",util->physical_consumed);
printf("Freq Percentage = %f\n",util->freq_pct);
printf("Entitlement Used Percentage = %f\n",util->entitlement_pct);
printf("Entitlement Busy Percentage = %f\n",util->busy_pct);
printf("Idle Cycles Donated Percentage = %f\n",util->idle_donated_pct);
printf("Busy Cycles Donated Percentage = %f\n",util->busy_donated_pct);
printf("Idle Cycles Stolen Percentage = %f\n",util->idle_stolen_pct);
printf("Busy Cycles Stolen Percentage = %f\n",util->busy_stolen_pct);
printf("User percentage for logical cpu in ticks = %f\n",util->l_user_pct);
printf("Sytem percentage for logical cpu in ticks= %f\n",util->l_kern_pct);
printf("Idle percentage for logical cpu in ticks= %f\n",util->l_idle_pct);
printf("Wait percentage for logical cpu in ticks= %f\n",util->l_wait_pct);
printf("delta time in milliseconds = %llu \n",util->delta_time);
printf("=====\n");
}

```

The program produces the output similar to the following:

```

====Overall CPU Utilization Metrics====
Utilization Metrics for a period of 5 seconds
User Percentage = 0.050689
System Percentage = 0.262137
Idle Percentage = 99.687172
Wait Percentage = 0.000000
Physical Busy = 0.003128
Physical Consumed = 0.008690
Freq Percentage = 99.935417
Entitlement Used Percentage = 0.869017
Entitlement Busy Percentage = 0.312826
Idle Cycles Donated Percentage = 0.000000
Busy Cycles Donated Percentage = 0.000000
Idle Cycles Stolen Percentage = 0.000000
Busy Cycles Stolen Percentage = 0.000000
User percentage for logical cpu in ticks = 0.000000

```

```

System percentage for logical cpu in ticks= 0.082034
Idle percentage for logical cpu in ticks= 99.917969
Wait percentage for logical cpu in ticks= 0.000000
delta time in milliseconds = 4980

```

The example code to calculate system utilization per CPU, and CPU utilization, by using the perfstat\_cpu\_util interface follows:

```

#include <libperfstat.h>
#define PERIOD 5

void main()
{
    perfstat_rawdata_t data;
    perfstat_cpu_util_t *util;
    perfstat_cpu_t *newt,*oldt;
    perfstat_id_t id;
    int i,cpu_count,rc;

    /* Check how many perfstat_cpu_t structures are available */
    cpu_count = perfstat_cpu(NULL, NULL,sizeof(perfstat_cpu_t),0);

    /* check for error */
    if(cpu_count <= 0)
    {
        perror("Error in perfstat_cpu");
        exit(-1);
    }
    /* allocate enough memory */
    oldt = (perfstat_cpu_t *)calloc(cpu_count,sizeof(perfstat_cpu_t));
    if(oldt == NULL)
    {
        perror("Memory Allocation Error");
        exit(-1);
    }
    /* set name to first cpu */
    strcpy(id.name,FIRST_CPU);
    /* ask to get all the structures available in one call */
    rc = perfstat_cpu(&id, oldt, sizeof(perfstat_cpu_t), cpu_count);
    /* check for error */
    if(rc <=0)
    {
        perror("Error in perfstat_cpu");
        exit(-1);
    }
    data.type = UTIL_CPU;
    data.prevstat= oldt;
    data.sizeof_data = sizeof(perfstat_cpu_t);
    data.prev_elems = cpu_count;
    sleep(PERIOD);
    /* Check how many perfstat_cpu_t structures are available after a defined period */
    cpu_count = perfstat_cpu(NULL, NULL,sizeof(perfstat_cpu_t),0);

    /* Check for error */
    if(cpu_count <= 0)
    {
        perror("Error in perfstat_cpu");
        exit(-1);
    }

    data.cur_elems = cpu_count;
    if(data.prev_elems != data.cur_elems)
    {
        perror("The number of CPUs has become different for defined period");
        exit(-1);
    }
    /* allocate enough memory */

```

```

newt = (perfstat_cpu_t *)calloc(cpu_count,sizeof(perfstat_cpu_t));
util = (perfstat_cpu_util_t *)calloc(cpu_count,sizeof(perfstat_cpu_util_t));
if(newt == NULL || util == NULL)
{
    perror("Memory Allocation Error");
    exit(-1);
}
data.curstat = newt;
rc = perfstat_cpu(&id, newt, sizeof(perfstat_cpu_t), cpu_count);
if(rc <= 0)
{
    perror("Error in perfstat_cpu");
    exit(-1);
}
/* Calculate CPU Utilization Metrics*/
rc = perfstat_cpu_util(&data, util, sizeof(perfstat_cpu_util_t), cpu_count);
if(rc <= 0)
{
    perror("Error in perfstat_cpu_util");
    exit(-1);
}
printf("==== Per CPU Utilization Metrics =====\n");
printf("Utilization Metrics for a period of %d seconds\n",PERIOD);
printf("=====\n");
for ( i = 0;i<cpu_count;i++)
{
    printf("Utilization metrics for CPU-ID = %s\n",util[i].cpu_id);
    printf("User Percentage = %f\n",util[i].user_pct);
    printf("System Percentage = %f\n",util[i].kern_pct);
    printf("Idle Percentage = %f\n",util[i].idle_pct);
    printf("Wait Percentage = %f\n",util[i].wait_pct);
    printf("Physical Busy = %f\n",util[i].physical_busy);
    printf("Physical Consumed = %f\n",util[i].physical_consumed);
    printf("Freq Percentage = %f\n",util[i].freq_pct);
    printf("Entitlement Used Percentage = %f\n",util[i].entitlement_pct);
    printf("Entitlement Busy Percentage = %f\n",util[i].busy_pct);
    printf("Idle Cycles Donated Percentage = %f\n",util[i].idle_donated_pct);
    printf("Busy Cycles Donated Percentage = %f\n",util[i].busy_donated_pct);
    printf("Idle Cycles Stolen Percentage = %f\n",util[i].idle_stolen_pct);
    printf("Busy Cycles Stolen Percentage = %f\n",util[i].busy_stolen_pct);
    printf("system percentage for logical cpu in ticks = %f\n",util[i].l_kern_pct);
    printf("idle percentage for logical cpu in ticks = %f\n",util[i].l_idle_pct);
    printf("wait percentage for logical cpu in ticks = %f\n",util[i].l_wait_pct);
    printf("delta time in milliseconds = %llu \n",util[i].delta_time);
    printf("\n\n");
}
printf("=====\n");
}

```

The program produces the output similar to the following:

```

==== Per CPU Utilization Metrics =====
Utilization Metrics for a period of 5 seconds
=====
Utilization metrics for CPU-ID =   cpu0
User Percentage =                   14.850358
System Percentage =                  63.440376
Idle Percentage =                    21.709267
Wait Percentage =                     0.000000
Physical Busy =                       0.003085
Physical Consumed =                   0.003941
Freq Percentage =                     99.975967
Entitlement Used Percentage =          0.394055
Entitlement Busy Percentage =          0.308508
Idle Cycles Donated Percentage =       0.000000
Busy Cycles Donated Percentage =       0.000000
Idle Cycles Stolen Percentage =        0.000000

```

Busy Cycles Stolen Percentage = 0.000000  
system percentage for logical cpu in ticks = 0.000000  
idle percentage for logical cpu in ticks = 100.000000  
wait percentage for logical cpu in ticks = 0.000000  
delta time in milliseconds = 4999

Utilization metrics for CPU-ID = cpu1  
User Percentage = 0.000000  
System Percentage = 4.720662  
Idle Percentage = 95.279335  
Wait Percentage = 0.000000  
Physical Busy = 0.000065  
Physical Consumed = 0.001371  
Freq Percentage = 99.938919  
Entitlement Used Percentage = 0.137110  
Entitlement Busy Percentage = 0.006472  
Idle Cycles Donated Percentage = 0.000000  
Busy Cycles Donated Percentage = 0.000000  
Idle Cycles Stolen Percentage = 0.000000  
Busy Cycles Stolen Percentage = 0.000000  
system percentage for logical cpu in ticks = 0.000000  
idle percentage for logical cpu in ticks = 100.000000  
wait percentage for logical cpu in ticks = 0.000000  
delta time in milliseconds = 5000

Utilization metrics for CPU-ID = cpu2  
User Percentage = 0.000000  
System Percentage = 5.848962  
Idle Percentage = 94.151039  
Wait Percentage = 0.000000  
Physical Busy = 0.000079  
Physical Consumed = 0.001348  
Freq Percentage = 99.900566  
Entitlement Used Percentage = 0.134820  
Entitlement Busy Percentage = 0.007886  
Idle Cycles Donated Percentage = 0.000000  
Busy Cycles Donated Percentage = 0.000000  
Idle Cycles Stolen Percentage = 0.000000  
Busy Cycles Stolen Percentage = 0.000000  
system percentage for logical cpu in ticks = 0.000000  
idle percentage for logical cpu in ticks = 100.000000  
wait percentage for logical cpu in ticks = 0.000000  
delta time in milliseconds = 5000

Utilization metrics for CPU-ID = cpu3  
User Percentage = 0.000000  
System Percentage = 4.644570  
Idle Percentage = 95.355431  
Wait Percentage = 0.000000  
Physical Busy = 0.000061  
Physical Consumed = 0.001312  
Freq Percentage = 99.925430  
Entitlement Used Percentage = 0.131174  
Entitlement Busy Percentage = 0.006092  
Idle Cycles Donated Percentage = 0.000000  
Busy Cycles Donated Percentage = 0.000000  
Idle Cycles Stolen Percentage = 0.000000  
Busy Cycles Stolen Percentage = 0.000000  
system percentage for logical cpu in ticks = 0.000000  
idle percentage for logical cpu in ticks = 100.000000  
wait percentage for logical cpu in ticks = 0.000000  
delta time in milliseconds = 5000

Utilization metrics for CPU-ID = cpu4

User Percentage = 0.000000  
System Percentage = 55.325123  
Idle Percentage = 44.674877  
Wait Percentage = 0.000000  
Physical Busy = 0.000153  
Physical Consumed = 0.000276  
Freq Percentage = 99.927551  
Entitlement Used Percentage = 0.027605  
Entitlement Busy Percentage = 0.015273  
Idle Cycles Donated Percentage = 0.000000  
Busy Cycles Donated Percentage = 0.000000  
Idle Cycles Stolen Percentage = 0.000000  
Busy Cycles Stolen Percentage = 0.000000  
system percentage for logical cpu in ticks = 0.000000  
idle percentage for logical cpu in ticks = 100.000000  
wait percentage for logical cpu in ticks = 0.000000  
delta time in milliseconds = 4999

Utilization metrics for CPU-ID = cpu5  
User Percentage = 0.000000  
System Percentage = 1.854463  
Idle Percentage = 98.145538  
Wait Percentage = 0.000000  
Physical Busy = 0.000002  
Physical Consumed = 0.000113  
Freq Percentage = 99.612183  
Entitlement Used Percentage = 0.011326  
Entitlement Busy Percentage = 0.000210  
Idle Cycles Donated Percentage = 0.000000  
Busy Cycles Donated Percentage = 0.000000  
Idle Cycles Stolen Percentage = 0.000000  
Busy Cycles Stolen Percentage = 0.000000  
system percentage for logical cpu in ticks = 0.255102  
idle percentage for logical cpu in ticks = 99.744896  
wait percentage for logical cpu in ticks = 0.000000  
delta time in milliseconds = 3913

Utilization metrics for CPU-ID = cpu6  
User Percentage = 0.000000  
System Percentage = 1.776852  
Idle Percentage = 98.223145  
Wait Percentage = 0.000000  
Physical Busy = 0.000002  
Physical Consumed = 0.000115  
Freq Percentage = 99.475967  
Entitlement Used Percentage = 0.011506  
Entitlement Busy Percentage = 0.000204  
Idle Cycles Donated Percentage = 0.000000  
Busy Cycles Donated Percentage = 0.000000  
Idle Cycles Stolen Percentage = 0.000000  
Busy Cycles Stolen Percentage = 0.000000  
system percentage for logical cpu in ticks = 0.255102  
idle percentage for logical cpu in ticks = 99.744896  
wait percentage for logical cpu in ticks = 0.000000  
delta time in milliseconds = 3912

Utilization metrics for CPU-ID = cpu7  
User Percentage = 0.000000  
System Percentage = 2.138275  
Idle Percentage = 97.861725  
Wait Percentage = 0.000000  
Physical Busy = 0.000002  
Physical Consumed = 0.000112  
Freq Percentage = 99.593727  
Entitlement Used Percentage = 0.011205

```

Entitlement Busy Percentage =      0.000240
Idle Cycles Donated Percentage =   0.000000
Busy Cycles Donated Percentage =   0.000000
Idle Cycles Stolen Percentage =    0.000000
Busy Cycles Stolen Percentage =    0.000000
system percentage for logical cpu in ticks = 0.255102
idle percentage for logical cpu in ticks = 99.744896
wait percentage for logical cpu in ticks = 0.000000
delta time in milliseconds = 3912

```

## Example for simpleparstat.c code:

This topic provides an example for using the simpleparstat.c code.

```

#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <libperfstat.h>
#include <sys/systemcfg.h>

#define XINTFRAC ((double)(Xint)/(double)(Xfrac))
/* convert physical processor tics to seconds */
#define HTIC2SEC(x) ((double)x * XINTFRAC)/(double)1000000000.0

#define INTERVAL_DEFAULT 2
#define COUNT_DEFAULT 10

/*simpleparstat.c file can be used in two modes:-
1) Auto Mode:It makes use of perfstat_cpu_util API to calculate utilization values,enable 'UTIL_AUTO' macro for execution in auto mode.
2) Manual Mode: Calculations are done in the current code.
*/

/*#define UTIL_AUTO 1*/

#ifdef UTIL_AUTO
#define UTIL_MS 1
#define UTIL_PCT 0
#define UTIL_CORE 2
#define UTIL_PURR 0
#define UTIL_SPURR 1
void display_lpar_util_auto(int mode,int cpumode,int count,int interval);
#endif

static int disp_util_header = 1;
static u_longlong_t last_time_base;
static u_longlong_t last_pcpu_user, last_pcpu_sys, last_pcpu_idle, last_pcpu_wait;
static u_longlong_t last_lcpu_user, last_lcpu_sys, last_lcpu_idle, last_lcpu_wait;
static u_longlong_t last_busy_donated, last_idle_donated;
static u_longlong_t last_busy_stolen, last_idle_stolen;
static u_longlong_t last_phint = 0, last_vcsw = 0, last_pit = 0;

/* support for remote node statistics collection in a cluster environment */
perfstat_id_node_t nodeid;
static char nodename[MAXHOSTNAMELEN] = "";
static int collect_remote_node_stats = 0;

void display_lpar_util(void);

int main(int argc, char* argv[])
{
    int interval = INTERVAL_DEFAULT;
    int count = COUNT_DEFAULT;
    int i, rc;
    char *optlist = "i:c:n:";
    int mode=0,cpumode=0;

    /* Process the arguments */
    while ((i = getopt(argc, argv, optlist)) != EOF)
    {
        switch(i)
        {
            case 'i': /* Interval */
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c': /* Number of iterations */
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'n': /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                collect_remote_node_stats = 1;
                break;
            default:
                /* Invalid arguments. Print the usage and terminate */
                fprintf(stderr, "usage: %s [-i <interval in seconds>] [-c <number of iterations>] [-n <node name in the cluster> ]\n", argv[0]);
                return(-1);
        }
    }

    if(collect_remote_node_stats)
    { /* perfstat_config needs to be called to enable cluster statistics collection */
        rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    }
}

```

```

    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
        exit(-1);
    }
}

#ifdef UTIL_AUTO
printf("Enter CPU mode.\n");
printf(" 0 PURR \n 1 SPURR \n");
scanf("%d",&cpumode);
printf("Enter print mode.\n");
printf(" 0 PERCENTAGE\n 1 MILLISECOND\n 2 CORES \n");
scanf("%d",&mode);

if((mode>2)&& (cpumode>1))
{
    printf("Error: Invalid Input\n");
    exit(0);
}
display_lpar_util_auto(mode,cpumode,count,interval);

#else
/* Iterate "count" times */
while (count > 0)
{
    display_lpar_util();
    sleep(interval);
    count--;
}
#endif

if(collect_remote_node_stats)
{
    /* Now disable cluster statistics by calling perfstat_config */
    perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}

return(0);
}

/* Save the current values for the next iteration */
void save_last_values(perfstat_cpu_total_t *cpustats, perfstat_partition_total_t *lparstats)
{
    last_vcswh = lparstats->vol_virt_cswitch + lparstats->invol_virt_cswitch;
    last_time_base = lparstats->timebase_last;
    last_phint = lparstats->phantintrs;
    last_pit = lparstats->pool_idle_time;

    last_pcpu_user = lparstats->puser;
    last_pcpu_sys = lparstats->psys;
    last_pcpu_idle = lparstats->pidle;
    last_pcpu_wait = lparstats->pwait;

    last_lcpu_user = cpustats->user;
    last_lcpu_sys = cpustats->sys;
    last_lcpu_idle = cpustats->idle;
    last_lcpu_wait = cpustats->wait;

    last_busy_donated = lparstats->busy_donated_purr;
    last_idle_donated = lparstats->idle_donated_purr;

    last_busy_stolen = lparstats->busy_stolen_purr;
    last_idle_stolen = lparstats->idle_stolen_purr;
}

/* retrieve metrics using perfstat API */
void collect_metrics (perfstat_cpu_total_t *cpustats, perfstat_partition_total_t *lparstats)
{
    if (collect_remote_node_stats)
    {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;

        if (perfstat_partition_total_node(&nodeid, lparstats, sizeof(perfstat_partition_total_t), 1) <= 0) {
            perror("perfstat_partition_total_node");
            exit(-1);
        }
        if (perfstat_cpu_total_node(&nodeid, cpustats, sizeof(perfstat_cpu_total_t), 1) <= 0) {
            perror("perfstat_cpu_total_node");
            exit(-1);
        }
    }
    else
    {
        if (perfstat_partition_total(NULL, lparstats, sizeof(perfstat_partition_total_t), 1) <= 0) {
            perror("perfstat_partition_total");
            exit(-1);
        }

        if (perfstat_cpu_total(NULL, cpustats, sizeof(perfstat_cpu_total_t), 1) <= 0) {
            perror("perfstat_cpu_total");
            exit(-1);
        }
    }
}

/* print header informations */
void print_header(perfstat_partition_total_t *lparstats)
{
    if (lparstats->type.b.shared_enabled) { /* partition is a SPLPAR */
        if (lparstats->type.b.pool_util_authority) { /* partition has PUA access */
            printf("\n%5s %5s %6s %6s %5s %5s %5s %4s %5s",
                "%user", "%sys", "%wait", "%idle", "phyc", "%entc", "lbusy", "app", "vcswh", "phint");
        }
    }
}

```

```

        printf("\n%5s %5s %6s %6s %5s %5s %5s %4s %5s",
            "-----", "-----", "-----", "-----", "-----", "-----", "-----", "-----");
    } else {
        printf("\n%5s %5s %6s %6s %5s %5s %5s %4s %5s",
            "%user", "%sys", "%wait", "%idle", "%phyc", "%entc", "%lbusy", "%vcsw", "%phint");

        printf("\n%5s %5s %6s %6s %5s %5s %5s %4s %5s",
            "-----", "-----", "-----", "-----", "-----", "-----", "-----", "-----");
    }
} else { /* partition is a DLPAR */
    printf("\n%5s %5s %6s %6s", "%user", "%sys", "%wait", "%idle");
    printf("\n%5s %5s %6s %6s", "-----", "-----", "-----", "-----");
    if (lparstats->type.b.donate_enabled) { /* if donation is enabled for this DLPAR */
        printf(" %6s %6s", "%phyc", "%vcsw");
        printf(" %6s %6s", "-----", "-----");
    }
}
fprintf(stdout, "\n");
}

/* Gather and display lpar utilization metrics */
void display_lpar_util(void)
{
    u_longlong_t delta_pcpu_user, delta_pcpu_sys, delta_pcpu_idle, delta_pcpu_wait;
    u_longlong_t delta_lcpu_user, delta_lcpu_sys, delta_lcpu_idle, delta_lcpu_wait;
    u_longlong_t delta_busy_stolen, delta_busy_donated, delta_idle_stolen, delta_idle_donated;
    u_longlong_t vcswh, lcpu_time, pcpu_time;
    u_longlong_t entitled_purr, unused_purr;
    u_longlong_t delta_purr, delta_time_base;
    double phys_proc_consumed, entitlement, percent_ent, delta_sec;
    perfstat_partition_total_t lparstats;
    perfstat_cpu_total_t cpustats;

    /* retrieve the metrics */
    collect_metrics (&cpustats, &lparstats);

    /* Print the header for utilization metrics (only once) */
    if (disp_util_header) {
        print_header (&lparstats);

        disp_util_header = 0;

        /* first iteration, we only read the data, print the header and save the data */
        save_last_values(&cpustats, &lparstats);
        return;
    }

    /* calculate physical processor tics during the last interval in user, system, idle and wait mode */
    delta_pcpu_user = lparstats.puser - last_pcpu_user;
    delta_pcpu_sys = lparstats.psys - last_pcpu_sys;
    delta_pcpu_idle = lparstats.pidle - last_pcpu_idle;
    delta_pcpu_wait = lparstats.pwait - last_pcpu_wait;

    /* calculate total physical processor tics during the last interval */
    delta_purr = pcpu_time = delta_pcpu_user + delta_pcpu_sys + delta_pcpu_idle + delta_pcpu_wait;

    /* calculate clock tics during the last interval in user, system, idle and wait mode */
    delta_lcpu_user = cpustats.user - last_lcpu_user;
    delta_lcpu_sys = cpustats.sys - last_lcpu_sys;
    delta_lcpu_idle = cpustats.idle - last_lcpu_idle;
    delta_lcpu_wait = cpustats.wait - last_lcpu_wait;

    /* calculate total clock tics during the last interval */
    lcpu_time = delta_lcpu_user + delta_lcpu_sys + delta_lcpu_idle + delta_lcpu_wait;

    /* calculate entitlement for this partition - entitled physical processors for this partition */
    entitlement = (double)lparstats.entitled_proc_capacity / 100.0;

    /* calculate delta time in terms of physical processor tics */
    delta_time_base = lparstats.timebase_last - last_time_base;

    if (lparstats.type.b.shared_enabled) { /* partition is a SPLPAR */
        /* calculate entitled physical processor tics for this partitions */
        entitled_purr = delta_time_base * entitlement;
        if (entitled_purr < delta_purr) { /* for uncapped SPLPAR */
            /* in case of uncapped SPLPAR, consider entitled physical processor tics or
             * consumed physical processor tics, which ever is greater */
            entitled_purr = delta_purr;
        }
        /* calculate unused physical processor tics out of the entitled physical processor tics */
        unused_purr = entitled_purr - delta_purr;

        /* distributed unused physical processor tics among wait and idle proportionally to wait and idle in clock tics */
        delta_pcpu_wait += unused_purr * ((double)delta_lcpu_wait / (double)(delta_lcpu_wait + delta_lcpu_idle));
        delta_pcpu_idle += unused_purr * ((double)delta_lcpu_idle / (double)(delta_lcpu_wait + delta_lcpu_idle));

        /* far SPLPAR, consider the entitled physical processor tics as the actual delta physical processor tics */
        pcpu_time = entitled_purr;
    }
} else if (lparstats.type.b.donate_enabled) { /* if donation is enabled for this DLPAR */
    /* calculate busy stolen and idle stolen physical processor tics during the last interval */
    /* these physical processor tics are stolen from this partition by the hypervisor
     * which will be used by wanting partitions */
    delta_busy_stolen = lparstats.busy_stolen_purr - last_busy_stolen;
    delta_idle_stolen = lparstats.idle_stolen_purr - last_idle_stolen;

    /* calculate busy donated and idle donated physical processor tics during the last interval */
    /* these physical processor tics are voluntarily donated by this partition to the hypervisor
     * which will be used by wanting partitions */
    delta_busy_donated = lparstats.busy_donated_purr - last_busy_donated;
    delta_idle_donated = lparstats.idle_donated_purr - last_idle_donated;

    /* add busy donated and busy stolen to the kernel bucket, as cpu
     * cycles were donated / stolen when this partition is busy */
}

```

```

delta_pcpu_sys += delta_busy_donated;
delta_pcpu_sys += delta_busy_stolen;

/* distribute idle stolen to wait and idle proportionally to the logical wait and idle in clock tics, as
 * cpu cycles were stolen when this partition is idle or in wait */
delta_pcpu_wait += delta_idle_stolen *
    ((double)delta_lcpu_wait / (double)(delta_lcpu_wait + delta_lcpu_idle));
delta_pcpu_idle += delta_idle_stolen *
    ((double)delta_lcpu_idle / (double)(delta_lcpu_wait + delta_lcpu_idle));

/* distribute idle donated to wait and idle proportionally to the logical wait and idle in clock tics, as
 * cpu cycles were donated when this partition is idle or in wait */
delta_pcpu_wait += delta_idle_donated *
    ((double)delta_lcpu_wait / (double)(delta_lcpu_wait + delta_lcpu_idle));
delta_pcpu_idle += delta_idle_donated *
    ((double)delta_lcpu_idle / (double)(delta_lcpu_wait + delta_lcpu_idle));

/* add donated to the total physical processor tics for CPU usage calculation, as they were
 * distributed to respective buckets accordingly */
pcputime += (delta_idle_donated + delta_busy_donated);

/* add stolen to the total physical processor tics for CPU usage calculation, as they were
 * distributed to respective buckets accordingly */
pcputime += (delta_idle_stolen + delta_busy_stolen);
}

/* Processor Utilization - Applies for both SPLPAR and DLPAR*/
printf("%5.1f ", (double)delta_pcpu_user * 100.0 / (double)pcputime);
printf("%5.1f ", (double)delta_pcpu_sys * 100.0 / (double)pcputime);
printf("%6.1f ", (double)delta_pcpu_wait * 100.0 / (double)pcputime);
printf("%6.1f ", (double)delta_pcpu_idle * 100.0 / (double)pcputime);

if (lparstats.type.b.shared_enabled) { /* print SPLPAR specific stats */
/* Physical Processor Consumed by this partition */
phys_proc_consumed = (double)delta_purr / (double)delta_time_base;
printf("%5.2f ", (double)phys_proc_consumed);

/* Percentage of Entitlement Consumed - percentage of entitled physical processor tics consumed */
percent_ent = (double)((phys_proc_consumed / entitlement) * 100);
printf("%5.1f ", percent_ent);

/* Logical Processor Utilization of this partition */
printf("%5.1f ", (double)(delta_lcpu_user+delta_lcpu_sys) * 100.0 / (double)lcpuctime);

if (lparstats.type.b.pool_util_authority) {
/* Available physical Processor units available in the shared pool (app) */
printf("%5.2f ", (double)(lparstats.pool_idle_time - last_pit) /
    XINTFRAC*(double)delta_time_base);
}

/* Virtual CPU Context Switches per second */
vcsw = lparstats.vol_virt_cswitch + lparstats.invol_virt_cswitch;
delta_sec = HTIC2SEC(delta_time_base);
printf("%4.0f ", (double)(vcsw - last_vcsw) / delta_sec);

/* Phantom Interrupts per second */
printf("%5.0f", (double)(lparstats.phantintrs - last_phint) / delta_sec);
}
else if (lparstats.type.b.donate_enabled) { /* print donation-enabled DLPAR specific stats */
/* Physical Processor Consumed by this partition
 * (excluding donated and stolen physical processor tics). */
phys_proc_consumed = (double)delta_purr / (double)delta_time_base;
printf("%5.2f ", (double)phys_proc_consumed);

/* Virtual CPU Context Switches per second */
vcsw = lparstats.vol_virt_cswitch + lparstats.invol_virt_cswitch;
delta_sec = HTIC2SEC(delta_time_base);
printf("%5.0f ", (double)(vcsw - last_vcsw) / delta_sec);
}
printf("\n");

save_last_values(&cpustats, &lparstats);
}

#ifdef UTIL_AUTO
void display_lpar_util_auto(int mode,int cpumode,int count,int interval)
{
float user_core_purr,kern_core_purr,wait_core_purr,idle_core_purr;
float user_core_spurr,kern_core_spurr,wait_core_spurr,idle_core_spurr,sum_core_spurr;
u_longlong_t user_ms_purr,kern_ms_purr,wait_ms_purr,idle_ms_purr,sum_ms;
u_longlong_t user_ms_spurr,kern_ms_spurr,wait_ms_spurr,idle_ms_spurr;
perfstat_rawdata_t data;
u_longlong_t delta_purr, delta_time_base;
double phys_proc_consumed, entitlement, percent_ent, delta_sec;
perfstat_partition_total_t lparstats;
static perfstat_cpu_total_t oldt,newt;
perfstat_cpu_util_t util;
int rc;

/* retrieve the metrics */

/* Print the header for utilization metrics (only once) */
if (disp_util_header) {
if(mode==UTIL_PCT)
printf("\n%5s %5s %6s %6s %5s \n",
"%user", "%sys", "%wait", "%idle", "physc");
else if(mode==UTIL_MS)
printf("\n%5s %5s %6s %6s %5s \n",
"user(ms)", "sys(ms)", "wait(ms)", "idle(ms)", "physc");
else if(mode==UTIL_CORE)
printf("\n%5s %5s %6s %6s %5s \n",
"user", "sys", "wait", "idle", "physc");
}
}

```

```

disp_util_header = 0;
}
/* first iteration, we only read the data, print the header and save the data */
while(count)
{
    collect_metrics (&oldt, &parstats);
    sleep(interval);
    collect_metrics (&newt, &parstats);

    data.type = UTIL_CPU_TOTAL;
    data.curstat = &newt; data.prevstat = &oldt;
    data.sizeof_data = sizeof(perfstat_cpu_total_t);
    data.cur_elems = 1;
    data.prev_elems = 1;
    rc = perfstat_cpu_util(&data, &util, sizeof(perfstat_cpu_util_t), 1);
    if(rc <= 0)
    {
        perror("Error in perfstat_cpu_util");
        exit(-1);
    }
    delta_time_base = util.delta_time;

    switch(mode)
    {
    case UTIL_PCT:
        printf(" %5.1f %5.1f %5.1f %5.1f %5.4f \n", util.user_pct, util.kern_pct, util.wait_pct, util.idle_pct, util.physical_consumed);
        break;

    case UTIL_MS:
        user_ms_purr=((util.user_pct*delta_time_base)/100.0);
        kern_ms_purr=((util.kern_pct*delta_time_base)/100.0);
        wait_ms_purr=((util.wait_pct*delta_time_base)/100.0);
        idle_ms_purr=((util.idle_pct*delta_time_base)/100.0);

        if(cpumode==UTIL_PURR)
        {
            printf(" %11u %11u %11u %11u %5.4f\n", user_ms_purr, kern_ms_purr, wait_ms_purr, idle_ms_purr, util.physical_consumed);
        }
        else if(cpumode==UTIL_SPURR)
        {
            user_ms_spurr=(user_ms_purr*util.freq_pct)/100.0;
            kern_ms_spurr=(kern_ms_purr*util.freq_pct)/100.0;
            wait_ms_spurr=(wait_ms_purr*util.freq_pct)/100.0;
            sum_ms=user_ms_spurr+kern_ms_spurr+wait_ms_spurr;
            idle_ms_spurr=delta_time_base-sum_ms;

            printf(" %11u %11u %11u %11u %5.4f \n", user_ms_spurr, kern_ms_spurr, wait_ms_spurr, idle_ms_spurr, util.physical_consumed);
        }
        break;

    case UTIL_CORE:

        user_core_purr=((util.user_pct*util.physical_consumed)/100.0);
        kern_core_purr=((util.kern_pct*util.physical_consumed)/100.0);
        wait_core_purr=((util.wait_pct*util.physical_consumed)/100.0);
        idle_core_purr=((util.idle_pct*util.physical_consumed)/100.0);

        user_core_spurr=((user_core_purr*util.freq_pct)/100.0);
        kern_core_spurr=((kern_core_purr*util.freq_pct)/100.0);
        wait_core_spurr=((wait_core_purr*util.freq_pct)/100.0);

        if(cpumode==UTIL_PURR)
        {
            printf(" %5.4f %5.4f %5.4f %5.4f %5.4f \n", user_core_purr, kern_core_purr, wait_core_purr, idle_core_purr, util.physical_consumed);
        }
        else if(cpumode==UTIL_SPURR)
        {
            sum_core_spurr=user_core_spurr+kern_core_spurr+wait_core_spurr;
            idle_core_spurr=util.physical_consumed-sum_core_spurr;

            printf(" %5.4f %5.4f %5.4f %5.4f %5.4f \n", user_core_spurr, kern_core_spurr, wait_core_spurr, idle_core_spurr, util.physical_consumed);
        }
        break;

        default:
            printf("In correct usage\n");
            return;
    }
}
count--;
}
}
#endif

```

The program displays an output that is similar to the following example output:

```

%user %sys %wait %idle physc %ntc lbusy vcsw phint
-----
0.1 0.3 0.0 99.6 0.01 1.1 0.2 285 0
0.0 0.3 0.0 99.7 0.01 0.8 0.0 229 0
0.0 0.2 0.0 99.8 0.01 0.6 0.1 181 0
0.1 0.2 0.0 99.7 0.01 0.8 0.1 189 0
0.0 0.3 0.0 99.7 0.01 0.7 0.0 193 0

```

0.0	0.2	0.0	99.8	0.01	0.7	0.2	204	0
0.1	0.3	0.0	99.7	0.01	0.9	1.0	272	0
0.0	0.3	0.0	99.7	0.01	0.9	0.1	304	0
0.0	0.3	0.0	99.7	0.01	0.9	0.0	212	0

### Example for simplempstat.c code:

This topic provides an example for using the simplempstat.c code.

```
#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <libperfstat.h>
#include <errno.h>
#include <wpars/wparcfg.h>
static int disp_util_header = 1;

/*simplempstat.c file can be used in two modes:-
1) Auto Mode:It makes use of perfstat_cpu_util API to calculate utilization values,enable 'UTIL_AUTO' macro for execution in auto mode.
2) Manual Mode: Calculations are done in the current code.
*/

/* #define UTIL_AUTO */

#ifdef UTIL_AUTO
#define UTIL_MS 1
#define UTIL_PCT 0
#define UTIL_CORE 2
#define UTIL_PURR 0
#define UTIL_SPURR 1
void display_metrics_global_auto(int mode,int cpmode,int count,int interval);
#endif

/* To Check whether malloc is successful or not */
#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
                                perror ("malloc");\
                                exit(2);\
                                }\
}

/* Convert 4K pages to MB */
#define AS_MB(X) ((X) * 4096/1024/1024)

/* WPAR ID for global will always be zero */
#define IS_GLOBAL(X) (!(X))

/* Non zero WPAR ID indicates WPAR */
#define IS_WPAR(X) ((X))

/* For WPAR, use NULL else use the actual WPAR ID (for global) */
#define WPAR_ID ((cid)?NULL:&wparid)

/* To store the count of Logical CPUs in the LPAR */

/* Default values for interval and count */

#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1

static int ncpu, atflag;
static int returncode, count = COUNT_DEFAULT, interval = INTERVAL_DEFAULT;
unsigned long long last_user, last_sys, last_idle, last_wait, last_timebase;
unsigned long long delta_user, delta_sys, delta_wait, delta_idle, delta_total, delta_timebase;

/* store LPAR level stats */
perfstat_cpu_total_t *totalcinfo, *totalcinfo_last;
perfstat_memory_total_t minfo;
perfstat_partition_total_t pinfo, qinfo;
perfstat_cpu_t *cinfo, *cinfo_last;

/* stores wpar id for perfstat library */
perfstat_id_wpar_t wparid;

/* store per WPAR stats */
perfstat_wpar_total_t winfo;
perfstat_cpu_total_wpar_t cinfo_wpar;

/* store current WPAR ID */
cid_t cid;
char wpar[MAXCORRALNAMELEN+1];

/* support for remote node statistics collection in a cluster environment */
perfstat_id_node_t nodeid;
char nodename[MAXHOSTNAMELEN];
```

```

int nflag = 0;
/* display the usage */

void showusage(char *cmd)
{
    if (!cid)
        fprintf(stderr, "usage: %s [-@ { ALL | WPARNAME } | -n nodename ] [-i <interval in seconds> ] [-c <number of iterations> ]\n", cmd);
    else
        fprintf(stderr, "usage: %s [-i <interval in seconds> ] [-c <number of iterations> ]\n", cmd);
    exit(1);
}

/* Save the current values for the next iteration */

void save_last_values (void)
{
    memcpy( totalcinfo_last, totalcinfo, sizeof(perfstat_cpu_total_t));
    memcpy( cinfo_last, cinfo, sizeof(perfstat_cpu_t));
}

void initialise(void)
{
    totalcinfo = (perfstat_cpu_total_t *)malloc(sizeof(perfstat_cpu_total_t));
    CHECK_FOR_MALLOC_NULL(totalcinfo);

    totalcinfo_last = (perfstat_cpu_total_t *)malloc(sizeof(perfstat_cpu_total_t));
    CHECK_FOR_MALLOC_NULL(totalcinfo_last);

    cinfo = (perfstat_cpu_t *)malloc(sizeof(perfstat_cpu_t) * ncpu);
    CHECK_FOR_MALLOC_NULL(cinfo);

    cinfo_last = (perfstat_cpu_t *)malloc(sizeof(perfstat_cpu_t) * ncpu);
    CHECK_FOR_MALLOC_NULL(cinfo_last);
}

void display_configuration (void)
{
    unsigned long long memlimit;
    double cpulimit;
    int i ,totalcpu;

    /* gather LPAR level data */
    if(nflag) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        if (perfstat_partition_total_node(&nodeid, &pinfo, sizeof(perfstat_partition_total_t), 1) <= 0) {
            perror("perfstat_partition_total_node:");
            exit(1);
        }

        if (perfstat_memory_total_node(&nodeid, &minfo, sizeof(perfstat_memory_total_t), 1) <= 0) {
            perror("perfstat_memory_total_node:");
            exit(1);
        }

        totalcpu = perfstat_cpu_node(&nodeid, NULL, sizeof(perfstat_cpu_t), 0);
    }
    else {
        if (perfstat_partition_total(NULL, &pinfo, sizeof(perfstat_partition_total_t), 1) <= 0) {
            perror("perfstat_partition_total:");
            exit(1);
        }

        if (perfstat_memory_total(NULL, &minfo, sizeof(perfstat_memory_total_t), 1) <= 0) {
            perror("perfstat_memory_total:");
            exit(1);
        }

        totalcpu = perfstat_cpu(NULL, NULL, sizeof(perfstat_cpu_t), 0);
    }

    /* print LPAR configuration */
    printf("Purr counter value = %lld \n",pinfo.purr_counter);
    printf("Spurr counter value = %lld \n",pinfo.spurr_counter);
    printf("Free memory = %lld \n",pinfo.real_free);
    printf("Available memory = %lld \n",pinfo.real_avail);

    printf("\n\lpar configuration : ");
    printf("\lcpus = %d ", totalcpu); /* number of CPUs online */
    printf("mem = %lluMB ", AS_MB(minfo.real_total)); /* real memory */
    printf("ent = %#5.2f\n", (double)pinfo.entitled_proc_capacity/100.0); /* entitled capacity */
}

/*
 * NAME: display_metrics_global
 * used to display the metrics when called from global
 */

```

```

void display_metrics_global(void)
{
    int i;
    perfstat_id_t first;

    strcpy(first.name, FIRST_CPU);
    if(nflag){
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        if (perfstat_cpu_total_node(&nodeid, totalcinfo_last, sizeof(perfstat_cpu_total_t), 1) <= 0){
            perror("perfstat_cpu_total_node:");
            exit(1);
        }

        if (perfstat_cpu_node(&nodeid, cinfo_last, sizeof(perfstat_cpu_t), ncpu) <= 0){
            perror("perfstat_cpu_node:");
            exit(1);
        }

        if (perfstat_partition_total_node(&nodeid, &qinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
            perror("perfstat_partition_total_node:");
            exit(1);
        }
    }
    else{
        if (perfstat_cpu_total(NULL, totalcinfo_last, sizeof(perfstat_cpu_total_t), 1) <= 0){
            perror("perfstat_cpu_total:");
            exit(1);
        }

        if (perfstat_cpu(&first, cinfo_last, sizeof(perfstat_cpu_t), ncpu) <= 0){
            perror("perfstat_cpu:");
            exit(1);
        }

        if (perfstat_partition_total(NULL, &qinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
            perror("perfstat_partition_total:");
            exit(1);
        }
    }
    printf("\n cpu\tuser\tsys\twait\tidle\tstate\n\n");

    while(count)
    {
        sleep(interval);

        if(nflag){
            if (perfstat_cpu_total_node(&nodeid, totalcinfo, sizeof(perfstat_cpu_total_t), 1) <= 0){
                perror("perfstat_cpu_total_node:");
                exit(1);
            }

            if (perfstat_cpu_node(&nodeid, cinfo, sizeof(perfstat_cpu_t), ncpu) <= 0){
                perror("perfstat_cpu_node:");
                exit(1);
            }

            if (perfstat_partition_total_node(&nodeid, &pinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
                perror("perfstat_partition_total_node:");
                exit(1);
            }
        }
        else{
            if (perfstat_cpu_total(NULL, totalcinfo, sizeof(perfstat_cpu_total_t), 1) <= 0){
                perror("perfstat_cpu_total:");
                exit(1);
            }

            if (perfstat_cpu(&first, cinfo, sizeof(perfstat_cpu_t), ncpu) <= 0){
                perror("perfstat_cpu:");
                exit(1);
            }

            if (perfstat_partition_total(NULL, &pinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
                perror("perfstat_partition_total:");
                exit(1);
            }
        }
    }

    for(i = 0; i < ncpu; i++){
        delta_user = cinfo[i].puser - cinfo_last[i].puser;
        delta_sys = cinfo[i].psys - cinfo_last[i].psys;
        delta_idle = cinfo[i].pidle - cinfo_last[i].pidle;
        delta_wait = cinfo[i].pwait - cinfo_last[i].pwait;
        delta_total = delta_user + delta_sys + delta_idle + delta_wait;
        delta_timebase = pinfo.timebase_last - qinfo.timebase_last;
        if(!delta_total)
            continue;
    }
}

```

```

        printf("%s\t%#4.1f\t%#4.1f\t%#4.1f\t%#4.1d\n",cinfo[i].name,
            ((double)(delta_user)/(double)(delta_total) * 100.0),
            ((double)(delta_sys)/(double)(delta_total) * 100.0),
            ((double)(delta_wait)/(double)(delta_total) * 100.0),
            ((double)(delta_idle)/(double)(delta_total) * 100.0),
            cinfo[i].state);
    }
    delta_user = totalcinfo->puser - totalcinfo_last->puser;
    delta_sys = totalcinfo->psys - totalcinfo_last->psys;
    delta_wait = totalcinfo->pwait - totalcinfo_last->pwait;
    delta_idle = totalcinfo->pidle - totalcinfo_last->pidle;
    delta_total= delta_user + delta_sys + delta_idle + delta_wait;

    printf("%s\t%#4.1f\t%#4.1f\t%#4.1f\t%#4.1f\n", "ALL", ((double)(delta_user)/(double)(delta_total) * 100.0),
        ((double)(delta_sys)/(double)(delta_total) * 100.0),
        ((double)(delta_wait)/(double)(delta_total) * 100.0),
        ((double)(delta_idle)/(double)(delta_total) * 100.0));

    count--;
    save_last_values();
}
}

/*
*NAME: display_metrics_wpar
* used to display the metrics when called from wpar
*
*/
void display_metrics_wpar(void)
{
    int i;
    char last[5];
    perfstat_id_wpar_t first;
    /*first.spec = WPARNAME;*/
    strcpy(first.name, NULL);
    if (perfstat_wpar_total(NULL, &winfo, sizeof(perfstat_wpar_total_t), 1) <= 0){
        perror("perfstat_wpar_total:");
        exit(1);
    }

    if (perfstat_cpu_total_rset(NULL, totalcinfo_last, sizeof(perfstat_cpu_total_t), 1) <= 0){
        perror("perfstat_cpu_total_rset:");
        exit(1);
    }

    if (perfstat_cpu_rset(NULL, cinfo_last, sizeof(perfstat_cpu_t), ncpu) <= 0){
        perror("perfstat_cpu_rset:");
        exit(1);
    }

    if (perfstat_partition_total(NULL, &qinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
        perror("perfstat_partition_total:");
        exit(1);
    }
    printf("\n cpu\tuser\tsys\twait\tidle\n\n");

    while(count)
    {
        sleep(interval);

        if (perfstat_cpu_total_rset(NULL, totalcinfo, sizeof(perfstat_cpu_total_t), 1) <= 0){
            perror("perfstat_cpu_total_rset:");
            exit(1);
        }

        if (perfstat_cpu_rset(NULL, cinfo, sizeof(perfstat_cpu_t), ncpu) <= 0){
            perror("perfstat_cpu_rset:");
            exit(1);
        }

        if (perfstat_partition_total(NULL, &pinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
            perror("perfstat_partition_total:");
            exit(1);
        }

        for(i=0; i<ncpu; i++){
            delta_user = cinfo[i].puser - cinfo_last[i].puser;
            delta_sys = cinfo[i].psys - cinfo_last[i].psys;
            delta_idle = cinfo[i].pidle - cinfo_last[i].pidle;
            delta_wait = cinfo[i].pwait - cinfo_last[i].pwait;
            delta_total= delta_user + delta_sys + delta_idle + delta_wait;
            delta_timebase = pinfo.timebase_last - qinfo.timebase_last;
            if(!delta_total)
                continue;

            printf("%s\t%#4.1f\t%#4.1f\t%#4.1f\t%#4.1f\n",cinfo[i].name,((double)(delta_user)/(double)(delta_total) * 100.0),
                ((double)(delta_sys)/(double)(delta_total) * 100.0),
                ((double)(delta_wait)/(double)(delta_total) * 100.0),
                ((double)(delta_idle)/(double)(delta_total) * 100.0));

```

```

}

delta_user = totalcinfo->puser - totalcinfo_last->puser;
delta_sys = totalcinfo->psys - totalcinfo_last->psys;
delta_wait = totalcinfo->pwait - totalcinfo_last->pwait;
delta_idle = totalcinfo->pidle - totalcinfo_last->pidle;
delta_total= delta_user + delta_sys + delta_idle + delta_wait;

if (winfo.type.b.cpu_rset)
    strcpy(last,"RST");
else
    strcpy(last,"ALL");

printf("%s\t%#4.1f\t%#4.1f\t%#4.1f\t%#4.1f\n",last,((double)(delta_user)/(double)(delta_total) * 100.0),
                                             ((double)(delta_sys)/(double)(delta_total) * 100.0),
                                             ((double)(delta_wait)/(double)(delta_total) * 100.0),
                                             ((double)(delta_idle)/(double)(delta_total) * 100.0));

count--;
save_last_values();
}
}

/*
 * NAME: display_metrics_wpar_from_global
 *      display metrics of wpar when called from global
 *
 */
void display_metrics_wpar_from_global(void)
{
    char last[5];
    int i;
    if (perfstat_wpar_total(&wparid, &winfo, sizeof(perfstat_wpar_total_t), 1) <= 0){
        perror("perfstat_wpar_total:");
        exit(1);
    }
    if (winfo.type.b.cpu_rset)
        strcpy(last,"RST");
    else
        strcpy(last,"ALL");

    strcpy(wparid.u.wparname,wpar);

    if (perfstat_cpu_total_rset(&wparid, totalcinfo_last, sizeof(perfstat_cpu_total_t), 1) <= 0){
        perror("perfstat_cpu_total_rset:");
        exit(1);
    }

    if (perfstat_cpu_rset(&wparid, cinfo_last, sizeof(perfstat_cpu_t), ncpu) <= 0){
        perror("perfstat_cpu_rset:");
        exit(1);
    }

    if (perfstat_partition_total(NULL, &qinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
        perror("perfstat_partition_total:");
        exit(1);
    }

    printf("\n cpu\tuser\tsys\twait\tidle\n");

    while(count)
    {
        sleep(interval);

        if (perfstat_cpu_total_rset(&wparid, totalcinfo, sizeof(perfstat_cpu_total_t), 1) <= 0){
            perror("perfstat_cpu_total_rset:");
            exit(1);
        }

        if (perfstat_cpu_rset(&wparid, cinfo, sizeof(perfstat_cpu_t), ncpu) <= 0){
            perror("perfstat_cpu_rset:");
            exit(1);
        }

        if (perfstat_partition_total(NULL, &pinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
            perror("perfstat_partition_total:");
            exit(1);
        }

        for(i = 0; i < ncpu; i++){
            delta_user = cinfo[i].puser - cinfo_last[i].puser;
            delta_sys = cinfo[i].psys - cinfo_last[i].psys;
            delta_idle = cinfo[i].pidle - cinfo_last[i].pidle;
            delta_wait = cinfo[i].pwait - cinfo_last[i].pwait;
            delta_total= delta_user + delta_sys + delta_idle + delta_wait;
            delta_timebase = pinfo.timebase_last - qinfo.timebase_last;
            if(!delta_total)
                continue;

```

```

printf("%s\t%#4.1f\t%#4.1f\t%#4.1f\t%#4.1f\n",cinfo[i].name,((double)(delta_user)/(double)(delta_total) * 100.0),
((double)(delta_sys)/(double)(delta_total) * 100.0),
((double)(delta_wait)/(double)(delta_total) * 100.0),
((double)(delta_idle)/(double)(delta_total) * 100.0));
}

delta_user = totalcinfo->puser - totalcinfo_last->puser;
delta_sys = totalcinfo->psys - totalcinfo_last->psys;
delta_wait = totalcinfo->pwait - totalcinfo_last->pwait;
delta_idle = totalcinfo->pidle - totalcinfo_last->pidle;
delta_total= delta_user + delta_sys + delta_idle + delta_wait;

printf("%s\t%#4.1f\t%#4.1f\t%#4.1f\t%#4.1f\n",last, ((double)(delta_user)/(double)(delta_total) * 100.0),
((double)(delta_sys)/(double)(delta_total) * 100.0),
((double)(delta_wait)/(double)(delta_total) * 100.0),
((double)(delta_idle)/(double)(delta_total) * 100.0));

count--;
save_last_values();
}
}

#ifdef UTIL_AUTO
void display_metrics_global_auto(int mode,int cpumode,int count,int interval)
{
float user_core_purr,kern_core_purr,wait_core_purr,idle_core_purr;
float user_core_spurr,kern_core_spurr,wait_core_spurr,idle_core_spurr,sum_core_spurr;
u_longlong_t user_ms_purr,kern_ms_purr,wait_ms_purr,idle_ms_purr,sum_ms;
u_longlong_t user_ms_spurr,kern_ms_spurr,wait_ms_spurr,idle_ms_spurr;
perfstat_rawdata_t data;
u_longlong_t delta_purr;
double phys_proc_consumed, entitlement, percent_ent, delta_sec;
perfstat_partition_total_t lparstats;
static perfstat_cpu_t *oldt,*newt;
perfstat_cpu_util_t *util;
int rc,cpu_count,1;
perfstat_id_t id;

/* retrieve the metrics */
while(count) {
/* Print the header for utilization metrics (only once) */
if (disp_util_header) {
if(mode==UTIL_PCT)
printf("\nCPU %5s %5s %6s %6s %5s \n",
"user", "sys", "%wait", "%idle", "physc");
else if(mode==UTIL_MS)
printf("\nCPU %5s %5s %6s %6s %5s \n",
"user(ms)", "sys(ms)", "wait(ms)", "idle(ms)", "physc");
else if(mode==UTIL_CORE)
printf("\nCPU %5s %5s %6s %6s %5s %5s \n",
"user", "sys", "wait", "idle", "physc", "state");

/* first iteration, we only read the data, print the header and save the data */
}
cpu_count = perfstat_cpu(NULL, NULL,sizeof(perfstat_cpu_t),0);

/* check for error */
if(cpu_count <= 0)
{
perror("Error in perfstat_cpu");
exit(-1);
}

/* allocate enough memory */
oldt = (perfstat_cpu_t *)calloc(cpu_count,sizeof(perfstat_cpu_t));
if(oldt == NULL)
{
perror("Memory Allocation Error");
exit(-1);
}
/* set name to first cpu */
strcpy(id.name,FIRST_CPU);

/* ask to get all the structures available in one call */
rc = perfstat_cpu(&id, oldt, sizeof(perfstat_cpu_t), cpu_count);

/* check for error */
if(rc <=0)
{
perror("Error in perfstat_cpu");
exit(-1);
}

data.type = UTIL_CPU;
}
}

```

```

data.prevstat= oldt;
data.sizeof_data = sizeof(perfstat_cpu_t);
data.prev_elems = cpu_count;

sleep(interval);

/* Check how many perfstat_cpu_t structures are available after a defined period */
cpu_count = perfstat_cpu(NULL, NULL, sizeof(perfstat_cpu_t), 0);

/* Check for error */
if(cpu_count <= 0)
{
    perror("Error in perfstat_cpu");
    exit(-1);
}

data.cur_elems = cpu_count;

if(data.prev_elems != data.cur_elems)
{
    perror("The number of CPUs has become different for defined period");
    exit(-1);
}

/* allocate enough memory */
newt = (perfstat_cpu_t *)calloc(cpu_count, sizeof(perfstat_cpu_t));
util = (perfstat_cpu_util_t *)calloc(cpu_count, sizeof(perfstat_cpu_util_t));

if(newt == NULL || util == NULL)
{
    perror("Memory Allocation Error");
    exit(-1);
}
data.curstat = newt;
rc = perfstat_cpu(&id, newt, sizeof(perfstat_cpu_t), cpu_count);
if(rc <= 0)
{
    perror("Error in perfstat_cpu");
    exit(-1);
}

/* Calculate CPU Utilization Metrics*/
rc = perfstat_cpu_util(&data, util, sizeof(perfstat_cpu_util_t), cpu_count);
if(rc <= 0)
{
    perror("Error in perfstat_cpu_util");
    exit(-1);
}

switch(mode)
{
case UTIL_PCT:
    for(i=0; i<cpu_count; i++)
        printf("%d %5.1f %5.1f %5.1f %5.1f %5.7f \n", i, util[i].user_pct, util[i].kern_pct, util[i].wait_pct, util[i].idle_pct, util[i].physical_consumed);
    break;

case UTIL_MS:
    for(i=0; i<cpu_count; i++)
    {
        user_ms_purr=((util[i].user_pct*util[i].delta_time)/100.0);
        kern_ms_purr=((util[i].kern_pct*util[i].delta_time)/100.0);
        wait_ms_purr=((util[i].wait_pct*util[i].delta_time)/100.0);
        idle_ms_purr=((util[i].idle_pct*util[i].delta_time)/100.0);
        if(cpumode==UTIL_PURR)
        {
            printf("%d\t %llu\t %llu\t %llu\t %llu\t %5.4f\n", i, user_ms_purr, kern_ms_purr, wait_ms_purr, idle_ms_purr, util[i].physical_consumed);
        }
        else if(cpumode==UTIL_SPURR)
        {
            user_ms_spurr=(user_ms_purr*util[i].freq_pct)/100.0;
            kern_ms_spurr=(kern_ms_purr*util[i].freq_pct)/100.0;
            wait_ms_spurr=(wait_ms_purr*util[i].freq_pct)/100.0;
            sum_ms=user_ms_spurr+kern_ms_spurr+wait_ms_spurr;
            idle_ms_spurr=util[i].delta_time-sum_ms;

            printf("%d\t %llu\t %llu\t %llu\t %llu\t %5.4f \n", i, user_ms_spurr, kern_ms_spurr, wait_ms_spurr, idle_ms_spurr, util[i].physical_consumed);
        }
    }
    break;

case UTIL_CORE:
    for(i=0; i<cpu_count; i++)
    {
        user_core_purr=((util[i].user_pct*util[i].physical_consumed)/100.0);
        kern_core_purr=((util[i].kern_pct*util[i].physical_consumed)/100.0);
        wait_core_purr=((util[i].wait_pct*util[i].physical_consumed)/100.0);
        idle_core_purr=((util[i].idle_pct*util[i].physical_consumed)/100.0);

        user_core_spurr=((user_core_purr*util[i].freq_pct)/100.0);
        kern_core_spurr=((kern_core_purr*util[i].freq_pct)/100.0);
        wait_core_spurr=((wait_core_purr*util[i].freq_pct)/100.0);

        if(cpumode==UTIL_PURR)
        {
            printf("%d %5.4f %5.4f %5.4f %5.4f %5.4f\n", i, user_core_purr, kern_core_purr, wait_core_purr, idle_core_purr, util[i].physical_consumed);
        }
    }
}

```

```

    }
else if(cpumode==UTIL_SPURR)
{
    sum_core_spurr=user_core_spurr+kern_core_spurr+wait_core_spurr;
    idle_core_spurr=util[i].physical_consumed-sum_core_spurr;

    printf("%d %5.4f %5.4f %5.4f %5.4f %5.4f \n",i,user_core_spurr,kern_core_spurr,wait_core_spurr,idle_core_spurr,util[i].physical_consumed);
}
}
break;

default:
printf("In correct usage\n");
return;
}
count--;
}
}
#endif

/*
*NAME: main
*
*/

int main(int argc,char* argv[])
{
    int c, rc;
    int mode,cpumode;

    cid = corral_getcid();

    while((c = getopt(argc, argv, "@:n:i:c:"))!= EOF){
        switch(c)
        {
            case 'i': /* Interval */
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c': /* Number of iterations */
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'n': /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                nflag = 1;
                break;
            case '@': /* Per-WPAR stats */
                if (IS_WPAR(cid))
                    showusage(argv[0]);
                atflag = 1;
                strcpy(wpar, optarg);
                break;
            default: /* Invalid arguments. Print the usage and terminate */
                showusage(argv[0]);
        }
    }
    if (nflag && atflag){
        showusage(argv[0]);
    }
    if(nflag)
    { /* perfstat_config needs to be called to enable cluster statistics collection */
        rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
        if (rc == -1)
        {
            perror("cluster statistics collection is not available");
            exit(-1);
        }
    }
    if (atflag){
        wparid.spec = WPARNAME;
        strcpy(wparid.u.wparname,wpar);
        ncpu = perfstat_cpu_rset ( &wparid, NULL, sizeof(perfstat_cpu_t), 0);
    }
    else if (nflag){
        nodeid.spec = NODENAME;
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        ncpu = perfstat_cpu_node(&nodeid, NULL, sizeof(perfstat_cpu_t), 0);
    }
    else if (IS_GLOBAL(cid)){
        ncpu = perfstat_cpu(NULL, NULL, sizeof(perfstat_cpu_t), 0);
    }
    else{
        ncpu = perfstat_cpu_rset(NULL, NULL, sizeof(perfstat_cpu_t), 0);
    }

    initialise();
}

```

```

display_configuration();

if(atflag)
    display_metrics_wpar_from_global();
else if (cid)
    display_metrics_wpar();
else
    #ifdef UTIL_AUTO
    printf("Enter CPU mode.\n");
    printf(" 0 PURR \n 1 SPURR \n");
    scanf("%d",&cpumode);
    printf("Enter print mode.\n");
    printf(" 0 PERCENTAGE\n 1 MILLISECONDS\n 2 CORES \n");
    scanf("%d",&mode);

    if((mode>2)&& (cpumode>1))
    {
        printf("Error: Invalid Input\n");
        exit(0);
    }
    display_metrics_global_auto(mode,cpumode,count,interval);
    #else
    display_metrics_global();
    #endif
    if(nflag)
    { /* Now disable cluster statistics by calling perfstat_config */
        perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
    }
    return(0);
}

```

The program displays an output that is similar to the following example output:

```

Purr counter value = 54500189780
Spurr counter value = 54501115744
Free memory = 760099
Available memory = 758179

```

```

lpar configuration : lcpus = 8 mem = 4096MB ent = 1.00

```

cpu	user	sys	wait	idle	state
cpu0	26.8	54.9	0.0	18.3	1
cpu1	0.0	2.3	0.0	97.7	1
cpu2	0.0	4.7	0.0	95.3	1
cpu3	0.0	2.5	0.0	97.5	1
cpu4	0.0	49.6	0.0	50.4	1
cpu5	0.0	12.7	0.0	87.3	1
cpu6	0.0	10.5	0.0	89.5	1
cpu7	0.0	10.7	0.0	89.3	1
ALL	10.7	24.9	0.0	64.4	

## perfstat\_disk Interface

The `perfstat_disk` interface returns a set of structures of type `perfstat_disk_t`, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_disk_t` structure include:

Item	Descriptor
<code>name</code>	Disk name (from ODM)
<code>description</code>	Disk description (from ODM)
<code>vgname</code>	Volume group name (from ODM)
<code>size</code>	Disk size (in MB)
<code>free</code>	Free space (in MB)
<code>xfers</code>	Transfers to/from disk (in KB)

Several other disk-related metrics (such as number of blocks read from and written to disk, and adapter names) are also returned. For a complete list, see the `perfstat_disk_t` section in the `libperfstat.h` header file in *Files Reference*.

The following program emulates `diskstat` behavior and also shows an example of how the `perfstat_disk` interface is used:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(int argc, char* argv[]) {
    int i, ret, tot;
    perfstat_disk_t *statp;
    perfstat_id_t first;

    /* check how many perfstat_disk_t structures are available */
    tot = perfstat_disk(NULL, NULL, sizeof(perfstat_disk_t), 0);

    /* check for error */
    if (tot < 0)
    {
        perror("perfstat_disk");
        exit(-1);
    }
    if (tot == 0)
    {
        printf("No disks found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    statp = calloc(tot, sizeof(perfstat_disk_t));

    /* set name to first interface */
    strcpy(first.name, FIRST_DISK);

    /* ask to get all the structures available in one call */
    /* return code is number of structures returned */
    ret = perfstat_disk(&first, statp,
        sizeof(perfstat_disk_t), tot);

    /* check for error */
    if (ret <= 0)
    {
        perror("perfstat_disk");
        exit(-1);
    }

    /* print statistics for each of the disks */
    for (i = 0; i < ret; i++) {
        printf("\nStatistics for disk : %s\n", statp[i].name);
        printf("-----\n");
        printf("description           : %s\n", statp[i].description);
        printf("volume group name      : %s\n", statp[i].vgname);
        printf("adapter name          : %s\n", statp[i].adapter);
        printf("size                   : %llu MB\n", statp[i].size);
        printf("free space             : %llu MB\n", statp[i].free);
        printf("number of blocks read  : %llu blocks of %llu bytes\n", statp[i].rblks, statp[i].bsize);
        printf("number of blocks written : %llu blocks of %llu bytes\n", statp[i].wblks, statp[i].bsize);
    }
}

```

The preceding program produces the following output:

```

Statistics for disk : hdisk1
-----
description           : 16 Bit SCSI Disk Drive
volume group name      : rootvg
adapter name          : scsi0
size                   : 4296 MB
free space             : 2912 MB
number of blocks read  : 403946 blocks of 512 bytes
number of blocks written : 768176 blocks of 512 bytes

```

```

Statistics for disk : hdisk0
-----
description      : 16 Bit SCSI Disk Drive
volume group name : None
adapter name     : scsi0
size             : 0 MB
free space       : 0 MB
number of blocks read : 0 blocks of 512 bytes
number of blocks written : 0 blocks of 512 bytes

```

```

Statistics for disk : cd0
-----
description      : SCSI Multimedia CD-ROM Drive
volume group name : not available
adapter name     : scsi0
size             : 0 MB
free space       : 0 MB
number of blocks read : 3128 blocks of 2048 bytes
number of blocks written : 0 blocks of 2048 bytes

```

## perfstat\_diskpath Interface

The **perfstat\_diskpath** interface returns a set of structures of type **perfstat\_diskpath\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_diskpath\_t** structure include:

Item	Descriptor
<b>name</b>	Path name (<disk_name>_Path<path_id>)
<b>xfers</b>	Total transfers through this path (in KB)
<b>adapter</b>	Name of the adapter linked to the path

Several other disk path-related metrics (such as the number of blocks read from and written through the path) are also returned. For a complete list, see the **perfstat\_diskpath\_t** section in the **libperfstat.h** header file.

The following code shows an example of how the **perfstat\_diskpath** interface is used:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(int argc, char* argv[]) {
    int ret, tot, i;
    perfstat_diskpath_t *statp;
    perfstat_id_t first;
    char *substring;
    perfstat_disk_t dstat;

    /* check how many perfstat_diskpath_t structures are available */
    tot = perfstat_diskpath(NULL, NULL, sizeof(perfstat_diskpath_t), 0);

    /* check for error */
    if (tot < 0)
    {
        perror("perfstat_diskpath");
        exit(-1);
    }

    if (tot == 0)
    {
        printf("No Paths found in the system\n");
        exit(-1);
    }
}

```

```

}

/* allocate enough memory for all the structures */
statp = calloc(tot, sizeof(perfstat_diskpath_t));
if(statp==NULL){
printf("No sufficient memory\n");
exit(-1);
}

/* set name to first interface */
strcpy(first.name, FIRST_DISKPATH);

/* ask to get all the structures available in one call */
/* return code is number of structures returned */
ret = perfstat_diskpath(&first, statp, sizeof(perfstat_diskpath_t), tot);

/* check for error */
if (ret <= 0)
{

perror("perfstat_diskpath");
exit(-1);
}

/* print statistics for each of the disk paths */
for (i = 0; i < ret; i++) {
printf("\nStatistics for disk path : %s\n", statp[i].name);
printf("-----\n");
printf("number of blocks read      : %llu\n", statp[i].rblks);
printf("number of blocks written   : %llu\n", statp[i].wblks);
printf("adapter name                : %s\n", statp[i].adapter);
}

/* retrieve paths for last disk if any */
if (ret > 0) {
/* extract the disk name from the last disk path name */
substring = strstr(statp[ret-1].name, "_Path");
if (substring == NULL) {
return (-1);
}
substring[0] = '\0';

/* set name to the disk name */
strcpy(first.name, substring);
/* retrieve info about disk */
ret = perfstat_disk(&first, &dstat, sizeof(perfstat_disk_t),1);

if (ret <= 0)
{
perror("perfstat_diskpath");
exit(-1);
}

printf("\nPaths for disk path : %s (%d)\n", dstat.name, dstat.paths_count);
printf("-----\n");

/* retrieve all paths for this disk */
ret = perfstat_diskpath(&first, statp, sizeof(perfstat_diskpath_t), dstat.paths_count);
if (ret <= 0)
{
perror("perfstat_diskpath");
exit(-1);
}

/* print statistics for each of the paths */
for (i = 0; i < ret; i++) {

```

```

        printf("\nStatistics for disk path : %s\n", statp[i].name);
        printf("-----\n");
        printf("number of blocks read      : %llu\n", statp[i].rblks);
        printf("number of blocks written   : %llu\n", statp[i].wblks);
        printf("adapter name                : %s\n", statp[i].adapter);
    }
}

```

The program displays an output that is similar to the following example output:

```
Statistics for disk path : hdisk0_Path0
```

```
-----
number of blocks read      : 335354
number of blocks written   : 291416
adapter name              : vscsi0
```

```
Paths for disk path : hdisk0 (1)
```

```
-----
Statistics for disk path : hdisk0_Path0
```

```
-----
number of blocks read      : 335354
number of blocks written   : 291416
adapter name              : vscsi0
```

## perfstat\_diskadapter Interface

The `perfstat_diskadapter` interface returns a set of structures of type `perfstat_diskadapter_t`, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_diskadapter_t` structure include:

Item	Descriptor
<code>name</code>	Adapter name (from ODM)
<code>description</code>	Adapter description (from ODM)
<code>size</code>	Total disk size connected to this adapter (in MB)
<code>free</code>	Total free space on disks connected to this adapter (in MB)
<code>xfers</code>	Total transfers to/from this adapter (in KB)

Several other disk adapter-related metrics (such as the number of blocks read from and written to the adapter) are also returned. For a complete list, see the `perfstat_diskadapter_t` section in the `libperfstat.h` header file.

The following program emulates the `diskadapterstat` behavior and also shows an example of how the `perfstat_diskadapter` interface is used:

```

#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <errno.h>
#include <libperfstat.h>
#include <errno.h>
#include <wpars/wparcfg.h>

/* Non zero WPAR ID indicates WPAR */
#define IS_WPAR(X) ((X))

/* To Check whether malloc is successful or not */
#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
    perror ("malloc");\
    exit(2);\
}\
}

/* Default values for interval and count */
#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1

/* Function prototypes */

static int do_initialization(void);

```

```

static void do_cleanup(void);
static void collect_disk_metrics(void);
static void print_disk_header(void);
static void showusage(char *);

/* variables and data structures declaration */

static perfstat_diskadapter_t *statp, *statq;
static int num_adapt;
static int interval = INTERVAL_DEFAULT;
static int count = COUNT_DEFAULT;
static int rc;

/* support for remote node statistics collection in a cluster environment */
static perfstat_id_node_t nodeid;
static char nodename[MAXHOSTNAMELEN] = "";
static int collect_remote_node_stats = 0;

cid_t cid;          /* store the WPAR cid */

/*
 * NAME: do_initialization
 * This function initializes the data structures.
 * It also collects initial set of values.
 *
 * RETURNS:
 * On successful completion:
 * - returns 0.
 * In case of error
 * - exit with code 1.
 */
static int do_initialization(void)
{
    if (collect_remote_node_stats){
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        /* Get the total number of disk adapters available in the current system */
        num_adapt = perfstat_diskadapter_node(&nodeid, NULL, sizeof(perfstat_diskadapter_t), 0);
    }
    else{
        /* Get the total number of disk adapters available in the current system */
        num_adapt = perfstat_diskadapter(NULL, NULL, sizeof(perfstat_diskadapter_t), 0);
    }

    if (num_adapt == 0) {
        printf("There are no disk adapters.\n");
        exit(0);
    }

    if (num_adapt < 0) {
        perror("perfstat_diskadapter: ");
        exit(1);
    }

    /* Allocate sufficient memory for perfstat structures */

    statp = (perfstat_diskadapter_t *)malloc(sizeof(perfstat_diskadapter_t) * num_adapt);
    CHECK_FOR_MALLOC_NULL(statp);

    statq = (perfstat_diskadapter_t *)malloc(sizeof(perfstat_diskadapter_t) * num_adapt);
    CHECK_FOR_MALLOC_NULL(statq);

    /* Make the structures as 0 */
    memset(statq, 0, (sizeof(perfstat_diskadapter_t) * num_adapt));

    memset(statp, 0, (sizeof(perfstat_diskadapter_t) * num_adapt));

    return (0);
}

/*
 *NAME: Showusage
 * This function displays the usage
 */

void showusage (char *cmd)
{
    fprintf(stderr, "usage: %s [-i <interval in seconds> ] [-c <number of iterations> ] [-n <node name in the cluster> ]\n", cmd);
    exit(1);
}

/*
 * NAME: do_cleanup
 * This function frees the memory allocated for the perfstat structures.
 */

```

```

*/
static void do_cleanup(void)
{
    if (statp) {
        free(statp);
    }

    if (statq) {
        free(statq);
    }
}

/*
 * NAME: collect_diskadapter_metrics
 * This function collects the raw values in to
 * the specified structures and derive the metrics from the
 * raw values
 */
void collect_diskadapter_metrics(void)
{
    perfstat_id_t first;
    unsigned long long delta_read, delta_write, delta_xfers, delta_xrate;

    if (collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        strcpy(nodeid.name, FIRST_DISKADAPTER);
        rc = perfstat_diskadapter_node(&nodeid, statq, sizeof(perfstat_diskadapter_t), num_adapt);
    }
    else {
        strcpy(first.name, FIRST_DISKADAPTER);
        rc = perfstat_diskadapter(&first, statq, sizeof(perfstat_diskadapter_t), num_adapt);
    }

    if (rc < num_adapt) {
        perror("perfstat_diskadapter: ");
        exit(1);
    }

    /* Name - name of the diskadapter
     * Disks- number of disks connected
     * Size - total size of all the disks
     * Free - free space on disk
     * ARS - average read per second
     * AWS - average write per second
     */
    printf("\n%-8s %7s %8s %8s %8s %8s\n", " Name ", " Disks ", " Size ", " Free ", " ARS ", " AWS ");
    printf("%-8s %7s %8s %8s %8s %8s\n", "=====", "=====", "=====", "=====", "=====", "=====");

    while (count > 0) {
        sleep(interval);

        if (collect_remote_node_stats) {
            rc = perfstat_diskadapter_node(&nodeid, statp, sizeof(perfstat_diskadapter_t), num_adapt);
        }
        else {
            rc = perfstat_diskadapter(&first, statp, sizeof(perfstat_diskadapter_t), num_adapt);
        }

        if (rc < num_adapt) {
            perror("perfstat_diskadapter:");
            exit(-1);
        }

        /* print statistics for each of the diskadapter */
        for (int i = 0; i < rc; i++) {
            delta_write = statp[i].wblks - statq[i].wblks;
            delta_read = statp[i].rblks - statq[i].rblks;
            delta_xfers = statp[i].xfers - statq[i].xfers;
            delta_xrate = statp[i].xrate - statq[i].xrate;

            printf("%-8s %7d %8llu %8llu %8llu %8llu\n", statp[i].name, statp[i].number,
                statp[i].size, statp[i].free, (u_longlong_t)(delta_read / (statp[i].xrate - statq[i].xrate)),
                (u_longlong_t)(delta_write / (delta_xfers - delta_xrate)));
        }

        /* copy to the old data structures */
        memcpy(statq, statp, sizeof(perfstat_diskadapter_t) * num_adapt);
        count--;
        printf("\n");
    }

    /* Free all the memory allocated for all the data structures */
    do_cleanup();
}

```

```

/*
 *NAME: main
 */
int main(int argc, char* argv[])
{
    int i;
    cid = corral_getcid();

    /* Check Whether running Inside WPAR or on Global*/
    if(IS_WPAR(cid)) {
        printf("The metrics requested for WPAR cannot be retrieved.\n");
        exit(1);
    }

    /* Process the arguments */
    while ((i = getopt(argc, argv, "i:c:n:")) != EOF)
    {
        switch(i)
        {
            case 'i':          /* Interval */
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c':          /* Number of interations */
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'n':          /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                collect_remote_node_stats = 1;
                break;
            default:
                /* Invalid arguments. Print the usage and terminate */
                showusage(argv[0]);
        }
    }

    if(collect_remote_node_stats)
    {
        /* perfstat_config needs to be called to enable cluster statistics collection */
        rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
        if (rc == -1)
        {
            perror("cluster statistics collection is not available");
            exit(-1);
        }
    }
    do_initialization();
    /* call the functions to collect the metrics and display them */
    collect_diskadapter_metrics();

    if(collect_remote_node_stats)
    {
        /* Now disable cluster statistics by calling perfstat_config */
        perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
    }
    return (0);
}

```

The program displays an output that is similar to the following example output:

Name	Disks	Size	Free	ARS	AWS
===== vscsi0	===== 1	===== 25568	===== 19616	===== 1	===== 9

## perfstat\_fcstat Interface

The **perfstat\_fcstat** interface returns a set of structures of type **perfstat\_fcstat\_t**, which is defined in the **libperfstat.h** file.

The following program is an example of how the **perfstat\_fcstat** interface is used:

```

/* The sample program displays the metrics *
 * related to every Individual *
 * Fiber Channel adapter in the LPAR */
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

/* define default interval and count values */
#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1

/* Check value returned by malloc for NULL */
#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\

```

```

                perror("malloc");\
                exit(2);\
            }\
        }

int count = COUNT_DEFAULT, interval = INTERVAL_DEFAULT, tot=0;
int returncode=0;

/* store the data structures */
static perfstat_fcstat_t *statp=NULL, *statq=NULL;

/* support for remote node statistics collection in a cluster environment */
perfstat_id_node_t nodeid;
static char nodename[MAXHOSTNAMELEN] = "";
static int collect_remote_node_stats = 0;

unsigned long long wwpn_id=0;
int fc_flag=0, wwpn_flag=0;
char fcadapter_name[MAXHOSTNAMELEN];
/*
 * NAME: showusage
 *       to display the usage
 *
 */
void showusage(char *cmd)
{
    fprintf(stderr, "usage: %s [-i <interval in seconds> ] [-c <number of iterations> ] [-n <node name in the cluster> ] [-a FC adapter name] [-w worldwide port name] \n", cmd);
    exit(1);
}

/*
 * NAME: do_initialization
 *       This function initializes the data structures.
 *       It also collects the initial set of values.
 *
 * RETURNS:
 * On successful completion:
 * - returns 0.
 * In case of error
 * - exits with code 1.
 */

int do_initialization(void)
{
    /* check how many perfstat_fcstat_t structures are available */
    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        tot = perfstat_fcstat_node(&nodeid, NULL, sizeof(perfstat_fcstat_t), 0)
    ;
    }
    else if(fc_flag == 1 && wwpn_flag == 1)
    {
        tot = perfstat_fcstat_wwpn(NULL, NULL, sizeof(perfstat_fcstat_t), 0);
        if(tot >= 1)
        {
            tot = 1;
        }
    }
    else
    {
        printf("There is no FC adapter \n");
        exit(-1);
    }
}
else
{
    tot = perfstat_fcstat(NULL, NULL, sizeof(perfstat_fcstat_t), 0);
}
if (tot <= 0) {
    printf("There is no FC adapter\n");
    exit(0);
}

/* allocate enough memory for all the structures */

statp = (perfstat_fcstat_t *)malloc(tot * sizeof(perfstat_fcstat_t));
CHECK_FOR_MALLOC_NULL(statp);

statq = (perfstat_fcstat_t *)malloc(tot * sizeof(perfstat_fcstat_t));
CHECK_FOR_MALLOC_NULL(statq);
return(0);

```

```

}

/*
 *Name: display_metrics
 *      collect the metrics and display them
 *
 */
void display_metrics()
{
    perfstat_id_t first;
    perfstat_wwpn_id_t wwpn;
    int ret=0, i=0;

    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;

        strcpy(nodeid.name , FIRST_NETINTERFACE);
        ret = perfstat_fcstat_node(&nodeid, statq, sizeof(perfstat_fcstat_t), tot);
    } else if((fc_flag == 1) && (wwpn_flag == 1)) {
        strcpy(wwpn.name , fcadapter_name);
        wwpn.initiator_wwpn_name = wwpn_id;
        ret = perfstat_fcstat_wwpn( &wwpn, statq, sizeof(perfstat_fcstat_t), tot);
    }
    else
    {
        strcpy(first.name , FIRST_NETINTERFACE);
        ret = perfstat_fcstat( &first, statq, sizeof(perfstat_fcstat_t), tot);
    }
    if (ret < 0)
    {
        free(statp);
        free(statq);
        perror("perfstat_fcstat: ");
        exit(1);
    }
    while (count)
    {
        sleep (interval);
    }
    if(collect_remote_node_stats) {
        ret = perfstat_fcstat_node(&nodeid, statp, sizeof(perfstat_fcstat_t), tot);
    }
    if((fc_flag == 1) && (wwpn_flag == 1))
    {
        strcpy(wwpn.name , fcadapter_name);
        wwpn.initiator_wwpn_name = wwpn_id;
        ret = perfstat_fcstat_wwpn(&wwpn, statp, sizeof(perfstat_fcstat_t), tot);
    }
    else
    {
        ret = perfstat_fcstat(&first, statp, sizeof(perfstat_fcstat_t), tot);
    }
}
/* print statistics for the Fiber channel */
for (i = 0; i < ret; i++) {
    printf(" FC Adapter name: %s \n", statp[i].name);
    printf(" ===== Traffic Statistics =====\n");
    printf(" Number of Input Requests: %lld \n",
        statp[i].InputRequests - statq[i].InputRequests);
    printf(" Number of Output Requests: %lld \n",
        statp[i].OutputRequests - statq[i].OutputRequests);
    printf(" Number of Input Bytes : %lld \n",
        statp[i].InputBytes - statq[i].InputBytes);
    printf(" Number of Output Bytes : %lld \n",
        statp[i].OutputBytes - statq[i].OutputBytes);
    printf(" ===== Transfer Statistics =====\n");
    printf(" Adapter's Effective Maximum Transfer Value : %lld \n",
        statp[i].EffMaxTransfer - statq[i].EffMaxTransfer);
}

```

```

printf(" ===== Driver Statistics =====\n");
printf(" Count of DMA failures: %lld \n",
statp[i].NoDMAResourceCnt - statq[i].NoDMAResourceCnt);
printf(" No command resource available :%lld \n",
statp[i].NoCmdResourceCnt - statq[i].NoCmdResourceCnt);
printf(" Link Indicator : %d \n", statp[i].AttentionType);
printf(" ===== CHBA Statistics =====\n");
printf(" Seconds since last reset of the statistics on the adapter: %lld \n",
statp[i].SecondsSinceLastReset - statq[i].SecondsSinceLastReset);
printf(" Number of frames transmitted: %lld \n",
statp[i].TxFrames - statq[i].TxFrames);
printf(" Fiber Channel Kbytes transmitted : %lld \n",
statp[i].TxWords - statq[i].TxWords);
printf(" Number of Frames Received.: %lld \n",
statp[i].RxFrames - statq[i].RxFrames);
printf(" Fiber Channel Kbytes Received : %lld \n",
statp[i].RxWords - statq[i].RxWords);
printf(" Loop Initialization Protocol (LIP) Count: %lld \n",
statp[i].LIPCount - statq[i].LIPCount);
printf(" NOS(Not_Operational) Count : %lld \n",
statp[i].NOSCount - statq[i].NOSCount);
printf(" Number of frames received with the CRC Error : %lld \n",
statp[i].ErrorFrames - statq[i].ErrorFrames);
printf(" Number of lost frames : %lld \n",
statp[i].DumpedFrames - statq[i].DumpedFrames);
printf(" Count of Link failures: %lld \n",
statp[i].LinkFailureCount - statq[i].LinkFailureCount);
printf(" Count of loss of sync : %lld \n",
statp[i].LossofSyncCount - statq[i].LossofSyncCount);
printf(" Count of loss of Signal:%lld \n",
statp[i].LossofSignal - statq[i].LossofSignal);
printf(" Number of times a primitive sequence was in error :%lld \n",
statp[i].PrimitiveSeqProtocolErrCount - statq[i].PrimitiveSeqProtocolErrCount);
printf(" Count of Invalid Transmission words received : %lld \n",
statp[i].InvalidTxWordCount - statq[i].InvalidTxWordCount);
printf(" Count of CRC Errors in a Received Frame :%lld \n",
statp[i].InvalidCRCCount - statq[i].InvalidCRCCount);
printf(" SCSI Id of the adapter : %lld \n",
statp[i].PortFcId);
printf(" Speed of Adapter in GBIT : %lld \n",
statp[i].PortSpeed);
printf(" Connection Type: %s \n",
statp[i].PortType);
printf(" worldwide port name : %lld \n",
statp[i].PortWWN);
printf(" Supported Port Speed in GBIT: %lld \n",
statp[i].PortSupportedSpeed);

printf(" ===== End =====\n");

}
memcpy(statq, statp, (tot * sizeof(perfstat_fcstat_t)));
count--;
}
}

/*
 *Name: main
 *
 */

int main(int argc, char *argv[])
{
    int i=0, rc=0;
    /* get the interval and count values */

    /* Process the arguments */

```

```

while ((i = getopt(argc, argv, "i:c:n:a:w")) != EOF)
{
    switch(i)
    {
        case 'i':          /* Interval */
            interval = atoi(optarg);
            if( interval <= 0 )
                interval = INTERVAL_DEFAULT;
            break;
        case 'c':          /* Number of iterations */
            count = atoi(optarg);
            if( count <= 0 )
                count = COUNT_DEFAULT;
            break;
        case 'n':          /* Node name in a cluster environment */
            strncpy(nodename, optarg, MAXHOSTNAMELEN);
            nodename[MAXHOSTNAMELEN-1] = '\0';
            collect_remote_node_stats = 1;
            break;
        case 'a':          /* Fiber Channel Adapter Name */
            strncpy(fcadapter_name, optarg, MAXHOSTNAMELEN);
            fcadapter_name[MAXHOSTNAMELEN-1] = '\0';
            fc_flag = 1;
            break;
        case 'w':          /* Worldwide port name(WWPN) */
            wwpn_id = (unsigned long long) (atoll(optarg));
            wwpn_flag = 1;
            break;
        default:
            /* Invalid arguments. Print the usage and terminate */
            showusage(argv[0]);
    }
}

if((fc_flag == 1))
{
    if(fcadapter_name == NULL )
    {
        fprintf(stderr, "FC adapter Name should not be NULL");
        exit(-1);
    }
}

if(wwpn_flag == 1)
{
    if(wwpn_id < 0 )
    {
        fprintf(stderr, "WWPN id should not be negavite ");
        exit(-1);
    }
}

if(collect_remote_node_stats)
{
    /* perfstat_config needs to be called to enable cluster statistics collection */
    rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
    }
}
exit(-1);
}

do_initialization();
display_metrics();

if(collect_remote_node_stats)
{
    /* Now disable cluster statistics by calling perfstat_config */

```

```

    perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}
free(statp);
free(statq);
return 0;
}

```

## perfstat\_hfistat\_window Interface

The **perfstat\_hfistat\_window** interface returns a set of structures of type **perfstat\_hfistat\_window\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_hfistat\_window\_t** structure include:

Item	Descriptor
<b>pkts_sent</b>	The number of packets sent (56 bit counter).
<b>pkts_dropped_sending</b>	The number of packets that were dropped from sending (40 bit counter).
<b>pkts_received</b>	The number of the packets that were received (56 bit counter).

## perfstat\_logicalvolume Interface

The **perfstat\_logicalvolume** interface returns a set of structures of type **perfstat\_logicalvolume\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_logicalvolume\_t** structure include:

Item	Descriptor
<b>Ppsize</b>	Physical partition size (in MB)
<b>locnt</b>	Number of read and write requests
<b>Kbread</b>	Number of kilobytes read
<b>Kbwrites</b>	Number of kilobytes written

Several other paging-space-related metrics (such as name, type, and active) are also returned. For a complete list of other paging-space-related metrics, see the **perfstat\_logicalvolume\_t** section in the **libperfstat.h** header file in *Files Reference*.

**Note:** The **perfstat\_config (PERFSTAT\_ENABLE | PERFSTAT\_LV, NULL)** must be used to enable the logical volume statistical collection.

The following code shows an example of how the **perfstat\_logicalvolume** interface is used:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(){
int lv_count,i, rc;
perfstat_id_t first;
perfstat_logicalvolume_t *lv;

strcpy(first.name,NULL);

/* enable the logical volume statistical collection */
perfstat_config(PERFSTAT_ENABLE | PERFSTAT_LV,NULL);

/* get the number of logical volumes */
lv_count = perfstat_logicalvolume (NULL, NULL, sizeof(perfstat_logicalvolume_t), 0);

/* check the subroutine return code for any error */
if (lv_count == -1){
    perror("perfstat_logicalvolume");
    exit(-1);
}

/* Allocate enough memory to hold all the structures */
lv = (perfstat_logicalvolume_t *)calloc(lv_count, sizeof(perfstat_logicalvolume_t));

```

```

if (lv == NULL){
    perror(".malloc");
    exit(-1);
}

/* Call the API to get the data */
rc = perfstat_logicalvolume(&first, (perfstat_logicalvolume_t*)lv,
sizeof(perfstat_logicalvolume_t),lv_count);

/* check the return code for any error */
if (rc == -1){
    perror("perfstat_logical volume ");
    exit(-1);
}

for(i=0;i<lv_count;i++){
    printf("\n");
    printf("Logical volume name=%s\n",lv[i].name);
    printf("Volume group name=%s\n",lv[i].vgname);
    printf("Physical partition size in MB=%lld\n",lv[i].ppsize);
    printf("total number of logical paritions configured for this logical volume=%lld\n",lv[i].logical_partitions);
    printf("number of physical mirrors for each logical partition=%lu\n",lv[i].mirrors);
    printf("Number of read and write requests=%lu\n",lv[i].iocnt);
    printf("Number of Kilobytes read=%lld\n",lv[i].kbreads);
    printf("Number of Kilobytes written=%lld\n",lv[i].kbwrits);
}

/* disable logical volume statistical collection */
perfstat_config(PERFSTAT_DISABLE | PERFSTAT_LV , NULL);
}

```

The program displays an output that is similar to the following example output:

```

Logical volume name=hd5
Volume group name=rootvg
Physical partition size in MB=32
total number of logical paritions configured for this logical volume=1
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=hd6
Volume group name=rootvg
Physical partition size in MB=32
total number of logical paritions configured for this logical volume=16
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=hd8
Volume group name=rootvg
Physical partition size in MB=32
total number of logical paritions configured for this logical volume=1
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=hd4
Volume group name=rootvg
Physical partition size in MB=32
total number of logical paritions configured for this logical volume=2
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=hd2
Volume group name=rootvg
Physical partition size in MB=32

```

total number of logical partitions configured for this logical volume=31  
number of physical mirrors for each logical partition=1  
Number of read and write requests=0  
Number of Kilobytes read=0  
Number of Kilobytes written=0

Logical volume name=hd9var  
Volume group name=rootvg  
Physical partition size in MB=32  
total number of logical partitions configured for this logical volume=1  
number of physical mirrors for each logical partition=1  
Number of read and write requests=0  
Number of Kilobytes read=0  
Number of Kilobytes written=0

Logical volume name=hd10opt  
Volume group name=rootvg  
Physical partition size in MB=32  
total number of logical partitions configured for this logical volume=1  
number of physical mirrors for each logical partition=1  
Number of read and write requests=0  
Number of Kilobytes read=0  
Number of Kilobytes written=0

Logical volume name=hd3  
Volume group name=rootvg  
Physical partition size in MB=32  
total number of logical partitions configured for this logical volume=4  
number of physical mirrors for each logical partition=1  
Number of read and write requests=0  
Number of Kilobytes read=0  
Number of Kilobytes written=0

Logical volume name=hd1  
Volume group name=rootvg  
Physical partition size in MB=32  
total number of logical partitions configured for this logical volume=74  
number of physical mirrors for each logical partition=1  
Number of read and write requests=0  
Number of Kilobytes read=0  
Number of Kilobytes written=0

Logical volume name=hd11admin  
Volume group name=rootvg  
Physical partition size in MB=32  
total number of logical partitions configured for this logical volume=4  
number of physical mirrors for each logical partition=1  
Number of read and write requests=0  
Number of Kilobytes read=0  
Number of Kilobytes written=0

Logical volume name=lg\_dump1v  
Volume group name=rootvg  
Physical partition size in MB=32  
total number of logical partitions configured for this logical volume=32  
number of physical mirrors for each logical partition=1  
Number of read and write requests=0  
Number of Kilobytes read=0  
Number of Kilobytes written=0

Logical volume name=livedump  
Volume group name=rootvg  
Physical partition size in MB=32  
total number of logical partitions configured for this logical volume=8  
number of physical mirrors for each logical partition=1  
Number of read and write requests=0  
Number of Kilobytes read=0

```

Number of Kilobytes written=0

Logical volume name=fslv00
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=3
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=fslv01
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=1
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

```

The preceding program emulates **vmstat** behavior and also shows how **perfstat\_logicalvolume** is used.

### perfstat\_memory\_page Interface

The **perfstat\_memory\_page** interface returns a set of structures of type **perfstat\_memory\_page\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_memory\_page\_t** structure include:

Item	Descriptor
<b>psize</b>	Page size in bytes
<b>real_total</b>	Amount of real memory (in units of psize)
<b>real_freesize</b>	Amount of free real memory (in units of psize)
<b>real_pinned</b>	Amount of pinned memory (in units of psize multiplied by 4)
<b>Pgins</b>	Number of pages paged in
<b>Pgouts</b>	Number of pages paged out

Several other disk-adapter related metrics (such as the number of blocks read from and written to the adapter) are also returned. For a complete list of other disk-adapter-related metrics, see the **perfstat\_memory\_page\_t** section in the **libperfstat.h** header file.

The following program shows an example of how the **perfstat\_memory\_page** interface is used:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main (){
    int total_psizes, avail_psizes;
    perfstat_memory_page_t *psize_mem_values;
    perfstat_psize_t pagesize;
    int i;
    /*get the total number of page sizes */

    total_psizes = perfstat_memory_page(NULL, NULL, sizeof(perfstat_memory_page_t), 0);

    /*check for any error*/
    if(total_psizes < 1)
    {
        perror("do_initialization:"
            " Unable to retrieve the number of available pagesizes.");
        exit(-1);
    }

    /* allocate sufficient memory to store the structures */
    psize_mem_values = (perfstat_memory_page_t *)malloc(sizeof(perfstat_memory_page_t) * total_psizes);

```

```

/*check for bad malloc */
if(psize_mem_values == NULL)
{
    perror("do_initialization: Unable to allocate sufficient"
          " memory for psize_mem_values buffer.");
    exit(-1);
}

pagesize.psize = FIRST_PSIZE;
avail_psizes = perfstat_memory_page(&pagesize, psize_mem_values, sizeof(perfstat_memory_page_t),
total_psizes);

/*check the return value for any error */

if(avail_psizes < 1)
{
    perror("display_psize_memory_stats: Unable to retrieve memory "
          "statistics for the available page sizes.");
    exit(-1);
}

for(i=0;i<avail_psizes;i++){
    printf("Page size in bytes=%llu\n",psize_mem_values[i].psize);
    printf("Number of real memory frames of this page size=%lld\n",psize_mem_values[i].real_total);
    printf("Number of pages on free list=%lld\n",psize_mem_values[i].real_free);
    printf("Number of pages pinned=%lld\n",psize_mem_values[i].real_pinned);
    printf("Number of pages in use=%lld\n",psize_mem_values[i].real_inuse);
    printf("Number of page faults =%lld\n",psize_mem_values[i].pgexct);
    printf("Number of pages paged in=%lld\n",psize_mem_values[i].pgins);
    printf("Number of pages paged out=%lld\n",psize_mem_values[i].pgouts);
    printf("\n");
}
return 0;
}

```

The program displays an output that is similar to the following example output:

```

Page size in bytes=4096
Number of real memory frames of this page size=572640
Number of pages on free list=364101
Number of pages pinned=171770
Number of pages in use=208539
Number of page faults =1901334
Number of pages paged in=40569
Number of pages paged out=10381

```

```

Page size in bytes=65536
Number of real memory frames of this page size=29746
Number of pages on free list=24741
Number of pages pinned=4333
Number of pages in use=5005
Number of page faults =28495
Number of pages paged in=0
Number of pages paged out=0

```

## perfstat\_netinterface Interface

The `perfstat_netinterface` interface returns a set of structures of type `perfstat_netinterface_t`, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_netinterface_t` structure include:

<b>name</b>	Interface name (from ODM)
<b>description</b>	Interface description (from ODM)
<b>ipackets</b>	Total number of input packets received on this network interface
<b>opackets</b>	Total number of output packets sent on this network interface
<b>ierror</b>	Total number of input errors on this network interface
<b>oerror</b>	Total number of output errors on this network interface

Several other network-interface related metrics (such as number of bytes sent and received, type, and bitrate) are also returned. For a complete list of other network-interfaced related metrics, see the **perfstat\_netinterface\_t** section in the **libperfstat.h** header file in *Files Reference*.

The following code shows an example of how **perfstat\_netinterface** is used:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
#include <net/if_types.h>

char *
decode(uchar type) {
    switch(type) {
        case IFT_LOOP:
            return("loopback");

        case IFT_IS088025:
            return("token-ring");

        case IFT_ETHER:
            return("ethernet");
        }
    return("other");
}

int main(int argc, char* argv[]) {
    int i, ret, tot;
    perfstat_netinterface_t *statp;
    perfstat_id_t first;

    /* check how many perfstat_netinterface_t structures are available */
    tot = perfstat_netinterface(NULL, NULL, sizeof(perfstat_netinterface_t), 0);

    /* check for error */
    if (tot < 0)
    {

        /* check for error */
        if (tot == 0)
        {
            printf("No network interfaces found\n");
            exit(-1);
        }

        perror("perfstat_netinterface");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    statp = calloc(tot, sizeof(perfstat_netinterface_t));

    /* set name to first interface */
    strcpy(first.name, FIRST_NETINTERFACE);
```

```

/* ask to get all the structures available in one call */
/* return code is number of structures returned */
ret = perfstat_netinterface(&first, statp, sizeof(perfstat_netinterface_t), tot);

/* check for error */
if (ret <= 0)
{

perror("perfstat_netinterface");
exit(-1);
}

/* print statistics for each of the interfaces */
for (i = 0; i < ret; i++) {
printf("\nStatistics for interface : %s\n", statp[i].name);
printf("-----\n");
printf("type : %s\n", decode(statp[i].type));
printf("\ninput statistics:\n");
printf("number of packets : %llu\n", statp[i].ipackets);
printf("number of errors : %llu\n", statp[i].ierrors);
printf("number of bytes : %llu\n", statp[i].ibytes);
printf("\noutput statistics:\n");
printf("number of packets : %llu\n", statp[i].opackets);
printf("number of bytes : %llu\n", statp[i].obytes);
printf("number of errors : %llu\n", statp[i].oerrors);
}
}

```

The preceding program produces the following output:

```

Statistics for interface : tr0
-----
type : token-ring

input statistics:
number of packets : 306352
number of errors : 0
number of bytes : 24831776

output statistics:
number of packets : 62669
number of bytes : 11497679
number of errors : 0

Statistics for interface : lo0
-----
type : loopback

input statistics:
number of packets : 336
number of errors : 0
number of bytes : 20912

output statistics:
number of packets : 336
number of bytes : 20912
number of errors : 0

```

The preceding program emulates **diskadapterstat** behavior and also shows how **perfstat\_netinterface** is used.

## perfstat\_netbuffer Interface

The **perfstat\_netbuffer** interface returns a set of structures of type **perfstat\_netbuffer\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_netbuffer\_t** structure include:

Item	Descriptores a
size	Size of the allocation (string expressing size in bytes)
inuse	Current allocation of this size
failed	Failed allocation of this size
free	Free list for this size

Several other allocation-related metrics (such as high-water mark and freed) are also returned. For a complete list of other allocation-related metrics, see the `perfstat_netbuffer_t` section in the `libperfstat.h` header file.

The following code shows an example of how the `perfstat_netbuffer` interface is used: The preceding program produces the following output:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(int argc, char* argv[]) {
    int i, ret, tot;
    perfstat_netbuffer_t *statp;
    perfstat_id_t first;

    /* check how many perfstat_netbuffer_t structures are available */
    tot = perfstat_netbuffer(NULL, NULL, sizeof(perfstat_netbuffer_t), 0);

    /* check for error */
    if (tot <= 0)
    {
        perror("perfstat_netbuffer");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    statp = calloc(tot, sizeof(perfstat_netbuffer_t));
    if(statp==NULL){
        printf("No sufficient memory\n");
        exit(-1);
    }

    /* set name to first interface */
    strcpy(first.name, FIRST_NETBUFFER);

    /* ask to get all the structures available in one call */
    /* return code is number of structures returned */
    ret = perfstat_netbuffer(&first, statp,
        sizeof(perfstat_netbuffer_t), tot);

    /* check for error */
    if (ret <= 0)
    {
        perror("perfstat_netbuffer");
        exit(-1);
    }

    /* print info in netstat -m format */
    printf("%-12s %10s %9s %6s %9s %7s %7s %7s\n",
        "By size", "inuse", "calls", "failed",
        "delayed", "free", "hiwat", "freed");
    for (i = 0; i < ret; i++) {
        printf("%-12s %10llu %9llu %6llu %9llu %7llu %7llu %7llu\n",
            statp[i].name,
            statp[i].inuse,
            statp[i].calls,
            statp[i].delayed,
            statp[i].free,
            statp[i].failed,
```

```

        statp[i].highwatermark,
        statp[i].freed);
    }
}

```

The program displays an output that is similar to the following example output:

By size	inuse	calls	failed	delayed	free	hiwat	freed
64	598	12310	14	682	0	10480	0
128	577	8457	16	287	0	7860	0
256	1476	287157	88	716	0	15720	0
512	2016	1993915	242	808	0	32750	0
1024	218	8417	81	158	0	7860	0
2048	563	2077	277	307	0	19650	0
4096	39	127	15	143	0	1310	0
8192	4	16	4	0	0	327	0
16384	128	257	19	4	0	163	0
32768	25	55	9	4	0	81	0
65536	59	121	35	5	0	81	0
131072	3	7	0	217	0	204	0

## perfstat\_netadapter Interface

The `perfstat_netadpater` interface returns a set of structures of type `perfstat_netadapter_t`, which is defined in the `libperfstat.h` file.

**Note:** The `perfstat_netadpater` interface returns only the network Ethernet adapter statistics similar to the `entstat` command.

The following program shows an example of how the `perfstat_netadapter` interface is used:

```

/* The sample program displays the metrics *
 * related to every Individual *
 * network adapter in the LPAR*/
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
#include <net/if_types.h>
/* define default interval and count values */
#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1

/* Check value returned by malloc for NULL */

#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
    perror ("malloc");\
    exit(2);\
}

int count = COUNT_DEFAULT, interval = INTERVAL_DEFAULT, tot;
int returncode;

/* store the data structures */

static perfstat_netadapter_t *statp,*statq;
/* support for remote node statistics collection in a cluster environment */
perfstat_id_node_t nodeid;
static char nodename[MAXHOSTNAMELEN] = "";
static int collect_remote_node_stats = 0;

/*
 * NAME: showusage
 * to display the usage
 */

void showusage(char *cmd)
{
    fprintf (stderr, "usage: %s [-i <interval in seconds> ] [-c <number of iterations> ] [-n <node name in the cluster> ]\n", cmd);
    exit(1);
};

/*
 * NAME: do_initialization
 * This function initializes the data structures.
 * It also collects the initial set of values.
 * RETURNS:

```

```

* On successful completion:
* - returns 0.
* In case of error
* - exits with code 1.
*/

int do_initialization(void)
{
    /* check how many perfstat_netadapter_t structures are available */
    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        tot = perfstat_netadapter_node(&nodeid, NULL, sizeof(perfstat_netadapter_t), 0);
    }
    else
    {
        tot = perfstat_netadapter(NULL, NULL, sizeof(perfstat_netadapter_t), 0);
    }
    if (tot == 0)
    {
        printf("There is no net adapter\n");
        exit(0);
    }
    if (tot < 0)
    {
        perror("perfstat_netadapter: ");
        exit(1);
    }
    /* allocate enough memory for all the structures */

    statp = (perfstat_netadapter_t *)malloc(tot * sizeof(perfstat_netadapter_t));
    CHECK_FOR_MALLOC_NULL(statp);

    statq = (perfstat_netadapter_t *)malloc(tot * sizeof(perfstat_netadapter_t));
    CHECK_FOR_MALLOC_NULL(statq);

    return(0);
}

/*
*Name: display_metrics
*   collect the metrics and display them
*/
void display_metrics()
{
    perfstat_id_t first;
    int ret, i;

    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;

        strcpy(nodeid.name , FIRST_NETINTERFACE);
        ret = perfstat_netadapter_node(&nodeid, statq, sizeof(perfstat_netadapter_t), tot);
    }
    else {
        strcpy(first.name , FIRST_NETINTERFACE);
        ret = perfstat_netadapter( &first, statq, sizeof(perfstat_netadapter_t), tot);
    }
    if (ret < 0){
        free(statp);
        free(statq);
        perror("perfstat_netadapter: ");
        exit(1);
    }
    while (count)
    {
        sleep (interval);
        if(collect_remote_node_stats)
        {
            ret = perfstat_netadapter_node(&nodeid, statp, sizeof(perfstat_netadapter_t), tot);
        }
        else {
            ret = perfstat_netadapter(&first, statp, sizeof(perfstat_netadapter_t), tot);
        }
        /* print statistics for each of the interfaces */
        for (i = 0; i < ret; i++)
        {
            printf(" Adapter name: %s \n", statp[i].name);
            printf(" ===== Transmit Statistics===== \n");
            printf(" Transmit Packets: %lld \n",
statp[i].tx_packets - statq[i].tx_packets);
            printf(" Transmit Bytes: %lld \n",
statp[i].tx_bytes - statq[i].tx_bytes);
            printf(" Transfer Interrupts : %lld \n",
statp[i].tx_interrupts - statq[i].tx_interrupts);
            printf(" Transmit Errors : %lld \n",
statp[i].tx_errors - statq[i].tx_errors);
            printf(" Packets Dropped at the time of Data Transmission : %lld \n",

```

```

    statp[i].tx_packets_dropped - statq[i].tx_packets_dropped);
    printf(" Transmit Queue Size: %lld \n",
    statp[i].tx_queue_size - statq[i].tx_queue_size);
    printf(" Transmit Queue Length :%lld \n",
    statp[i].tx_queue_len - statq[i].tx_queue_len);
    printf(" Transmit Queue Overflow : %lld \n",
    statp[i].tx_queue_overflow - statq[i].tx_queue_overflow);
    printf(" Broadcast Packets Transmitted: %lld \n",
    statp[i].tx_broadcast_packets - statq[i].tx_broadcast_packets);
    printf(" Multicast packets Transmitted: %lld \n",
    statp[i].tx_multicast_packets - statq[i].tx_multicast_packets);
    printf(" Lost Carrier Sense signal count : %lld \n",
    statp[i].tx_carrier_sense - statq[i].tx_carrier_sense);
    printf(" Count of DMA Under-runs for Transmission: %lld \n",
    statp[i].tx_DMA_underrun - statq[i].tx_DMA_underrun);
    printf(" Number of unsuccessful transmissions : %lld \n",
    statp[i].tx_lost_CTS_errors - statq[i].tx_lost_CTS_errors);
    printf(" Maximum Collision Errors at Transmission: %lld \n",
    statp[i].tx_max_collision_errors - statq[i].tx_max_collision_errors);
    printf(" Late Collision Errors at Transmission : %lld \n",
    statp[i].tx_late_collision_errors - statq[i].tx_late_collision_errors);
    printf(" Number of packets deferred for Transmission : %lld \n",
    statp[i].tx_deferred - statq[i].tx_deferred);
    printf(" Time Out Errors for Transmission : %lld \n",
    statp[i].tx_timeout_errors - statq[i].tx_timeout_errors);
    printf(" Count of Single Collision error at Transmission: %lld \n",
    statp[i].tx_single_collision_count - statq[i].tx_single_collision_count);
    printf(" Count of Multiple Collision error at Transmission : %lld \n",
    statp[i].tx_multiple_collision_count - statq[i].tx_multiple_collision_count);
    printf(" ===== Receive Statistics =====\n");
    printf(" Receive Packets :%lld \n",
    statp[i].rx_packets - statq[i].rx_packets);
    printf(" Receive Bytes :%lld \n",
    statp[i].rx_bytes - statq[i].rx_bytes);
    printf(" Receive Interrupts : %lld \n",
    statp[i].rx_interrupts - statq[i].rx_interrupts);
    printf(" Input errors on interface :%lld \n",
    statp[i].rx_errors - statq[i].rx_errors);
    printf(" Number of Packets Dropped : %lld \n",
    statp[i].rx_packets_dropped - statq[i].rx_packets_dropped);
    printf(" Count of Bad Packets Received : %lld \n",
    statp[i].rx_bad_packets - statq[i].rx_bad_packets);
    printf(" Number of MultiCast Packets Received : %lld \n",
    statp[i].rx_multicast_packets - statq[i].rx_multicast_packets);
    printf(" Number of Broadcast Packets Received : %lld \n",
    statp[i].rx_broadcast_packets - statq[i].rx_broadcast_packets);
    printf(" Count of Packets Received with CRC errors: %lld \n",
    statp[i].rx_CRC_errors - statq[i].rx_CRC_errors);
    printf(" DMA over-runs : %lld \n",
    statp[i].rx_DMA_ overrun - statq[i].rx_DMA_ overrun);
    printf(" Alignment Errors : %lld \n",
    statp[i].rx_alignment_errors - statq[i].rx_alignment_errors);
    printf(" No Resource Errors : %lld \n",
    statp[i].rx_noresource_errors - statq[i].rx_noresource_errors);
    printf(" Collision Errors: %lld \n",
    statp[i].rx_collision_errors - statq[i].rx_collision_errors);
    printf(" Number of Short Packets Received: %lld \n",
    statp[i].rx_packet_tooshort_errors - statq[i].rx_packet_tooshort_errors);
    printf(" Number of Too Long Packets Received : %lld \n",
    statp[i].rx_packet_toolong_errors - statq[i].rx_packet_toolong_errors);
    printf(" Number of Received Packets discarded by Adapter: %lld \n",
    statp[i].rx_packets_discardedbyadapter - statq[i].rx_packets_discardedbyadapter);
    printf(" =====\n");
}
memcpy(statq, statp, (tot * sizeof(perfstat_netadapter_t)));
count--;
}
}
/*
*Name: main
*
*/
int main(int argc, char *argv[])
{
    int i, rc;
    /* get the interval and count values */

    /* Process the arguments */
    while ((i = getopt(argc, argv, "i:c:n:")) != EOF)
    {
        switch(i)
        {
            case 'i': /* Interval */
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;

```

```

    case 'c':          /* Number of iterations */
        count = atoi(optarg);
        if( count <= 0 )
            count = COUNT_DEFAULT;
        break;
    case 'n':          /* Node name in a cluster environment */
        strncpy(nodename, optarg, MAXHOSTNAMELEN);
        nodename[MAXHOSTNAMELEN-1] = '\0';
        collect_remote_node_stats = 1;
        break;
    default:
        /* Invalid arguments. Print the usage and terminate */
        showusage(argv[0]);
}
}

if(collect_remote_node_stats)
{ /* perfstat_config needs to be called to enable cluster statistics collection */
    rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
        exit(-1);
    }
}

do_initialization();
display_metrics();

if(collect_remote_node_stats)
{ /* Now disable cluster statistics by calling perfstat_config */
    perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}
free(statp);
free(statq);
return 0;
}

```

The program produces the output similar to the following:

```

Adapter name: ent0
===== Transmit Statistics=====
Transmit Packets: 0
Transmit Bytes: 0
Transfer Interrupts : 0
Transmit Errors : 0
Packets Dropped at the time of Data Transmission : 0
Transmit Queue Size: 0
Transmit Queue Length :0
Transmit Queue Overflow : 0
Broadcast Packets Transmitted: 0
Multicast packets Transmitted: 0
Lost Carrier Sense signal count : 0
Count of DMA Under-runs for Transmission: 0
Number of unsuccessful transmissions : 0
Maximum Collision Errors at Transmission: 0
Late Collision Errors at Transmission : 0
Number of packets deferred for Transmission : 0
Time Out Errors for Transmission : 0
Count of Single Collision error at Transmission: 0
Count of Multiple Collision error at Transmission : 0
===== Receive Statistics =====
Receive Packets :48
Receive Bytes :2962
Receive Interrupts : 44
Input errors on interface :0
Number of Packets Dropped : 0
Count of Bad Packets Received : 0
Number of MultiCast Packets Received : 0
Number of Broadcast Packets Received : 47
Count of Packets Received with CRC errors: 0
DMA over-runs : 0
Alignment Errors : 0
No Resource Errors : 0
Collision Errors: 0
Number of Short Packets Received: 0
Number of Too Long Packets Received : 0
Number of Received Packets discarded by Adapter: 0

```

## perfstat\_pagingspace Interface

The `perfstat_pagingspace` interface returns a set of structures of type `perfstat_pagingspace_t`, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_pagingspace_t` structure include:

Item	Descriptor
<code>mb_size</code>	Size of the paging space in MB
<code>lp_size</code>	Size of the paging space in logical partitions
<code>mb_used</code>	Portion of the paging space used in MB

Several other paging-space-related metrics (such as name, type, and active) are also returned. For a complete list of other paging-space-related metrics, see the `perfstat_pagingspace_t` section in the `libperfstat.h` header file in *Files Reference*.

The following code shows an example of how `perfstat_pagingspace` is used:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(int argc, char agrv[]) {
    int i, ret, tot;
    perfstat_id_t first;
    perfstat_pagingspace_t *pinfo;

    tot = perfstat_pagingspace(NULL, NULL, sizeof(perfstat_pagingspace_t), 0);
    /* check for error */
    if (tot <= 0)
    {
        perror("perfstat_pagingspace");
        exit(-1);
    }

    pinfo = calloc(tot, sizeof(perfstat_pagingspace_t));

    strcpy(first.name, FIRST_PAGINGSPEACE);

    ret = perfstat_pagingspace(&first, pinfo, sizeof(perfstat_pagingspace_t), tot);
    /* check for error */
    if (tot <= 0)
    {
        perror("perfstat_pagingspace");
        exit(-1);
    }
    for (i = 0; i < ret; i++) {
        printf("\nStatistics for paging space : %s\n", pinfo[i].name);
        printf("-----\n");
        printf("type           : %s\n",
            pinfo[i].type == LV_PAGING ? "logical volume" : "NFS file");
        if (pinfo[i].type == LV_PAGING) {
            printf("volume group : %s\n", pinfo[i].u.lv_paging.vgname);
        }
        else {
            printf("hostname : %s\n", pinfo[i].u.nfs_paging.hostname);
            printf("filename : %s\n", pinfo[i].u.nfs_paging.filename);
        }
        printf("size (in LP) : %llu\n", pinfo[i].lp_size);
        printf("size (in MB) : %llu\n", pinfo[i].mb_size);
        printf("used (in MB) : %llu\n", pinfo[i].mb_used);
    }
}
```

The preceding program produces the following output:

```
Statistics for paging space : hd6
-----
type           : logical volume
volume group : rootvg
size (in LP) : 64
size (in MB) : 512
used (in MB) : 4
```

## perfstat\_protocol Interface

The `perfstat_protocol` interface returns a set of structures of type `perfstat_protocol_t`, which consists of a set of unions to accommodate the different sets of fields needed for each protocol, as defined in the `libperfstat.h` file.

Selected fields from the `perfstat_protocol_t` structure include:

Item	Descriptor
<b>name</b>	Protocol name, which can be any of the following values: <code>ip</code> , <code>ip6</code> , <code>icmp</code> , <code>icmp6</code> , <code>udp</code> , <code>tcp</code> , <code>rpc</code> , <code>nfs</code> , <code>nfsv2</code> , or <code>nfsv3</code> .
<b>ipackets</b>	Number of input packets received using this protocol. This field exists only for protocols <code>ip</code> , <code>ipv6</code> , <code>udp</code> , and <code>tcp</code> .
<b>opackets</b>	Number of output packets sent using this protocol. This field exists only for protocols <code>ip</code> , <code>ipv6</code> , <code>udp</code> , and <code>tcp</code> .
<b>received</b>	Number of packets received using this protocol. This field exists only for protocols <code>icmp</code> and <code>icmpv6</code> .
<b>calls</b>	Number of calls made to this protocol. This field exists only for protocols <code>rpc</code> , <code>nfs</code> , <code>nfsv2</code> , and <code>nfsv3</code> .

Many other network-protocol related metrics are also returned. For a complete list of network-protocol related metrics, see the `perfstat_protocol_t` section in the `libperfstat.h` header file.

The following code shows an example of how the `perfstat_protocol` interface is used:

```
#include <stdio.h>
#include <string.h>
#include <libperfstat.h>

int main(int argc, char* argv[]) {
    int ret, tot, retrieved = 0;
    perfstat_protocol_t pinfo;
    perfstat_id_t protid;

    /* check how many perfstat_protocol_t structures are available */
    tot = perfstat_protocol(NULL, NULL, sizeof(perfstat_protocol_t), 0);

    /* check for error */
    if (tot <= 0)
    {
        perror("perfstat_protocol");
        exit(-1);
    }

    printf("number of protocol usage structures available : %d\n", tot);

    /* set name to first protocol */
    strcpy(protid.name, FIRST_PROTOCOL);

    /* retrieve first protocol usage information */
    ret = perfstat_protocol(&protid, &pinfo, sizeof(perfstat_protocol_t), 1);

    if (ret < 0)
    {
        perror("perfstat_protocol");
        exit(-1);
    }
    retrieved += ret;
    do {
        printf("\nStatistics for protocol : %s\n", pinfo.name);
        printf("-----\n");

        if (!strcmp(pinfo.name, "ip")) {
            printf("number of input packets : %llu\n", pinfo.u.ip.ipackets);
            printf("number of input errors : %llu\n", pinfo.u.ip.ierrors);
            printf("number of output packets : %llu\n", pinfo.u.ip.opackets);
            printf("number of output errors : %llu\n", pinfo.u.ip.oerrors);
        } else if (!strcmp(pinfo.name, "ipv6")) {
            printf("number of input packets : %llu\n", pinfo.u.ipv6.ipackets);
            printf("number of input errors : %llu\n", pinfo.u.ipv6.ierrors);
        }
    } while (ret > 0);
}
```

```

        printf("number of output packets : %llu\n", pinfo.u.ipv6.opackets);
        printf("number of output errors : %llu\n", pinfo.u.ipv6.oerrors);
    } else if (!strcmp(pinfo.name,"icmp")) {
        printf("number of packets received : %llu\n", pinfo.u.icmp.received);
        printf("number of packets sent : %llu\n", pinfo.u.icmp.sent);
        printf("number of errors : %llu\n", pinfo.u.icmp.errors);
    } else if (!strcmp(pinfo.name,"icmpv6")) {
        printf("number of packets received : %llu\n", pinfo.u.icmpv6.received);
        printf("number of packets sent : %llu\n", pinfo.u.icmpv6.sent);
        printf("number of errors : %llu\n", pinfo.u.icmpv6.errors);
    } else if (!strcmp(pinfo.name,"udp")) {
        printf("number of input packets : %llu\n", pinfo.u.udp.ipackets);
        printf("number of input errors : %llu\n", pinfo.u.udp.ierrors);
        printf("number of output packets : %llu\n", pinfo.u.udp.opackets);
    } else if (!strcmp(pinfo.name,"tcp")) {
        printf("number of input packets : %llu\n", pinfo.u.tcp.ipackets);
        printf("number of input errors : %llu\n", pinfo.u.tcp.ierrors);
        printf("number of output packets : %llu\n", pinfo.u.tcp.opackets);
    } else if (!strcmp(pinfo.name,"rpc")) {
        printf("client statistics:\n");
        printf("number of connection-oriented RPC requests : %llu\n",
            pinfo.u.rpc.client.stream.calls);
        printf("number of rejected connection-oriented RPCs : %llu\n",
            pinfo.u.rpc.client.stream.badcalls);
        printf("number of connectionless RPC requests : %llu\n",
            pinfo.u.rpc.client.dgram.calls);
        printf("number of rejected connectionless RPCs : %llu\n",
            pinfo.u.rpc.client.dgram.badcalls);
        printf("\nserver statistics:\n");
        printf("number of connection-oriented RPC requests : %llu\n",
            pinfo.u.rpc.server.stream.calls);
        printf("number of rejected connection-oriented RPCs : %llu\n",
            pinfo.u.rpc.server.stream.badcalls);
        printf("number of connectionless RPC requests : %llu\n",
            pinfo.u.rpc.server.dgram.calls);
        printf("number of rejected connectionless RPCs : %llu\n",
            pinfo.u.rpc.server.dgram.badcalls);
    } else if (!strcmp(pinfo.name,"nfs")) {
        printf("total number of NFS client requests : %llu\n",
            pinfo.u.nfs.client.calls);
        printf("total number of NFS client failed calls : %llu\n",
            pinfo.u.nfs.client.badcalls);
        printf("total number of NFS server requests : %llu\n",
            pinfo.u.nfs.server.calls);
        printf("total number of NFS server failed calls : %llu\n",
            pinfo.u.nfs.server.badcalls);
        printf("total number of NFS version 2 server calls : %llu\n",
            pinfo.u.nfs.server.public_v2);
        printf("total number of NFS version 3 server calls : %llu\n",
            pinfo.u.nfs.server.public_v3);
    } else if (!strcmp(pinfo.name,"nfsv2")) {
        printf("number of NFS V2 client requests : %llu\n",
            pinfo.u.nfsv2.client.calls);
        printf("number of NFS V2 server requests : %llu\n",
            pinfo.u.nfsv2.server.calls);
    } else if (!strcmp(pinfo.name,"nfsv3")) {
        printf("number of NFS V3 client requests : %llu\n",
            pinfo.u.nfsv3.client.calls);
        printf("number of NFS V3 server requests : %llu\n",
            pinfo.u.nfsv3.server.calls);
    }
}

/* make sure we stop after the last protocol */
if (ret = strcmp(protid.name, "")) {
    printf("\nnext protocol name : %s\n", protid.name);

    /* retrieve information for next protocol */

```

```

        ret = perfstat_protocol(&protid, &pinfo, sizeof(perfstat_protocol_t), 1);
    if (ret < 0)
        {
            perror("perfstat_protocol");
            exit(-1);
        }
        retrieved += ret;
    }
} while (ret == 1);

printf("\nnumber of protocol usage structures retrieved : %d\n", retrieved);
}

```

The program displays an output that is similar to the following example output:

```
number of protocol usage structures available : 11
```

```

Statistics for protocol : ip
-----
number of input packets : 155855
number of input errors  : 32911
number of output packets : 25635
number of output errors : 32909

next protocol name : ipv6

Statistics for protocol : ipv6
-----
number of input packets : 0
number of input errors  : 0
number of output packets : 0
number of output errors : 0

next protocol name : icmp

Statistics for protocol : icmp
-----
number of packets received : 2
number of packets sent    : 1
number of errors          : 1

next protocol name : icmpv6

Statistics for protocol : icmpv6
-----
number of packets received : 0
number of packets sent    : 0
number of errors          : 0

next protocol name : udp

Statistics for protocol : udp
-----
number of input packets : 106630
number of input errors  : 91625
number of output packets : 14435

next protocol name : tcp

Statistics for protocol : tcp
-----
number of input packets : 16313
number of input errors  : 0
number of output packets : 11196

next protocol name : rpc

```

```

Statistics for protocol : rpc
-----
client statistics:
number of connection-oriented RPC requests : 41
number of rejected connection-oriented RPCs : 0
number of connectionless RPC requests      : 24
number of rejected connectionless RPCs     : 0

server statistics:
number of connection-oriented RPC requests : 0
number of rejected connection-oriented RPCs : 0
number of connectionless RPC requests      : 0
number of rejected connectionless RPCs     : 0

next protocol name : nfs

```

```

Statistics for protocol : nfs
-----
total number of NFS client requests      : 41
total number of NFS client failed calls  : 0
total number of NFS server requests     : 0
total number of NFS server failed calls  : 0
total number of NFS version 2 server calls : 0
total number of NFS version 3 server calls : 0

next protocol name : nfsv2

```

```

Statistics for protocol : nfsv2
-----
number of NFS V2 client requests : 0
number of NFS V2 server requests : 0

next protocol name : nfsv3

```

```

Statistics for protocol : nfsv3
-----
number of NFS V3 client requests : 41
number of NFS V3 server requests : 0

next protocol name : nfsv4

```

```

Statistics for protocol : nfsv4
-----

number of protocol usage structures retrieved : 11

```

The preceding program emulates **protocolstat** behavior and also shows how **perfstat\_protocol** is used.

## perfstat\_process interfaces

The `perfstat_process` interface returns a set of structures of type `perfstat_process_t`, which is defined in the `libperfstat.h` file.

The field of the `perfstat_process_t` structure includes:

Item	Descriptor
<code>pid</code>	Process ID
<code>proc_name</code>	Name of the process
<code>proc_priority</code>	Priority of the process
<code>num_threads</code>	Thread count
<code>proc_uid</code>	Information of the owner
<code>proc_classid</code>	WLM class name
<code>proc_size</code>	Virtual size of the process
<code>proc_real_mem_data</code>	Real memory used for the data in kilobytes
<code>proc_real_mem_text</code>	Real memory used for text in kilobytes

Item	Descriptor
<code>proc_virt_mem_data</code>	Virtual memory used for data in kilobytes
<code>proc_virt_mem_text</code>	Virtual memory used for text in kilobytes
<code>shared_lib_data_size</code>	Data size from shared library in kilobytes
<code>heap_size</code>	Heap size in kilobytes
<code>real_inuse</code>	The real memory in kilobytes used by the process including the segments
<code>virt_inuse</code>	The virtual memory in kilobytes used by the process including the segments
<code>pinned</code>	Pinned memory in kilobytes used for the process that is inclusive of all segments
<code>pgsp_inuse</code>	Paging space in kilobytes uses inclusive of all segments
<code>filepages</code>	File pages in kilobytes used including shared pages
<code>real_inuse_map</code>	Real memory in kilobytes used for shared memory and memory mapped regions
<code>virt_inuse_map</code>	Virtual memory in kilobytes used for shared memory and memory mapped regions
<code>pinned_inuse_map</code>	Pinned memory in kilobytes for shared memory and memory mapped regions
<code>ucpu_time</code>	User mode CPU time in milliseconds
<code>scpu_time</code>	System mode CPU time in milliseconds
<code>last_timebase</code>	Timebase counter
<code>inBytes</code>	Bytes read from the disk
<code>outBytes</code>	Bytes written to the disk
<code>inOps</code>	In operations from disk
<code>outOps</code>	Out operations from disk

The following is an example of code for the `perfstat_process` API:

```
#include <libperfstat.h>

void main()
{
    perfstat_process_t *proct;
    perfstat_id_t id;
    int i,rc,proc_count;

    /* Get the count of processes */
    proc_count = perfstat_process(NULL, NULL,sizeof(perfstat_process_t),0);

    /* check for error */
    if(proc_count <= 0)
    {
        perror("Error in perfstat_process");
        exit(-1) ;
    }
    printf("Number of Processes = %d\n",proc_count);

    /* Allocate enough memory */
    proct = (perfstat_process_t *)calloc(proc_count,sizeof(perfstat_process_t));
    if(proct == NULL)
    {
        perror("Memory Allocation Error");
        exit(-1) ;
    }

    strcpy(id.name,"");
    rc = perfstat_process(&id,proct,sizeof(perfstat_process_t),proc_count);
    if(rc <= 0)
    {
        perror("Error in perfstat_process");
        exit(-1) ;
    }

    printf("\n =====Process Related metrics =====\n");
    for(i=0 ; i<proc_count ;i++)
    {
        printf("Process Name =                %s\n",proct[i].proc_name);
        printf("Process ID =                %lld\n",proct[i].pid);
        printf("Process priority =            %d\n",proct[i].proc_priority);
        printf("Thread Count =                %d\n",proct[i].num_threads);
        printf("\nCredential Information\n");
        printf("Owner Info =                  %lld\n",proct[i].proc_uid);
        printf("WLM Class Name =              %lld\n",proct[i].proc_classid);
        printf("\nMemory Related Statistics \n");
        printf("Process Virtual Size =        %lld KB \n",proct[i].proc_size);
        printf("Real Memory used for Data =    %lld KB \n",proct[i].proc_real_mem_data);
    }
}
```

```

printf("Real Memory used for Text =      %lld KB \n",proct[i].proc_real_mem_text);
printf("Virtual Memory used for Data =   %lld KB \n",proct[i].proc_virt_mem_data);
printf("Virtual Memory used for Text =   %lld KB \n",proct[i].proc_virt_mem_text);
printf("Data Size from Shared Library =  %lld KB \n",proct[i].shared_lib_data_size);
printf("Heap Size =                      %lld KB \n",proct[i].heap_size);
printf("Real memory in use by process =   %lld KB \n",proct[i].real_inuse);
printf("Virtual memory in use by process= %lld KB \n",proct[i].virt_inuse);
printf("Pinned Memory for this process =  %lld KB \n",proct[i].pinned);
printf("Paging Space in use =            %lld KB \n",proct[i].pgsp_inuse);
printf("File Pages used =                 %lld KB \n",proct[i].filepages);
printf("Real memory used for Shared Memory and Memory Mapped regions =%lld KB \n", proct[i].real_inuse_map);
printf("Virtual Memory used for Shared Memory and Memory Mapped regions =%lld KB \n", proct[i].virt_inuse_map);
printf("Pinned memory for Shared Memory and Memory Mapped regions =%lld KB \n", proct[i].pinned_inuse_map);
printf("\nCPU Related Statistics \n");
printf("User Mode CPU time =                %lf ms\n",proct[i].ucpu_time);
printf("System Mode CPU time =                %lf ms\n",proct[i].scpu_time);
printf("Timebase Counter =                   %lld\n", proct[i].last_timebase);
printf("\nDisk Related Statistics \n");
printf("Bytes Written to Disk =                %lld\n",proct[i].inBytes);
printf("Bytes Read from Disk =                %lld\n",proct[i].outBytes);
printf("In Operations from Disk =            %lld\n",proct[i].inOps);
printf("Out Operations from Disk =            %lld\n",proct[i].outOps);
printf("=====\n");
printf("\n\n");
}
}

```

The program produces the output similar to the following:

Number of Processes = 77

```

=====Process Related metrics =====
Process Name =                swapper
Process ID =                   0
Process priority =             16
Thread Count =                 0

Credential Information
Owner Info =                   0
WLM Class Name =              257

Memory Related Statistics
Process Virtual Size =         384 KB
Real Memory used for Data =    384 KB
Real Memory used for Text =    0 KB
Virtual Memory used for Data = 384 KB
Virtual Memory used for Text = 0 KB
Data Size from Shared Library = 0 KB
Heap Size =                   0 KB
Real memory in use by process = 384 KB
Virtual memory in use by process= 384 KB
Pinned Memory for this process = 320 KB
Paging Space in use =         0 KB
File Pages used =             0 KB
Real memory used for Shared Memory and Memory Mapped regions =0 KB
Virtual Memory used for Shared Memory and Memory Mapped regions =0 KB
Pinned memory for Shared Memory and Memory Mapped regions =0 KB

CPU Related Statistics
User Mode CPU time =           0.000000 ms
System Mode CPU time =        9262.345828 ms
Timebase Counter =            7290723200327369

Disk Related Statistics
Bytes Written to Disk =        0
Bytes Read from Disk =         32768
In Operations from Disk =      0
Out Operations from Disk =      8
=====

```

The program displays an output that is similar to the following example output:

Number of Processes = 77

```

=====Process Related metrics =====
Process Name =                swapper
Process ID =                   0

```

```

Process priority =          16
Thread Count =            0

Credential Information
Owner Info =              0
WLM Class Name =         257

Memory Related Statistics
Process Virtual Size =     384 KB
Real Memory used for Data = 384 KB
Real Memory used for Text = 0 KB
Virtual Memory used for Data = 384 KB
Virtual Memory used for Text = 0 KB
Data Size from Shared Library = 0 KB
Heap Size =               0 KB
Real memory in use by process = 384 KB
Virtual memory in use by process= 384 KB
Pinned Memory for this process = 320 KB
Paging Space in use =     0 KB
File Pages used =         0 KB
Real memory used for Shared Memory and Memory Mapped regions =0 KB
Virtual Memory used for Shared Memory and Memory Mapped regions =0 KB
Pinned memory for Shared Memory and Memory Mapped regions =0 KB

CPU Related Statistics
User Mode CPU time =      0.000000 ms
System Mode CPU time =   9262.345828 ms
Timebase Counter =       7290723200327369

Disk Related Statistics
Bytes Written to Disk =   0
Bytes Read from Disk =   32768
In Operations from Disk = 0
Out Operations from Disk = 8
=====

```

## perfstat\_process\_util interface

The `perfstat_process_util` interface returns a set of structures of type `perfstat_process_t`, which is defined in the `libperfstat.h` file.

The following is an example of code that uses the `perfstat_process_util` API:

```

#include <libperfstat.h>
#include <stdio.h>
#include <stdlib.h>
#define PERIOD 5

void main()
{
    perfstat_process_t *cur, *prev;
    perfstat_rawdata_t buf;
    perfstat_process_t *proc_util;
    perfstat_id_t id;
    int cur_proc_count,prev_proc_count;
    int i,rc;
    prev_proc_count = perfstat_process(NULL, NULL,sizeof(perfstat_process_t),0);
    if(prev_proc_count <= 0)
    {
        perror("Error in perfstat_process");
        exit(-1) ;
    }
    prev = (perfstat_process_t *)calloc(prev_proc_count,sizeof(perfstat_process_t));
    if(prev == NULL)
    {
        perror("Memory Allocation Error");
        exit(-1) ;
    }
}

```

```

strcpy(id.name,"");
rc = perfstat_process(&id,prev,sizeof(perfstat_process_t),prev_proc_count);
if(rc <= 0)
{
    perror("Error in perfstat_process");
    exit(-1) ;
}
sleep(PERIOD);

cur_proc_count = perfstat_process(NULL, NULL,sizeof(perfstat_process_t),0);
if(cur_proc_count <= 0)
{
    perror("Error in perfstat_process");
    exit(-1) ;
}
cur = (perfstat_process_t *)calloc(cur_proc_count,sizeof(perfstat_process_t));
proc_util = (perfstat_process_t *)calloc(cur_proc_count,sizeof(perfstat_process_t));
if(cur == NULL || proc_util == NULL)
{
    perror("Memory Allocation Error");
    exit(-1) ;
}
rc = perfstat_process(&id,cur,sizeof(perfstat_process_t),cur_proc_count);
if(rc < 0)
{
    perror("Error in perfstat_process");
    exit(-1) ;
}

bzero(&buf, sizeof(perfstat_rawdata_t));
buf.type = UTIL_PROCESS;
buf.curstat = cur;
buf.prevstat = prev;
buf.sizeof_data = sizeof(perfstat_process_t);
buf.cur_elems = cur_proc_count;
buf.prev_elems = prev_proc_count;

/* Calculate Process Utilization */
rc = perfstat_process_util(&buf,proc_util,sizeof(perfstat_process_t),cur_proc_count);
if(rc <= 0)
{
    perror("Error in perfstat_process_util");
    exit(-1);
}

printf("\n =====Process Related Utilization Metrics =====\n");
for(i=0 ; i<cur_proc_count ;i++)
{
    printf("Process ID =                %lld\n",proc_util[i].pid);
    printf("User Mode CPU time =           %lf \n",proc_util[i].ucpu_time);
    printf("System Mode CPU time =           %lf \n",proc_util[i].scpu_time);
    printf("Bytes Written to Disk =          %lld\n",proc_util[i].inBytes);
    printf("Bytes Read from Disk =           %lld\n",proc_util[i].outBytes);
    printf("In Operations from Disk =        %lld\n",proc_util[i].inOps);
    printf("Out Operations from Disk =        %lld\n",proc_util[i].outOps);
    printf("===== \n");
    printf("\n\n");
}
}
}

```

The program displays an output that is similar to the following example output:

```

=====Process Related Utilization Metrics =====
Process ID =                0
User Mode CPU time =         0.000000
System Mode CPU time =       0.013752

```

```

Bytes Written to Disk = 0
Bytes Read from Disk = 0
In Operations from Disk = 0
Out Operations from Disk = 0
=====

```

```

Process ID = 1
User Mode CPU time = 0.000000
System Mode CPU time = 0.000000
Bytes Written to Disk = 0
Bytes Read from Disk = 0
In Operations from Disk = 0
Out Operations from Disk = 0
=====

```

```

Process ID = 196614
User Mode CPU time = 0.000000
System Mode CPU time = 0.000000
Bytes Written to Disk = 0
Bytes Read from Disk = 0
In Operations from Disk = 0
Out Operations from Disk = 0
=====

```

```

Process ID = 262152
User Mode CPU time = 0.000000
System Mode CPU time = 0.000000
Bytes Written to Disk = 0
Bytes Read from Disk = 0
In Operations from Disk = 0
Out Operations from Disk = 0
=====

```

## perfstat\_processor\_pool\_util interface

The `perfstat_processor_pool_util` interface returns a set of structures of type `perfstat_processor_pool_util_t`, which is defined in the `libperfstat.h` file

Item	Descriptor
<code>max_capacity</code>	Maximum pool processor capacity of the partition.
<code>entitled_capacity</code>	Entitled pool processor capacity of the partition.
<code>phys_cpus_pool</code>	Physical processors that are available in the Shared processor Pool to which the partition is associated.
<code>idle_cores</code>	Physical processors that are available in the Shared processor Pool from the last interval.
<code>max_cores</code>	Maximum cores used by the Shared processor Pool for the last interval, which is associated with the partition.
<code>busy_cores</code>	Maximum busy (non-idle) cores that are accumulated for the last interval across all partitions in the Shared processor Pool, which is associated with the partition.
<code>sbusy_cores</code>	Normalized summation of busy (non-idle) cores that are accumulated across all partitions in the Shared processor Pool, which is associated with the partition. This option applies if the cores run at nominal or rated frequency.
<code>gpool_tot_cores</code>	Total number of cores across all physical processors that are allocated for shared processor use (across all pools).
<code>gpool_busy_cores</code>	Summation of the busy (non-idle) cores that are accumulated across all shared processor partitions (across all pools) for the last interval.
<code>gpool_sbusy_cores</code>	Normalized summation of the busy cores that are accumulated across all shared processor partitions (across all pools) for the last interval. This option applies if the cores run at nominal or rated frequency.

Item	Descriptor
<code>tb_last_delta</code>	Elapsed number of clock ticks.
<code>version</code>	Version number of the data structure.

The use of the `perfstat_processor_pool_util` API for the system-level utilization follows:

```
#include <libperfstat.h>
#include <sys/dr.h>
#include <sys/types.h>
#include <stdio.h>
#include <errno.h>
#include <unistd.h>
#define COUNT 2
#define INTERVAL 2
void main(int argc, char **argv)
{
    perfstat_rawdata_t data;
    perfstat_partition_total_t oldt,newt;
    perfstat_processor_pool_util_t util,*uti;
    static int once=0;
    int rc;
    u_longlong_t x=0;
    int iInter=0,iCount=0;

    int c;
    while( (c = getopt(argc,argv,"i:c:"))!= EOF ){
        switch(c) {
            case 'i':
                iInter=atoi(optarg);
                break;
            case 'c':
                iCount=atoi(optarg);
                break;
        }
    }

    if(iCount<=0 && iInter<=0)
    {
        iCount=COUNT;
        iInter=INTERVAL;
    }
    while(iCount-->0)
    {
        rc = perfstat_partition_total(NULL, &oldt, sizeof(perfstat_partition_total_t), 1);
        if (rc != 1)
        {
            perror("Error in perfstat_partition_total");
            exit(-1);
        }
        sleep(INTERVAL);
        rc = perfstat_partition_total(NULL, &newt, sizeof(perfstat_partition_total_t), 1);
        if (rc != 1)
        {
            perror("Error in perfstat_partition_total");
            exit(-1);
        }
        data.type = SHARED_POOL_UTIL;
        data.curstat = &newt; data.prevstat= &oldt;
        data.sizeof_data = sizeof(perfstat_partition_total_t);
        data.cur_elems = 1;
        data.prev_elems = 1;
        rc = perfstat_processor_pool_util(&data, &util,sizeof(perfstat_processor_pool_util_t),1);
        if(rc <= 0)
        {
            perror("Error in perfstat_processor_util");
            exit(-1);
        }
    }
}
```

```

}
  if(!once)
  {
    printf("Pool_id\tCapacity\tPhys_cpus_pool\tApp\t\tPool_utilization\t\tGlobal_pool\n");
    printf("\tMax|Entitled\t\t\t\t\tBusy|Scaled_busy\tMax|busy\n");
    printf("-----\n");
    once=1;
  }
  printf("%u ", util.ssp_id);
  printf("\t%llu ", util.max_capacity/100);
  /*Convert physical units to cores*/
  printf(" %llu ", util.entitled_capacity/100);
  /*Convert physical units to cores*/
  printf("\t\t\t%d ", util.phys_cpus_pool);
  printf("\t\t%5.2f ",util.idle_cores);
  printf("\t\t%5.2f ", util.busy_cores );
  printf("%5.2f ", util.sbusy_cores );
  printf("\t\t\t%5.2f ", util.gpool_tot_cores );
  printf("%5.2f \n", util.gpool_busy_cores );

}
}

```

## perfstat\_tape Interface

The **perfstat\_tape** interface returns a set of structures of type **perfstat\_tape\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_tape\_t** structure include:

Item	Descriptor
<b>size</b>	Size of the tape (in MB)
<b>free</b>	Free portion of the tape (in MB)
<b>bsize</b>	Tape block size (in bytes)
<b>paths_count</b>	Number of paths to the tape

Several other paging-space-related metrics (such as name, type, and active) are also returned. For a complete list of paging-space-related metrics, see the **perfstat\_pagingspace\_t** section in the **libperfstat.h** header file in *Files Reference*.

The following code shows an example of how the **perfstat\_tape** interface is used:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(){
  int ret, tot, i;
  perfstat_tape_t *statp;
  perfstat_id_t first;

  /* check how many perfstat_tape_t structures are available */
  tot = perfstat_tape(NULL, NULL, sizeof(perfstat_tape_t), 0);

  /* check for error */
  if (tot < 0)
  {
    perror("perfstat_tape");
    exit(-1);
  }
  if (tot == 0)
  {
    printf("No tape found in the system\n");
    exit(-1);
  }
}

```

```

    /* allocate enough memory for all the structures */
    statp = calloc(tot, sizeof(perfstat_tape_t));
    if(statp==NULL){
printf("No sufficient memory\n");
exit(-1);
    }

    /* set name to first interface */
    strcpy(first.name, FIRST_TAPE);

    /* ask to get all the structures available in one call */
    /* return code is number of structures returned */
    ret = perfstat_tape(&first, statp,
        sizeof(perfstat_tape_t), tot);

    /* check for error */
    if (ret <= 0)
    {
perror("perfstat_tape");
exit(-1);
    }

    for(i=0;i<ret;i++){

        printf("Name of the tape=%s\n",statp[i].name);
        printf("Tape description=%s\n",statp[i].description);
        printf("Size of the tape (in MB)=%lld\n",statp[i].size);
        printf("Free portion of the tape (in MB)=%lld\n",statp[i].free);
        printf("Tape block size (in bytes)=%lld\n",statp[i].bsize);
        printf("Number of transfers to/from tape=%lld\n",statp[i].xfers);
        printf("Number of read transfers to/from tape=%lld\n",statp[i].rxfers);
        printf("Number of blocks written to tape=%lld\n",statp[i].wblks);
        printf("Number of blocks read from tape=%lld\n",statp[i].rblks);
        printf("Amount of time tape is active=%lld\n",statp[i].time);
        printf("Tape adapter name =%s\n",statp[i].adapter);
        printf("Number of paths to this tape=%d\n",statp[i].paths_count);
        printf("\n");
    }
}

```

## perfstat\_thread interfaces

The perfstat\_thread interface returns a set of structures of type perfstat\_thread\_t, which is defined in the libperfstat.h file.

The field of the perfstat\_thread\_t structure includes the following:

*Table 2. perfstat\_thread\_t fields*

Item	Description
Pid	The process ID of the thread.
Tid	The kernel ID of the thread.
Cpuid	The processor on which the thread is bound.
ucpu_time	The user mode CPU time in milliseconds.
scpu_time	The system mode CPU time in milliseconds.

The following is an example of code for the perfstat\_thread\_t API:

```

#include <libperfstat.h>

void main()
{
    perfstat_thread_t *threadt;
    perfstat_id_t id;

```

```

int i,rc,thread_count;

/* Get the count of threads */
thread_count = perfstat_thread(NULL, NULL,sizeof(perfstat_thread_t),0);

/* check for error */
if(thread_count <= 0)
{
    perror("Error in perfstat_thread");
    exit(-1) ;
}
printf("Number of Threads = %d\n",thread_count);

/* Allocate enough memory */
threadt = (perfstat_thread_t *)calloc(thread_count,sizeof(perfstat_thread_t));
if(threadt == NULL)
{
    perror("Memory Allocation Error");
    exit(-1) ;
}

strcpy(id.name,"");
rc = perfstat_thread(&id,threadt,sizeof(perfstat_thread_t),thread_count);
if(rc <= 0)
{
    free(threadt);
    perror("Error in perfstat_thread");
    exit(-1) ;
}

printf("\n =====Thread Related metrics =====\n");
for(i=0 ; i<thread_count ;i++)
{
    printf("Process ID =                %u\n",threadt[i].pid);
    printf("Thread ID =                %u\n",threadt[i].tid);
    printf("\nCPU Related Statistics \n");
    printf("User Mode CPU time =                %f ms\n",threadt[i].ucpu_time);
    printf("System Mode CPU time =                %f ms\n",threadt[i].scpu_time);
    printf("Processor to which the thread is bound = %d\n", threadt[i].cpuid);
    printf("=====\n");
    printf("\n\n");
}
free(threadt);
}

```

The program displays an output that is similar to the following example output:

```

Process ID = 6553744
Thread ID  = 12345

CPU Related Statistics
User Mode CPU time = 714000.000000 ms
System Mode CPU time = 3000.000000 ms
Processor to which the thread is bound = 1

```

#### Related information:

libperfstat.h command

### perfstat\_thread\_util interface

The perfstat\_thread\_util interface returns a set of structures of type perfstat\_thread\_t, which is defined in the libperfstat.h file.

The following is an example of code for the perfstat\_thread\_util API:

```

#include <libperfstat.h>
#define PERIOD 5

```

```

void main()
{
    perfstat_thread_t *cur, *prev;
    perfstat_rawdata_t buf;
    perfstat_thread_t *thread_util;
    perfstat_id_t id;
    int cur_thread_count,prev_thread_count;
    int i,rc;
    prev_thread_count = perfstat_thread(NULL, NULL,sizeof(perfstat_thread_t),0);
    if(prev_thread_count <= 0)
    {
        perror("Error in perfstat_thread");
        exit(-1) ;
    }
    prev = (perfstat_thread_t *)calloc(prev_thread_count,sizeof(perfstat_thread_t));
    if(prev == NULL)
    {
        perror("Memory Allocation Error");
        exit(-1) ;
    }
    strcpy(id.name,"");
    prev_thread_count = perfstat_thread(&id,prev,sizeof(perfstat_thread_t),prev_thread_count);
    if(prev_thread_count <= 0)
    {
        free(prev);
        perror("Error in perfstat_thread");
        exit(-1) ;
    }
    sleep(PERIOD);

    cur_thread_count = perfstat_thread(NULL, NULL,sizeof(perfstat_thread_t),0);
    if(cur_thread_count <= 0)
    {
        free(prev);
        perror("Error in perfstat_thread");
        exit(-1) ;
    }
    cur = (perfstat_thread_t *)calloc(cur_thread_count,sizeof(perfstat_thread_t));
    thread_util = (perfstat_thread_t *)calloc(cur_thread_count,sizeof(perfstat_thread_t));
    if(cur == NULL || thread_util == NULL)
    {
        free(prev);
        perror("Memory Allocation Error");
        exit(-1) ;
    }
    cur_thread_count = perfstat_thread(&id,cur,sizeof(perfstat_thread_t),cur_thread_count);
    if(cur_thread_count <= 0)
    {
        free(prev);
        free(cur);
        free(thread_util);
        perror("Error in perfstat_thread");
        exit(-1) ;
    }

    bzero(&buf, sizeof(perfstat_rawdata_t));
    buf.type = UTIL_PROCESS;
    buf.curstat = cur;
    buf.prevstat = prev;
    buf.sizeof_data = sizeof(perfstat_thread_t);
    buf.cur_elems = cur_thread_count;
    buf.prev_elems = prev_thread_count;

    /* Calculate Thread Utilization. This returns the number of thread_util structures that are filled */
    rc = perfstat_thread_util(&buf,thread_util,sizeof(perfstat_thread_t),cur_thread_count);
    if(rc <= 0)

```

```

{
    free(prev);
    free(cur);
    free(thread_util);
    perror("Error in perfstat_thread_util");
    exit(-1);
}

printf("\n =====Thread Related Utilization Metrics =====\n");
for(i=0 ; i<rc ;i++)
{
    printf("Process ID =                %u\n",thread_util[i].pid);
    printf("Thread ID =                 %u\n",thread_util[i].tid);
    printf("User Mode CPU time =          %f \n",thread_util[i].ucpu_time);
    printf("System Mode CPU time =          %f \n",thread_util[i].scpu_time);
    printf(" Bound CPU Id           =         %d\n", thread_util[i].cpuid);
    printf("=====\n");
    printf("\n\n");
}
free(prev);
free(cur);
free(thread_util);
}

```

The program displays an output that is similar to the following example output:

```

Process ID = 6160532
Thread ID = 123456
User Mode CPU time = 21.824531
System Mode CPU time = 0.000000
Bound CPU Id = 1

```

#### Related information:

libperfstat.h command

### perfstat\_volumegroup Interface

The `perfstat_volumegroup` interface returns a set of structures of type `perfstat_logicalvolume_t`, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_logicalvolume_t` structure include:

Item	Descriptor
<code>Total_disks</code>	Total number of disks in the volume group
<code>Active_disks</code>	Total number of active disks in the volume group
<code>Ioct</code>	Number of read and write requests

The following code shows an example of how the `perfstat_logicalvolume` interface is used:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    int vg_count, rc,i;
    perfstat_id_t first;
    perfstat_volumegroup_t *vg;

    strcpy(first.name,NULL);

    /* to enable the volumegroup statistical collection */
    perfstat_config(PERFSTAT_ENABLE|PERFSTAT_LV,NULL);

    /* to get the number of volume groups */
    vg_count = perfstat_volumegroup (NULL, NULL, sizeof(perfstat_logicalvolume_t), 0);
    /* check the subroutine return code for any error */

```

```

if (vg_count <=0 ){
    perror("perfstat_volumegroup");
    exit(-1);
}

/* Allocate enough memory to hold all the structures */
vg = (perfstat_volumegroup_t *)calloc(vg_count, sizeof(perfstat_volumegroup_t));
if (vg == NULL){
    perror(".malloc");
    exit(-1);
}

/* Call the API to get the data */
rc = perfstat_volumegroup(&first,vg,sizeof(perfstat_volumegroup_t),vg_count);
/* check the return code for any error */
if (rc <= 0){
    perror("perfstat_volumegroup ");
    exit(-1);
}
for(i=0;i<vg_count;i++){
    printf("Volume group name=%s\n",vg[i].name);
    printf("Number of physical volumes in the volume group=%lld\n",vg[i].total_disks);
    printf("Number of active physical volumes in the volume group=%lld\n",vg[i].active_disks);
    printf("Number of logical volumes in the volume group=%lld\n",vg[i].total_logical_volumes);
    printf("Number of logical volumes opened in the volume group=%lld\n",vg[i].opened_logical_volumes);
    printf("Number of read and write requests=%lld\n",vg[i].iocnt);
    printf("Number of Kilobytes read=%lld\n",vg[i].kbreads);
    printf("Number of Kilobytes written=%lld\n",vg[i].kbwrites);
}

/* disable logical volume statistical collection */
perfstat_config(PERFSTAT_DISABLE | PERFSTAT_LV , NULL);

return 0;
}

```

The program displays an output that is similar to the following example output:

```

Volume group name=rootvg
Number of physical volumes in the volume group=1
Number of active physical volumes in the volume group=1
Number of logical volumes in the volume group=16
Number of logical volumes opened in the volume group=11
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

```

The preceding program emulates **vmstat** behavior and also shows how **perfstat\_volumegroup** is used.

## perfstat\_virtualdiskadapter Interface

The **perfstat\_virtualdiskadapter** interface returns a set of structures of type **perfstat\_diskadapter\_t**, which is defined in the **libperfstat.h** file.

The following program shows an example of how the **perfstat\_virtualdiskadapter** interface is used:

```

/* The sample program display the metrics *
 * related to each and every Individual *
 * Virtual SCSI/SAS adapter stats in the VIOS */
#include<stdio.h>
#include<stdlib.h>
#include<libperfstat.h>
#include<net/if_types.h>
/* define default interval and count values */
#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1
/* Check value returned by malloc for NULL */

```

```

#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
                                perror ("malloc");\
                                exit(2);\
                                }\
}

int count = COUNT_DEFAULT, interval = INTERVAL_DEFAULT, tot;
int returncode;

/* support for remote node statistics collection in a cluster environment */
perfstat_id_node_t nodeid;
static char nodename[MAXHOSTNAMELEN] = "";
static int collect_remote_node_stats = 0;

/* store the data structures */
static perfstat_diskadapter_t *statp ,*statq;

/*
 * NAME: showusage
 *       to display the usage
 *
 */

void showusage(char *cmd)
{
    fprintf (stderr, "usage: %s [-i <interval in seconds>] [-c <number of iterations>]
[-n <node name in the cluster>]\n", cmd);
    exit(1);
}

/*
 * NAME: do_initialization
 *       This function initializes the data structures.
 *       It also collects initial set of values.
 *
 * RETURNS:
 * On successful completion:
 * - returns 0.
 * In case of error
 * - exits with code 1.
 */
int do_initialization(void)
{
    /* check how many perfstat_vhost_adapter_t structures are available */

    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        tot = perfstat_virtualdiskadapter_node(&nodeid, NULL, sizeof(perfstat_diskadapter_t), 0);
    }
    else
    {
        tot = perfstat_virtualdiskadapter(NULL, NULL, sizeof(perfstat_diskadapter_t), 0);
    }
    if (tot == 0)
    {
        printf("There is no net adapter\n");
        exit(0);
    }
    if (tot < 0)
    {
        perror("perfstat_vhost_adapter: ");
        exit(1);
    }
}

/* allocate enough memory for all the structures */

```

```

statp = (perfstat_diskadapter_t *)malloc(tot * sizeof(perfstat_diskadapter_t));
CHECK_FOR_MALLOC_NULL(statp);

statq = (perfstat_diskadapter_t *)malloc(tot * sizeof(perfstat_diskadapter_t));
CHECK_FOR_MALLOC_NULL(statq);

return(0);
}
/*
 *Name: display_metrics
 *      collect the metrics and display them
 *
 */
void display_metrics()
{
    perfstat_id_t first;
    int ret, i;

    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;

        strcpy(nodeid.name , FIRST_VHOST);
        ret = perfstat_virtualdiskadapter_node(&nodeid, statq, sizeof(perfstat_diskadapter_t), tot);
    } else
    {
        strcpy(first.name , FIRST_VHOST);
        ret = perfstat_virtualdiskadapter( &first, statq, sizeof(perfstat_diskadapter_t), tot);
    }
    if (ret < 0){
        free(statp);
        free(statq);
        perror("perfstat_vhost_adapter: ");
        exit(1);
    }

    while (count)
    {
        sleep (interval);

        if(collect_remote_node_stats)
        {
            ret = perfstat_virtualdiskadapter_node(&nodei, statp, sizeof(perfstat_diskadapter_t), tot);
        } else {
            ret = perfstat_virtualdiskadapter(&first, statp, sizeof(perfstat_diskadapter_t),tot);
        }
        /* print statistics for each of the interfaces */
        for (i = 0; i < ret; i++) {
            printf(" Adapter name: %s \n", statp[i].name);
            printf(" Adapter Type:%d \n",statp[i].adapter_type);
            printf(" Total number of transfers via adapter :%lld \n",statp[i].xfers - statq[i].xfers);
            printf(" Blocks written to disk: %lld \n",statp[i].wblks - statq[i].wblks);
            printf(" Blocks read from disk: %lld \n",statp[i].rblks - statq[i].rblks);
            printf(" Block size: %lld \n",statp[i].dk_bsize);
            printf(" Number of transfers from disk : %lld \n",statp[i].dk_rxfers - statq[i].dk_rxfers);
            printf(" Read or receive service time : %lld \n",statp[i].dk_rserv - statq[i].dk_rserv);
            printf(" Write or send service time : %lld \n",statp[i].dk_wserv - statq[i].dk_wserv);

            printf(" =====\n");

        }
        memcpy(statq, statp, (tot * sizeof(perfstat_diskadapter_t)));
        count--;
    }
}

```

```

/*
 *Name: main
 *
 */

int main(int argc, char *argv[])
{
    int i, rc;
    /* get the interval and count values */
    /* Process the arguments */
    while ((i = getopt(argc, argv, "i:c:n:")) != EOF)
    {
        switch(i)
        {
            case 'i': /* Interval */
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c': /* Number of interations */
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'n': /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                collect_remote_node_stats = 1;
                break;
            default:
                /* Invalid arguments. Print the usage and terminate */
                showusage(argv[0]);
        }
    }
    if(collect_remote_node_stats)
    {
        /* perfstat_config needs to be called to enable cluster statistics collection */
        rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
        if (rc == -1)
        {
            perror("cluster statistics collection is not available");
            exit(-1);
        }
    }

    do_initialization();
    display_metrics();

    if(collect_remote_node_stats)
    {
        /* Now disable cluster statistics by calling perfstat_config */
        perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
    }
    free(statp);
    free(statq);
    return 0;
}

```

## perfstat\_virtual\_fcadapter Interface

The **perfstat\_virtual\_fcadapter** interface returns a set of structures of type **perfstat\_fcadapter\_t**, which is defined in the **libperfstat.h** file.

The following program shows an example of how the **perfstat\_virtual\_fcadapter** interface is used:

```

/* The sample program display the metrics *
 * related to each and every Individual *
 * virtual FC adapter in the VIOS */
#include<stdio.h>
#include<stdlib.h>

```

```

#include<libperfstat.h>
#include<net/if_types.h>
/* define default interval and count values */
#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1
/* Check value returned by malloc for NULL */
#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
                                perror ("malloc");\!
                                exit(2);\
                                }\
}
int count = COUNT_DEFAULT, interval = INTERVAL_DEFAULT, tot;
int returncode;

/* support for remote node statistics collection in a cluster environment */
perfstat_id_node_t nodeid;
static char nodename[MAXHOSTNAMELEN] = "";
static int collect_remote_node_stats = 0;

/* store the data structures */
static perfstat_fcstat_t *statp ,*statq;

/*
 * NAME: showusage
 *      to display the usage
 */

void showusage(char *cmd)
{
    fprintf (stderr, "usage: %s [-i <interval in seconds>] [-c <number of iterations>]
    [-n <node name in the cluster>]/n; ", cmd);
    exit(1);
}
/*
 * NAME: do_initialization
 *      This function initializes the data structures.
 *      It also collects initial set of values.
 *
 * RETURNS:
 * On successful completion:
 * - returns 0.
 * In case of error
 * - exits with code 1.
 */

int do_initialization(void)
{
    /* check how many perfstat_vfchost_adapter_t structures are available */

    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        tot = perfstat_virtual_fcadapter_node(&nodeid, NULL, sizeof(perfstat_fcstat_t), 0);
    } else {
        tot = perfstat_virtual_fcadapter(NULL, NULL, sizeof(perfstat_fcstat_t), 0);
    }
    if (tot == 0)
    {
        printf("There is no net adapter\n");
        exit(0);
    }
    if (tot < 0)
    {
        perror("perfstat_vhost_adapter: ");
        exit(1);
    }
}

```

```

/* allocate enough memory for all the structures */
statp = (perfstat_fcstat_t *)malloc(tot * sizeof(perfstat_fcstat_t));
CHECK_FOR_MALLOC_NULL(statp);
statq = (perfstat_fcstat_t *)malloc(tot * sizeof(perfstat_fcstat_t));
CHECK_FOR_MALLOC_NULL(statq);

    return(0);
}

/*
 *Name: display_metrics
 *collect the metrics and display them *
 */
void display_metrics()
{
    perfstat_id_t first;
    int ret, i;

    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;

        strcpy(nodeid.name , FIRST_VFCHOST);
        ret = perfstat_virtual_fcadapter_node(&nodeid, statq, sizeof(perfstat_fcstat_t), tot);
    } else
    {
        strcpy(first.name , FIRST_VFCHOST);
        ret = perfstat_virtual_fcadapter(&first, statq, sizeof(perfstat_fcstat_t), 1);
    }
    if (ret &lt; 0)
    {
        free(statp);
        free(statq);
        perror("perfstat_vhost_adapter: ");
        exit(1);
    }
    while (count)
    {
        sleep (interval);
        if(collect_remote_node_stats)
        {
            ret = perfstat_virtual_fcadapter_node(&nodeid, statp, sizeof(perfstat_fcstat_t), tot);
        } else
        {
            ret = perfstat_virtual_fcadapter(&first, statp, sizeof(perfstat_fcstat_t), tot);
        }
        /* print statistics for each of the interfaces */
        for (i = 0; i < ret; i++)
        {
            printf(" Adapter name: %s \n", statp[i].name);
            printf(" VFCHOST Adapter name: %s \n", statp[i].vfc_name);
            printf(" WWPN : %llu \n", statp[i].PortWWN);
            printf(" =====\n");
        }
        memcpy(statq, statp, (tot * sizeof(perfstat_fcstat_t)));
        count--;
    }
}

/*
 *Name: main
 *
 */

int main(int argc, char *argv[])
{

```

```

int i, rc;
/* get the interval and count values */

/* Process the arguments */
while ((i = getopt(argc, argv, "i:c:n:")) != EOF)
{
    switch(i)
    {
        case 'i':          /* Interval */
            interval = atoi(optarg);
            if( interval <= 0 )
                interval = INTERVAL_DEFAULT;
            break;
        case 'c':          /* Number of iterations */
            count = atoi(optarg);
            if( count <= 0 )
                count = COUNT_DEFAULT;
            break;
        case 'n':          /* Node name in a cluster environment */
            strncpy(nodename, optarg, MAXHOSTNAMELEN);
            nodename[MAXHOSTNAMELEN-1] = '\0';
            collect_remote_node_stats = 1;
            break;
        default:
            /* Invalid arguments. Print the usage and terminate */
            showusage(argv[0]);
    }
}

if(collect_remote_node_stats)
{
    /* perfstat_config needs to be called to enable cluster statistics collection */
    rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
        exit(-1);
    }
}
do_initialization();
display_metrics();

if(collect_remote_node_stats)
{
    /* Now disable cluster statistics by calling perfstat_config */
    perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}
free(statp);
free(statq);
return 0;
}

```

## perfstat\_virtualdisktarget Interface

The **perfstat\_virtualdisktarget** interface returns a set of structures of type **perfstat\_disk\_t**, which is defined in the **libperfstat.h** file.

The following program shows an example of how the **perfstat\_virtualdisktarget** interface is used:

```

/* The sample program display the metrics *
 * related to each and every Individual *
 * Virtual Target Device in the VIOS */
#include<stdio.h>
#include<stdlib.h>
#include<libperfstat.h>
#include<net/if_types.h>
/* define default interval and count values */
#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1
/* Check value returned by malloc for NULL */

```

```

CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
                                perror ("malloc");\
                                exit(2);\
                                }\
}

int count = COUNT_DEFAULT, interval = INTERVAL_DEFAULT, tot;
int returncode;

/* support for remote node statistics collection in a cluster environment */
perfstat_id_node_t nodeid;
static char nodename[MAXHOSTNAMELEN] = "";
static int collect_remote_node_stats = 0;

/* store the data structures */
static perfstat_disk_t *statp ,*statq;

/*
 * NAME: showusage
 *      to display the usage
 *
 */

void showusage(char *cmd)
{
    fprintf (stderr, "usage: %s [-i <interval in seconds>] [-c <number of iterations>]
    [-n <node name in the cluster>]\n",
    cmd);
    exit(1);
}

/*
 * NAME: do_initialization
 *      This function initializes the data structures.
 *      It also collects initial set of values.
 *
 * RETURNS:
 * On successful completion:
 * - returns 0.
 * In case of error
 * - exits with code 1.
 */

int do_initialization(void)
{
    /* check how many perfstat_vhost_adapter_t structures are available */

    if(collect_remote_node_stats)
    {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        tot = perfstat_virtualdisktarget_node(&nodeid, NULL, sizeof(perfstat_disk_t), 0);
    } else {
        tot = perfstat_virtualdisktarget(NULL, NULL, sizeof(perfstat_disk_t), 0);
    }
    if (tot == 0) {
        printf("There is no VTD's\n");
        exit(0);
    }
    if (tot < 0) {
        perror("perfstat_virtualdisktarget: ");
        exit(1);
    }

    /* allocate enough memory for all the structures */

```

```

    statp = (perfstat_disk_t *)malloc(tot * sizeof(perfstat_disk_t));
    CHECK_FOR_MALLOC_NULL(statp);

    statq = (perfstat_disk_t *)malloc(tot * sizeof(perfstat_disk_t));
    CHECK_FOR_MALLOC_NULL(statq);

    return(0);
}

/*
 *Name: display_metrics
 *collect the metrics and display them
 *
 */
void display_metrics()
{
    perfstat_id_t first;
    int ret, i;

    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;

        strcpy(nodeid.name , FIRST_VTD);
        ret = perfstat_virtualdisktarget_node(&nodeid, statq, sizeof(perfstat_disk_t), tot);
    } else {
        strcpy(first.name , FIRST_VTD);
        ret = perfstat_virtualdisktarget( &first, statq, sizeof(perfstat_disk_t), tot);
    }
    if (ret < 0)
    {
        free(statp);
        free(statq);
        perror("perfstat_virtualdisktarget: ");
        exit(1);
    }
    while (count)
    {
        sleep (interval);

        if(collect_remote_node_stats)
        {
            ret = perfstat_virtualdisktarget_node(&nodeid, statp, sizeof(perfstat_disk_t), tot);
        } else {
            ret = perfstat_virtualdisktarget(&first, statp, sizeof(perfstat_disk_t), tot);
        }
        /* print statistics for each of the interfaces */
        for (i = 0; i < ret; i++)
        {
            printf(" Adapter name: %s \n", statp[i].name);
            printf(" Disk block size: %lld \n", statp[i].bsize);
            printf(" Number of transfers to/from disk : %lld \n", statp[i].xfers);
            printf(" Number of blocks written to disk : %lld \n", statp[i].wblks);
            printf(" =====\n");
        }
        memcpy(statq, statp, (tot * sizeof(perfstat_disk_t)));
        count--;
    }
}

/*
 *Name: main
 *
 */
int main(int argc, char *argv[])

```

```

{
    int i, rc;
    /* get the interval and count values */

    /* Process the arguments */
    while ((i = getopt(argc, argv, "i:c:n:")) != EOF)
    {
        switch(i)
        {
            case 'i': /* Interval */
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c': /* Number of iterations */
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'n': /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                collect_remote_node_stats = 1;
                break;
            default:
                /* Invalid arguments. Print the usage and terminate */
                showusage(argv[0]);
        }
    }
    if(collect_remote_node_stats)
    {
        /* perfstat_config needs to be called to enable cluster statistics collection */
        rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
        if (rc == -1)
        {
            perror("cluster statistics collection is not available");
            exit(-1);
        }
    }

    do_initialization();
    display_metrics();
    if(collect_remote_node_stats)
    {
        /* Now disable cluster statistics by calling perfstat_config */
        perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
    }

    free(statp);
    free(statq);
    return 0;
}

```

## | **perfstat\_bridgedadapters Interface**

| The **perfstat\_bridgedadapters** interface returns a set of structures of type **perfstat\_netadapter\_t**, which is defined in the **libperfstat.h** file.

| The following program shows an example of how the **perfstat\_bridgedadapters** interface is used:

```

| /* The sample program display the metrics *
| * related to each and every Individual *
| * physical and virtual/trunk adapters which are under SEA in the VIOS */
| #include<stdio.h>
| #include<stdlib.h>
| #include<libperfstat.h>
| #include<net/if_types.h>
| /* define default interval and count values */
| #define INTERVAL_DEFAULT 1
| #define COUNT_DEFAULT 1

```

```

| /* Check value returned by malloc for NULL */
| #define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
|                                     perror ("malloc");\
|                                     exit(2);\
|                                     }\
|                                     }
|
| int count = COUNT_DEFAULT, interval = INTERVAL_DEFAULT, tot;
| int returncode;
| /* support for remote node statistics collection in a cluster environment */
| perfstat_id_node_t nodeid;
| static char nodename[MAXHOSTNAMELEN] = "";
| static int collect_remote_node_stats = 0;
|
| /* store the data structures */
|
| static perfstat_netadapter_t *statp ,*statq;
|
| /*
|  * NAME: showusage
|  *       to display the usage
|  *
|  */
|
| void showusage(char *cmd)
| {
|     fprintf (stderr, "usage: %s [-i <interval in seconds>] [-c <number of iterations>]
|     [-n <node name in the cluster>]/n; ", cmd);
|     exit(1);
| }
| /*
| /*
|  * NAME: do_initialization
|  *       This function initializes the data structures.
|  *       It also collects initial set of values.
|  *
|  * RETURNS:
|  * On successful completion:
|  * - returns 0.
|  * In case of error
|  * - exits with code 1.
|  */
|
| int do_initialization(void)
| {
|     perfstat_id_t first;
|
|     /* check how many perfstat_netadapter_t structures are available */
|     if(collect_remote_node_stats) {
|         strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
|         /* SEA Adapter Name must be filled */
|         strcpy(nodeid.name , FIRST_SEA);
|         /*nodeid.spec = NODENAME; */
|         tot = perfstat_bridgedadapters_node(&nodeid, NULL, sizeof(perfstat_netadapter_t), 0);
|     } else
|     {
|         /* SEA Adapter Name must be filled */
|         strcpy(first.name , FIRST_SEA);
|         tot = perfstat_bridgedadapters(&first, NULL, sizeof(perfstat_netadapter_t), 0);
|     }
|     if (tot == 0)
|     {
|         printf("There is no SEA Children's\n");
|         exit(0);
|     }
|     if (tot < 0)
|     {

```

```

|         perror("perfstat_bridgedadapters: ");
|         exit(1);
|     }
|     /* allocate enough memory for all the structures */
|     statp = (perfstat_netadapter_t *)malloc(tot * sizeof(perfstat_netadapter_t));
|     CHECK_FOR_MALLOC_NULL(statp);
|     statq = (perfstat_netadapter_t *)malloc(tot * sizeof(perfstat_netadapter_t));
|     CHECK_FOR_MALLOC_NULL(statq);
|     return(0);
| }
| /*
| *Name: display_metrics
| *     collect the metrics and display them
| *
| */
| void display_metrics()
| {
|     perfstat_id_t first;
|     int ret, i;
|
|     if(collect_remote_node_stats) {
|         strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
|         nodeid.spec = NODENAME;
|
|         /* Valid SEA Adapter Name Must be passed */
|         strcpy(nodeid.name , FIRST_SEA);
|         ret = perfstat_bridgedadapters_node(&nodeid, statq, sizeof(perfstat_netadapter_t), tot);
|     } else
|     {
|         /* Valid SEA Adapter Name Must be passed */
|         strcpy(first.name , FIRST_SEA);
|         ret = perfstat_bridgedadapters( &first, statq, sizeof(perfstat_netadapter_t), tot);
|     }
|     if (ret &lt; 0)
|     {
|         free(statp);
|         free(statq);
|         perror("perfstat_netadapter: ");
|         exit(1);
|     }
|     while (count)
|     {
|         sleep (interval);
|         if(collect_remote_node_stats)
|         {
|             ret = perfstat_bridgedadapters_node(&nodeid, statp, sizeof(perfstat_netadapter_t), tot);
|         } else
|         {
|             ret = perfstat_bridgedadapters( &first, statp, sizeof(perfstat_netadapter_t), tot);
|         }
|         /* print statistics for each of the interfaces */
|         for (i = 0; i < ret; i++)
|         {
|             printf(" Adapter name: %s \n", statp[i].name);
|             printf(" ===== Transmit Statistics =====\n");
|             printf(" Transmit Packets: %lld \n", statp[i].tx_packets - statq[i].tx_packets);
|             printf(" Transmit Bytes: %lld \n", statp[i].tx_bytes - statq[i].tx_bytes);
|             printf(" Transfer Interrupts : %lld \n",
|                 statp[i].tx_interrupts - statq[i].tx_interrupts);
|             printf(" Transmit Errors : %lld \n", statp[i].tx_errors - statq[i].tx_errors);
|             printf(" Packets Dropped at the time of Data Transmission : %lld \n",
|                 statp[i].tx_packets_dropped - statq[i].tx_packets_dropped);
|             printf(" Transmit Queue Size: %lld \n",
|                 statp[i].tx_queue_size - statq[i].tx_queue_size);
|             printf(" Transmit Queue Length :%lld \n",
|                 statp[i].tx_queue_len - statq[i].tx_queue_len);
|             printf(" Transmit Queue Overflow : %lld \n",

```

```

statp[i].tx_queue_overflow - statq[i].tx_queue_overflow);
printf(" Broadcast Packets Transmitted: %lld \n",
statp[i].tx_broadcast_packets - statq[i].tx_broadcast_packets);
printf(" Multicast packets Transmitted: %lld \n",
statp[i].tx_multicast_packets - statq[i].tx_multicast_packets);
printf(" Lost Carrier Sense signal count : %lld \n",
statp[i].tx_carrier_sense - statq[i].tx_carrier_sense);
printf(" Count of DMA Under-runs for Transmission: %lld \n",
statp[i].tx_DMA_underrun - statq[i].tx_DMA_underrun);
printf(" Number of unsuccessful transmissions : %lld \n",
statp[i].tx_lost_CTS_errors - statq[i].tx_lost_CTS_errors);
printf(" Maximum Collision Errors at Transmission: %lld \n",
statp[i].tx_max_collision_errors - statq[i].tx_max_collision_errors);
printf(" Late Collision Errors at Transmission : %lld \n",
statp[i].tx_late_collision_errors - statq[i].tx_late_collision_errors);
printf(" Number of packets deferred for Transmission : %lld \n",
statp[i].tx_deferred - statq[i].tx_deferred);
printf(" Time Out Errors for Transmission : %lld \n",
statp[i].tx_timeout_errors - statq[i].tx_timeout_errors);
printf(" Count of Single Collision error at Transmission: %lld \n",
statp[i].tx_single_collision_count - statq[i].tx_single_collision_count);
printf(" Count of Multiple Collision error at Transmission : %lld \n",
statp[i].tx_multiple_collision_count - statq[i].tx_multiple_collision_count);

printf(" ===== Receive Statistics =====\n");
printf(" Receive Packets :%lld \n",statp[i].rx_packets - statq[i].rx_packets);
printf(" Receive Bytes :%lld \n", statp[i].rx_bytes - statq[i].rx_bytes);
printf(" Receive Interrupts : %lld \n",
statp[i].rx_interrupts - statq[i].rx_interrupts);
printf(" Input errors on interface :%lld \n",
statp[i].rx_errors - statq[i].rx_errors);
printf(" Number of Packets Dropped : %lld \n",
statp[i].rx_packets_dropped - statq[i].rx_packets_dropped);
printf(" Count of Bad Packets Received : %lld \n",
statp[i].rx_bad_packets - statq[i].rx_bad_packets);
printf(" Number of MultiCast Packets Received : %lld \n",
statp[i].rx_multicast_packets - statq[i].rx_multicast_packets);
printf(" Number of Broadcast Packets Received : %lld \n",
statp[i].rx_broadcast_packets - statq[i].rx_broadcast_packets);
printf(" Count of Packets Received with CRC errors: %lld \n",
statp[i].rx_CRC_errors - statq[i].rx_CRC_errors);
printf(" DMA over-runs : %lld \n",
statp[i].rx_DMA_overrun - statq[i].rx_DMA_overrun);
printf(" Alignment Errors : %lld \n",
statp[i].rx_alignment_errors - statq[i].rx_alignment_errors);
printf(" No Resource Errors : %lld \n",
statp[i].rx_noresource_errors - statq[i].rx_noresource_errors);
printf(" Collision Errors: %lld \n",
statp[i].rx_collision_errors - statq[i].rx_collision_errors);
printf(" Number of Short Packets Received: %lld \n",
statp[i].rx_packet_tooshort_errors - statq[i].rx_packet_tooshort_errors);
printf(" Number of Too Long Packets Received : %lld \n",
statp[i].rx_packet_toolong_errors - statq[i].rx_packet_toolong_errors);
printf(" Number of Received Packets discarded by Adapter: %lld \n",
statp[i].rx_packets_discardedbyadapter -statq[i].rx_packets_discardedbyadapter);
printf(" Adapter Type :%d \n",statp[i].adapter_type);
printf(" =====\n");
}

memcpy(statq, statp, (tot * sizeof(perfstat_netadapter_t)));
count--;
}
}
/*

```

```

| *Name: main
| *
| */
|
| int main(int argc, char *argv[])
| {
|     int i, rc;
|     /* get the interval and count values */
|
|     /* Process the arguments */
|     while ((i = getopt(argc, argv, "i:c:n:")) != EOF)
|     {
|         switch(i)
|         {
|             case 'i': /* Interval */
|                 interval = atoi(optarg);
|                 if( interval <= 0 )
|                     interval = INTERVAL_DEFAULT;
|                 break;
|             case 'c': /* Number of iterations */
|                 count = atoi(optarg);
|                 if( count <= 0 )
|                     count = COUNT_DEFAULT;
|                 break;
|             case 'n': /* Node name in a cluster environment */
|                 strncpy(nodename, optarg, MAXHOSTNAMELEN);
|                 nodename[MAXHOSTNAMELEN-1] = '\0';
|                 collect_remote_node_stats = 1;
|                 break;
|             default:
|                 /* Invalid arguments. Print the usage and terminate */
|                 showusage(argv[0]);
|         }
|     }
|
|     if(collect_remote_node_stats)
|     { /* perfstat_config needs to be called to enable cluster statistics collection */
|         rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
|         if (rc == -1)
|         {
|             perror("cluster statistics collection is not available");
|             exit(-1);
|         }
|     }
|
|     do_initialization();
|     display_metrics();
|
|     if(collect_remote_node_stats)
|     { /* Now disable cluster statistics by calling perfstat_config */
|         perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
|     }
|
|     free(statp);
|     free(statq);
|     return 0;
| }

```

## perfstat\_ssp Interface

The **perfstat\_ssp** interface returns a set of structures of type **perfstat\_ssp\_t**, which is defined in the **libperfstat.h** file.

The following program shows an example of how the **perfstat\_ssp** interface is used:

```

/* The sample program used to Display *
 * the shared storage pool information */
#include<stdio.h>

```

```

#include<libperfstat.h>
#include<errno.h>
/* define default interval and count values */
#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1
#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
                                perror ("malloc");\
                                exit(2);\
                                }\
                                }

/* store the data structures */
perfstat_ssp_t *sspstats = NULL;
int rc, returned_count, flag = 0;

/*
 * NAME: showusage
 *       to display the usage
 *
 */

void showusage()
{
    printf("Usage:simplesspstat -s | -d | -l [-i interval] [-c count]\n");
    exit(1);
}

/*
 * NAME: do_initialization
 *       This function initializes the data structures.
 *       It also collects initial set of values.
 *
 * RETURNS:
 * On successful completion:
 * - returns 0.
 * In case of error
 * - exits with code 1.
 */

int do_initialization()
{
    returned_count = perfstat_ssp(NULL, NULL, sizeof(perfstat_ssp_t),0,flag);

    if(returned_count < 0){
        perror("perfstat_ssp_t:");
        exit(-1);
    }

    /* Allocate memory for the structure*/
    if(returned_count==0)
        sspstats=( perfstat_ssp_t *) malloc(sizeof(perfstat_ssp_t));
    else
        sspstats=( perfstat_ssp_t *) malloc(sizeof(perfstat_ssp_t) * returned_count);

    CHECK_FOR_MALLOC_NULL(sspstats);

    return(0);
}

static void do_cleanup()
{
    free(sspstats);
}

/*
 *Name: display_metrics
 *       collect the metrics and display them

```

```

*
*/
void display_metrics()
{
    int i,rc;

    while (count)
    {
        /* Obtain cluster name, ssp name and vtd list*/
        rc=perfstat_ssp(NULL, sspstats, sizeof(perfstat_ssp_t),1,flag);
        if(rc<0)
        {
            perror("perfstat_ssp_t:");
            exit(-1);
        }

        sleep (interval);
        fprintf(stdout, "\nCluster Name : %s\n", sspstats->cluster_name);
        fprintf(stdout, "Storage Pool Name : %s\n", sspstats->spool_name);

        if(flag == 1){
            fprintf(stdout, "Total Space : %lld\n", sspstats->u.global.total_space);
            fprintf(stdout, "Total Used Space : %lld\n", sspstats->u.global.total_used_space);
        }

        if(flag == 2){
            if(rc!=0)
                fprintf(stdout, "Disk name : \n");
            else
                fprintf(stdout, "There are no disks in the storage pool\n");

            for(i=0; i<returned_count; i++){
                fprintf(stdout, "%s ",sspstats[i].u.disk.diskname);
            }
        }

        if(flag == 3){
            if(rc!=0)
                fprintf(stdout, "VTD name : \n");
            else{
                fprintf(stdout, "There are no VTD's in the storage pool\n");
                exit(-1);
            }

            for(i=0; i<returned_count; i++){
                fprintf(stdout, "%s ",sspstats[i].u.vtd.vtd_name);
                fprintf(stdout, "%s ",sspstats[i].u.vtd.lu_name);
            }

            fprintf(stdout, "\n\nLU type:\n");
            for(i=0; i<returned_count; i++){
                fprintf(stdout, "%s ",sspstats[i].u.vtd.lu_type);
            }

            fprintf(stdout, "\n\nLU size:\n");
            for(i=0; i<returned_count; i++){
                fprintf(stdout, "%lld ",sspstats[i].u.vtd.lu_size);
            }

            fprintf(stdout, "\n\nLU free:\n");
            for(i=0; i<returned_count; i++){
                fprintf(stdout, "%lld ",sspstats[i].u.vtd.lu_free);
            }

            fprintf(stdout, "\n\n");
        }
    }
}

```

```

        count--;
    }
}

int main(int argc, char* argv[])
{
    int c,sflag=0,dflag=0,lflag=0;
    /* Enable the cluster statistics using perfstat_config */
    rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
        exit(-1);
    }

    while((c = getopt(argc, argv, "i:c:sdl"))!= EOF){
        switch(c){
            case 'i':
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c':
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 's':
                flag = 1;
                sflag = 1;
                break;
            case 'd':
                flag = 2;
                dflag = 1;
                break;
            case 'l':
                flag = 3;
                lflag = 1;
                break;
            default:
                showusage(argv[0]);
        }
    }
    if(flag == 0){
        showusage(argv[0]);
    }

    if(sflag && (dflag || lflag)){
        showusage(argv[0]);
    }

    if(dflag && (sflag || lflag)){
        showusage(argv[0]);
    }

    if(lflag && (sflag || dflag)){
        showusage(argv[0]);
    }

    do_initialization();
    display_metrics();
    /* Now disable cluster statistics by calling perfstat_config */
    perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}

```

```

do_cleanup();
    /*realloc(sspstats);*/
    return 0;
}

```

## perfstat\_ssp\_ext Interface

The `perfstat_ssp_ext` subroutine returns a set of structures of type `perfstat_ssp_t`, which are defined in the `libperfstat.h` file.

The following example program shows the usage of the `perfstat_ssp_ext` subroutine:

```

#include <stdio.h>
#include <libperfstat.h>
#include <errno.h>
/* define default interval and count values */
#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1
/* Check value returned by malloc for NULL */
#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
    perror ("malloc");\
    exit(2);\
}\
}
int count = COUNT_DEFAULT, interval = INTERVAL_DEFAULT;
/* store the data structures */
perfstat_ssp_t *sspstats = NULL;
int rc, returned_count, flag = 0;
char tiername[VIOS_STR_128];
char fgname[VIOS_STR_128];
char diskname[VIOS_STR_128];
perfstat_ssp_id_t sspid = {0};
int tflag = 0, dflag = 0, fflag = 0;
/*
 * NAME: showusage
 *      to display the usage
 *
 */
void showusage()
{
    printf("Usage:simplesspstat -T | -F | -D | -N [-i interval] [-c count][-t <tiername> ]
          [-f <failuregroupname>] [-d <diskname>] [-n <nodename>]\n");
    exit(1);
}
/*
 * NAME: do_initialization
 *      This function initializes the data structures.
 *      It also collects initial set of values.
 *
 * RETURNS:
 * On successful completion:
 * - returns 0.
 * In case of error
 * - exits with code 1.
 */
int do_initialization()
{
    if(fflag || dflag || tflag)
        sspid.spec |= PERFFILT_NAME;
    else
        sspid.spec = PERFFILT_NONE;
    if(fflag)
    {
        sspid.spec |= PERFFILT_FG;
        strncpy(sspid.fg.name, fgname, VIOS_STR_128);
    }
    if(dflag)
    {

```

```

    sspid.spec |= PERFFILT_PHYSV;
    strncpy(sspid.pv.name,diskname,VIOS_STR_128);
}
if(tflag)
{
    sspid.spec |= PERFFILT_TIER;
    strncpy(sspid.tier.name,tiername,VIOS_STR_128);
}
if(nflag)
{
    sspid.spec |= PERFFILT_NODE;
    strncpy(sspid.node.name,nodename,VIOS_STR_128);
}
returned_count = perfstat_ssp_ext(&sspid, NULL, sizeof(perfstat_ssp_t),0,flag);
if(returned_count <= 0){
    printf("perfstat_ssp_exit failed with error:%d",errno);
    exit(-1);
}
/* Allocate memory for the structure*/
sspstats=( perfstat_ssp_t *) malloc(sizeof(perfstat_ssp_t) * returned_count);
CHECK_FOR_MALLOC_NULL(sspstats);
return(0);
}
static void do_cleanup()
{
    free(sspstats);
}
/*
 *Name: display_metrics
 *      collect the metrics and display them
 *
 */
void display_metrics()
{
    int i,rc;
    while (count)
    {
        /* Obtain SSP COnfig stats for tier/failure group or PV stats based on the flag*/
        rc=perfstat_ssp_ext(&sspid, sspstats, sizeof(perfstat_ssp_t),returned_count,flag);
        if(rc<0)
        { /*Tier/FG/PV*/
            perror("perfstat_ssp_t:");
            exit(-1);
        }
        sleep (interval);
        fprintf(stdout, "\nCluster Name : %s\n", sspstats->cluster_name);
        fprintf(stdout, "Storage Pool Name : %s\n", sspstats->spool_name);
        if(flag == SSPPV){
            if(rc!=0)
                fprintf(stdout, "Disk name \t Tier Name\t Failure Group:\n");
            else
                fprintf(stdout, "There are no disks in the storage pool\n");

            for(i=0; i<returned_count; i++){
                fprintf(stdout, "%8s\t%8s\t%13s\n ",
                    sspstats[i].u.disk.diskname,sspstats[i].u.disk.tiername,sspstats[i].u.disk.fgname);
            }
        }
        if(flag == SSPTIER)
        {
            if(rc!=0)
                fprintf(stdout, "Tier name \t Tier ID\n");
            else
                fprintf(stdout, "There are no tiers in the storage pool\n");

            for(i=0; i<returned_count; i++){
                fprintf(stdout, "%8s\t%6llu\n ",

```

```

    sspstats[i].u.tier.tiername,sspstats[i].u.tier.tierid);
}
}
if(flag == SSPFG)
{
    if(rc!=0)
        fprintf(stdout, "FailureGroupName FailureGroupID TierName Tier ID\n");
    else
        fprintf(stdout, "There are no failuregroups in the storage pool\n");

    for(i=0; i<returned_count; i++){
        fprintf(stdout, "%16s\t%15llu\t%8s\t%6llu\n ",
            sspstats[i].u.fg.fgname,sspstats[i].u.fg.fgid,
            sspstats[i].u.fg.tiername,sspstats[i].u.fg.tierid);
    }

}
if(flag == SSPNODE)
{
    for ( i =0; i <returned_count ; i++)
    {
        fprintf(stdout,"Nodename:%s,mtms:%s,status:%d,
            poolstatus:%d,ip:%s,lparid:%d\n",
            sspstats[i].u.node.hostname,sspstats[i].u.node.mtms,
            sspstats[i].u.node.status,sspstats[i].u.node.poolstatus,
            sspstats[i].u.node.ip,sspstats[i].u.node.lparid);
    }
}
fprintf(stdout,"\n\n");
count--;
}
}

int main(int argc, char* argv[])
{
    int c,Tflag=0,Dflag=0,Fflag=0;
    /* Enable the cluster statistics using perfstat_config */
    rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
        exit(-1);
    }
    while((c = getopt(argc, argv, "i:c:TFDf:d:"))!= EOF){
        switch(c){
            case 'i':
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c':
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'T':
                flag = SSPTIER;
                Tflag = 1;
                break;
            case 'F':
                flag = SSPFG;
                Fflag = 1;
                break;
            case 'D':
                flag = SSPPV;

```

```

    Dflag = 1;
    break;
case 'N':
    flag = SSPNODE;
    Nflag = 1;
    break;
case 't':
    tflag = 1;
    strncpy(tiename,optarg,VIOS_STR_128);
    break;
case 'f':
    fflag = 1;
    strncpy(fgname,optarg,VIOS_STR_128);
    break;
case 'd':
    dflag = 1;
    strncpy(diskname,optarg,VIOS_STR_128);
    break;
case 'n':
    nflag = 1;
    strncpy(nodename,optarg,MAXHOSTNAMELEN);
    break;

default:
    showusage(argv[0]);
}
}
if(flag == 0){
    showusage(argv[0]);
}
if(Tflag )
{
    if (Fflag || Dflag || fflag || dflag || Nflag || nflag){
        showusage(argv[0]);
    }
}
if(Fflag)
{
    if (Fflag || Dflag || fflag || dflag || Nflag || nflag){
        showusage(argv[0]);
    }
}
if(Dflag)
{
    if (Fflag || Dflag || fflag || dflag || Nflag || nflag)
        showusage(argv[0]);
}
if(Nflag)
{
    if(Tflag || Fflag || Dflag || fflag || dflag || tflag )
        showusage(argv[0]);
}
do_initialization();
display_metrics();

/* Now disable cluster statistics by calling perfstat_config */
perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);

do_cleanup();
/*realloc(sspstats);*/
return 0;
}

```

## WPAR Interfaces

The following are two types of WPAR interfaces:

- The metrics related to a set of components for a WPAR (such as processors, or memory).
- The specific metrics related to individual components on a WPAR (such as a processor, network interface, or memory page).

All of the following WPAR interfaces use the naming convention **perfstat\_subsystem\_total\_wpar**, and use a common signature:

Item	Descriptor
<b>perfstat_cpu_total_wpar</b>	Retrieves WPAR processor summary usage metrics
<b>perfstat_memory_total_wpar</b>	Retrieves WPAR memory summary usage metrics
<b>perfstat_wpar_total</b>	Retrieves WPAR information metrics
<b>perfstat_memory_page_wpar</b>	Retrieves WPAR memory page usage metrics

The signature used by the **subsystem\_total** interfaces, except for **perfstat\_memory\_page\_wpar**, is as follows:

```
int perfstat_subsystem_total_wpar(perfstat_id_wpar_t *name,
    perfstat_subsystem_total_t *userbuff,
    int sizeof_struct,
    int desired_number);
```

The signature used by the **perfstat\_memory\_page\_wpar** interface is as follows:

```
int perfstat_memory_page_wpar(perfstat_id_wpar_t *name,
    perfstat_psize_t *psize,
    perfstat_subsystem_total_t *userbuff,
    int sizeof_struct,
    int desired_number);
```

The usage of the parameters for all of the interfaces is as follows:

Item	Descriptor
<b>perfstat_id_wpar_t *name</b>	The WPAR ID or WPAR name for which the metrics must be retrieved. <b>Note:</b> When called inside of a WPAR environment, the name must be NULL.
<b>perfstat_subsystem_total_t *userbuff</b>	A memory area with enough space for the returned structure.
<b>int sizeof_struct</b>	The size of the <b>perfstat_memory_total_wpar_t</b> structure.
<b>int desired_number</b>	The number of different page size statistics to be collected.

The number of structures copied and returned without errors use the return value of 1. If there are errors, the return value is -1.

An exception to this scheme is **perfstat\_wpar\_total**. For this function, when name=NULL, userbuff=NULL and desired\_number=0, the total number of **perfstat\_wpar\_total\_t** structures available is returned.

To retrieve all **perfstat\_wpar\_total\_t** structures, select one of the following methods:

- Determine the number of structures and allocate the required memory to hold all structure at one time. You can then call the appropriate API to retrieve all structures using one call.
- Allocate a fixed set of structures and repeatedly call the API to get the next number of structures, each time passing the name returned by the previous call. Start the process by using one of the following queries:
  - wparname set to ""
  - FIRST\_WPARNAME

- wpar\_id set to -1
- FIRST\_WPARID

Repeat the process until the wparname is returned equal to "" or the wpar\_id is returned equal to -1.

The **perfstat\_id\_wpar\_total** interface returns a set of structures of type **perfstat\_id\_wpar\_total\_t**, which is defined in the **libperfstat.h** file. Selected fields from the **perfstat\_id\_wpar\_total\_t** structure include:

Item	Descriptor
spec	Select WPAR ID, WPAR Name, or the RSET Handle from the union
wpar_id	Specifies the WPAR ID
wparname	Specifies the WPAR Name
rset	Specifies the RSET Handle of the rset associated with the WPAR
name	Reserved for future use, must be NULL

The following sections provide examples of the type of data returned and code using each of the interfaces.

### perfstat\_wpar\_total Interface

The **perfstat\_wpar\_total** interface returns a set of structures of type **perfstat\_wpar\_total\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_wpar\_total\_t** structure include:

Item	Descriptor
Type	WPAR type.
online_cpus	The number of virtual processors currently allocated to the partition rset or the number of virtual processors currently allocated to the system partition.
online_memory	The amount of memory currently allocated to the system partition.
cpu_limit	The maximum limit of processor resources this WPAR consumes. The processor limit is in 100ths of percentage units.

Several other paging-space-related metrics (such as number of system calls, number of reads, writes, forks, execs, and load average) are also returned. For a complete list of other paging-space-related metrics, see the **perfstat\_wpar\_total\_t** section in the **libperfstat.h** header file in *Files Reference*.

The following program emulates **wparstat** behavior and also shows an example of how **perfstat\_wpar\_total** is used from the global environment:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfstat_wpar_total_t *winfo;
    perfstat_id_wpar_t wparid;
    int tot, rc, i;

    tot = perfstat_wpar_total(NULL, NULL, sizeof(perfstat_wpar_total_t), 0);

    if (tot < 0) {
        perror("Error in perfstat_wpar_total");
        exit(-1);
    }

    if (tot == 0) {
        printf("No WPARs found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    winfo = calloc(tot, sizeof(perfstat_wpar_total_t));
    if(winfo==NULL){
        printf("No sufficient memory\n");
        exit(-1);
    }
}
```

```

}

/* Retrieve all WPARs */
bzero(&wparid, sizeof(perfstat_id_wpar_t));
wparid.spec = WPARNAME;
strcpy(wparid.u.wparname, FIRST_WPARNAME);
rc = perfstat_wpar_total(&wparid, winfo, sizeof(perfstat_wpar_total_t), tot);

if (rc < 0) {
    perror("Error in perfstat_wpar_total");
    exit(-1);
}

for(i=0;i<tot;i++){
    printf("Name of the Workload Partition=%s\n",winfo[i].name);
printf("Workload partition identifier=%u\n",winfo[i].wpar_id);
printf("Number of Virtual CPUs in partition rset=%d\n",winfo[i].online_cpus);
printf("Amount of memory currently online in Global Partition=%lld\n",winfo[i].online_memory);
printf("Number of processor units this partition is entitled to receive=%d\n",winfo[i].entitled_proc_capacity);
printf("\n");
}

return(0);
}

```

The program displays an output that is similar to the following example output:

```

Name of the Workload Partition=test
Workload partition identifier=1
Number of Virtual CPUs in partition rset=2
Amount of memory currently online in Global Partition=4096
Number of processor units this partition is entitled to receive=100

```

The following code shows an example of how `perfstat_wpar_total` is used from the WPAR environment:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfstat_wpar_total_t *winfo;
    perfstat_id_wpar_t wparid;
    int tot, rc, i;

    tot = perfstat_wpar_total(NULL, NULL, sizeof(perfstat_wpar_total_t), 0);

    if (tot < 0) {
        perror("Error in perfstat_wpar_total");
        exit(-1);
    }

    if (tot == 0) {
        printf("No WPARs found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    winfo = calloc(tot,sizeof(perfstat_wpar_total_t));
    if(winfo==NULL){
        printf("No sufficient memory\n");
        exit(-1);
    }

    rc = perfstat_wpar_total(NULL, winfo, sizeof(perfstat_wpar_total_t), tot);

    if (rc < 0) {
        perror("Error in perfstat_wpar_total");
        exit(-1);
    }

    for(i=0;i<tot;i++){
        printf("Name of the Workload Partition=%s\n",winfo[i].name);
printf("Workload partition identifier=%u\n",winfo[i].wpar_id);
printf("Number of Virtual CPUs in partition rset=%d\n",winfo[i].online_cpus);
printf("Amount of memory currently online in Global Partition=%lld\n",winfo[i].online_memory);
printf("Number of processor units this partition is entitled to receive=%d\n",winfo[i].entitled_proc_capacity);
printf("\n");
}
}

```

```

    }
    return(0);
}

```

## perfstat\_cpu\_total\_wpar Interface

The `perfstat_cpu_total_wpar` interface returns a set of structures of type `perfstat_cpu_total_wpar_t`, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_cpu_total_wpar_t` structure include:

Item	Descriptor
<code>processorHz</code>	Processor speed in Hertz (from ODM)
<code>Description</code>	Processor type (from ODM)
<code>Ncpus</code>	Current number of active processors available to the WPAR
<code>ncpus_cfg</code>	Number of configured processors; that is, the maximum number of processors that this copy of AIX® can handle simultaneously
<code>Puser</code>	Total number of physical processor ticks spent in user mode
<code>Psys</code>	Total number of physical processor ticks spent in system (kernel) mode
<code>Piddle</code>	Total number of physical processor ticks spent idle with no I/O pending
<code>Pwait</code>	Total number of physical processor ticks spent idle with I/O pending

Several other paging-space-related metrics (such as number of system calls, number of reads, writes, forks, execs, and load average) are also returned. For a complete list of other paging-space-related metrics, see the `perfstat_cpu_total_wpar_t` section in the `libperfstat.h` header file.

The following program emulates `wparstat` behavior and also shows an example of how `perfstat_cpu_total_wpar_t` is used from the global environment:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfstat_cpu_total_wpar_t *cpustats;
    perfstat_id_wpar_t wparid;
    perfstat_wpar_total_t *winfo;
    int i,j,rc,totwpars;

    /* Retrieve total number of WPARs in the system */
    totwpars = perfstat_wpar_total(NULL, NULL, sizeof(perfstat_wpar_total_t), 0);
    if (totwpars < 0) {
        perror("Error in perfstat_wpar_total");
        exit(-1);
    }

    if (totwpars == 0) {
        printf("No WPARs found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    winfo = calloc(totwpars,sizeof(perfstat_wpar_total_t));

    /* Retrieve all WPARs */
    bzero(&wparid, sizeof(perfstat_id_wpar_t));
    wparid.spec = WPARNAME;
    strcpy(wparid.u.wparname, "test");
    rc = perfstat_wpar_total(&wparid, winfo, sizeof(perfstat_wpar_total_t), totwpars);

    if (rc <= 0) {
        perror("Error in perfstat_wpar_total");
        exit(-1);
    }
}

```

```

for(i=0; i < totwpars; i++)
{
    bzero(&wparid, sizeof(perfststat_id_wpar_t));
    wparid.spec = WPARID;
    wparid.u.wpar_id = winfo[i].wpar_id;

    cpustats=calloc(1,sizeof(perfststat_cpu_total_wpar_t));
    rc = perfstat_cpu_total_wpar(&wparid, cpustats, sizeof(perfststat_cpu_total_wpar_t), 1);
    if (rc != 1) {
        perror("perfstat_cpu_total_wpar");
        exit(-1);
    }
    for(j=0;j<rc;j++){
        printf("Number of active logical processors in Global=%d\n",cpustats[j].ncpus);
        printf("Processor description=%s\n",cpustats[j].description);
        printf("Processor speed in Hz=%lld\n",cpustats[j].processorHZ);
        printf("Number of process switches=%lld\n",cpustats[j].pswitch);
        printf("Number of forks system calls executed=%lld\n",cpustats[j].sysfork);
        printf("Length of the run queue=%lld\n",cpustats[j].runque);
        printf("Length of the swap queue=%lld\n",cpustats[j].swpque);
    }
}
}

```

The program displays an output that is similar to the following example output:

```

Number of active logical processors in Global=8
Processor description=PowerPC_POWER7
Processor speed in Hz=3304000000
Number of process switches=1995
Number of forks system calls executed=322
Length of the run queue=3
Length of the swap queue=1

```

The following code shows an example of how `perfstat_cpu_total_wpar` is used from the WPAR environment:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfstat_cpu_total_wpar_t *cpustats;
    perfstat_id_wpar_t wparid;
    perfstat_wpar_total_t *winfo;
    int i,j,rc,totwpars;

    /* Retrieve total number of WPARs in the system */
    totwpars = perfstat_wpar_total(NULL, NULL, sizeof(perfststat_wpar_total_t), 0);
    if (totwpars < 0) {

        perror("Error in perfstat_wpar_total");
        exit(-1);
    }

    if (totwpars == 0) {
        printf("No WPARs found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    winfo = calloc(totwpars,sizeof(perfststat_wpar_total_t));

    /* Retrieve all WPARs */
    bzero(&wparid, sizeof(perfststat_id_wpar_t));
    wparid.spec = WPARNAME;
    strcpy(wparid.u.wparname, "test");

```

```

rc = perfstat_wpar_total(NULL, winfo, sizeof(perfstat_wpar_total_t), totwpars);

if (rc <= 0) {
    perror("Error in perfstat_wpar_total");
    exit(-1);
}

for(i=0; i < totwpars; i++)
{
    bzero(&wparid, sizeof(perfstat_id_wpar_t));
    wparid.spec = WPARID;
    wparid.u.wpar_id = winfo[i].wpar_id;

    cpustats=calloc(1,sizeof(perfstat_cpu_total_wpar_t));
    rc = perfstat_cpu_total_wpar(NULL, cpustats, sizeof(perfstat_cpu_total_wpar_t), 1);
    if (rc != 1) {
        perror("perfstat_cpu_total_wpar");
        exit(-1);
    }
    for(j=0;j<rc;j++){
        printf("Number of active logical processors in Global=%d\n",cpustats[j].ncpus);
        printf("Processor description=%s\n",cpustats[j].description);
        printf("Processor speed in Hz=%lld\n",cpustats[j].processorHZ);
        printf("Number of process switches=%lld\n",cpustats[j].pswitch);
        printf("Number of forks system calls executed=%lld\n",cpustats[j].sysfork);
        printf("Length of the run queue=%lld\n",cpustats[j].runque);
        printf("Length of the swap queue=%lld\n",cpustats[j].swpque);
    }
}
}

```

## perfstat\_memory\_total\_wpar Interface

The `perfstat_memory_total_wpar` interface returns a set of structures of type `perfstat_memory_total_wpar_t`, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_memory_total_wpar_t` structure include:

Item	Descriptor
<code>real_total</code>	Amount of Global real memory (in units of 4 KB pages)
<code>real_free</code>	Amount of Global free real memory (in units of 4 KB pages)
<code>real_pinned</code>	Amount of WPAR pinned memory (in units of 4 KB pages)
<code>Pgins</code>	Number of WPAR pages paged in
<code>Pgouts</code>	Number of WPAR pages paged out

Several other paging-space-related metrics (such as number of system calls, number of reads, writes, forks, execs, and load average) are also returned. For a complete list of other paging-space-related metrics, see the `perfstat_memory_total_wpar_t` section in the `libperfstat.h` header file.

The following program emulates `wparstat` behavior and also shows an example of how `perfstat_memory_total_wpar` is used from the global environment:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfstat_memory_total_wpar_t *memstats;
    perfstat_id_wpar_t wparid;
    perfstat_wpar_total_t *winfo;
    int i,j,rc,totwpars;

    /* Retrieve total number of WPARs in the system */
    totwpars = perfstat_wpar_total(NULL, NULL, sizeof(perfstat_wpar_total_t), 0);
    if (totwpars < 0) {
        perror("Error in perfstat_wpar_total");
    }
}

```

```

        exit(-1);
    }
    if (totwpars == 0) {
        printf("No WPARs found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    winfo = calloc(totwpars, sizeof(perfststat_wpar_total_t));

    /* Retrieve all WPARs */
    bzero(&wparid, sizeof(perfststat_id_wpar_t));
    wparid.spec = WPARNAME;
    strcpy(wparid.u.wparname, "test");
    rc = perfststat_wpar_total(&wparid, winfo, sizeof(perfststat_wpar_total_t), totwpars);
    if (rc <= 0) {

        perror("Error in perfststat_wpar_total");
        exit(-1);
    }
    for(i=0; i < totwpars; i++)
    {

        bzero(&wparid, sizeof(perfststat_id_wpar_t));
        wparid.spec = WPARID;
        wparid.u.wpar_id = winfo[i].wpar_id;

        memstats=calloc(1, sizeof(perfststat_memory_total_wpar_t));
        rc = perfststat_memory_total_wpar(&wparid, memstats, sizeof(perfststat_memory_total_wpar_t), 1);
        if (rc != 1) {
            perror("perfststat_memory_total_wpar");
            exit(-1);
        }
    }
    for(j=0; j<rc; j++){
        printf("Global total real memory=%lld\n", memstats[j].real_total);
        printf("Global free real memory=%lld\n", memstats[j].real_free);
        printf("Real memory which is pinned=%lld\n", memstats[j].real_pinned);
        printf("Real memory which is in use=%lld\n", memstats[j].real_inuse);
        printf("Number of page faults=%lld\n", memstats[j].pgexct);
        printf("Number of pages paged in=%lld\n", memstats[j].pgins);
        printf("Number of pages paged out=%lld\n", memstats[j].pgouts);
    }
}
}

```

The program produces output that is similar to the following output:

```

Global total real memory=1048576
Global free real memory=721338
Real memory which is pinned=464
Real memory which is in use=2886
Number of page faults=37176802
Number of pages paged in=1304
Number of pages paged out=64

```

The following code shows an example of how `perfststat_memory_total_wpar` is used from the WPAR environment:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfststat_memory_total_wpar_t *memstats;
    perfststat_id_wpar_t wparid;
    perfststat_wpar_total_t *winfo;
    int i,j,rc,totwpars;

```

```

/* Retrieve total number of WPARs in the system */
totwpars = perfstat_wpar_total(NULL, NULL, sizeof(perfstat_wpar_total_t), 0);
if (totwpars < 0) {
    perror("Error in perfstat_wpar_total");
    exit(-1);
}
if (totwpars == 0) {
    printf("No WPARs found in the system\n");
    exit(-1);
}

/* allocate enough memory for all the structures */
winfo = calloc(totwpars,sizeof(perfstat_wpar_total_t));

/* Retrieve all WPARs */
bzero(&wparid, sizeof(perfstat_id_wpar_t));
wparid.spec = WPARNAME;
strcpy(wparid.u.wparname, "test");
rc = perfstat_wpar_total(NULL, winfo, sizeof(perfstat_wpar_total_t), totwpars);
if (rc <= 0) {
    perror("Error in perfstat_wpar_total");
    exit(-1);
}
for(i=0; i < totwpars; i++)
{
    bzero(&wparid, sizeof(perfstat_id_wpar_t));
    wparid.spec = WPARID;
    wparid.u.wpar_id = winfo[i].wpar_id;

    memstats=calloc(1,sizeof(perfstat_memory_total_wpar_t));
    rc = perfstat_memory_total_wpar(NULL, memstats, sizeof(perfstat_memory_total_wpar_t), 1);
    if (rc != 1) {
        perror("perfstat_memory_total_wpar");
        exit(-1);
    }
}
for(j=0;j<rc;j++){
    printf("Global total real memory=%lld\n",memstats[j].real_total);
    printf("Global free real memory=%lld\n",memstats[j].real_free);
    printf("Real memory which is pinned=%lld\n",memstats[j].real_pinned);
    printf("Real memory which is in use=%lld\n",memstats[j].real_inuse);
    printf("Number of page faults=%lld\n",memstats[j].pgexct);
    printf("Number of pages paged in=%lld\n",memstats[j].pgins);
    printf("Number of pages paged out=%lld\n",memstats[j].pgouts);
}
}
}

```

## perfstat\_memory\_page\_wpar Interface

The `perfstat_memory_page_wpar` interface returns a set of structures of type `perfstat_memory_page_wpar_t`, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_memory_page_wpar_t` structure include:

Item	Descriptor
<b>Psize</b>	Page size in bytes
<b>real_total</b>	Amount of Global real memory (in units of the psize)
<b>real_pinned</b>	Amount of WPAR pinned memory (in units of psize)
<b>Pgins</b>	Number of WPAR pages paged in
<b>Pgouts</b>	Number of WPAR pages paged out

Several other paging-space-related metrics (such as number of system calls, number of reads, writes, forks, execs, and load average) are also returned. For a complete list of other paging-space-related metrics, see the **perfstat\_memory\_page\_wpar\_t** section in the **libperfstat.h** header file.

The following program emulates **vmstat** behavior and also shows an example of how **perfstat\_memory\_page\_wpar** is used from the global environment:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(){
int i, psize, rc;
perfstat_memory_page_wpar_t *pageinfo;
perfstat_id_wpar_t wparid;
wparid.spec = WPARNAME;
strcpy(wparid.u.wparname,"test");
perfstat_psize_t psize;

psize.psize = FIRST_PSIZE;
/* Get the number of page sizes */
psizes = perfstat_memory_page_wpar(&wparid, NULL, NULL, sizeof(perfstat_memory_page_wpar_t),0);
/*check for error */
if (psizes <= 0 ){
    perror("perfstat_memory_page_wpar ");
    exit(-1);
}

/*Allocate enough memory to hold the structures */
pageinfo = (perfstat_memory_page_wpar_t *)calloc(psize, sizeof(perfstat_memory_page_wpar_t));

/*check for memory allocation */
if (!pageinfo){
    perror("calloc");
    exit(-1);
}

/* call the API and get the data */
rc = perfstat_memory_page_wpar(&wparid, &psize, pageinfo ,
sizeof(perfstat_memory_page_wpar_t), psize);
/* check the return values for any error */
if (rc <= 0){
    perror("perfstat_memory_page_wpar ");
    exit(-1);
}

for(i=0;i<psizes;i++){
printf("Page size in bytes=%lld\n",pageinfo[i].psize);
printf("Number of real memory frames of this page size=%lld\n",pageinfo[i].real_total);
printf("Number of pages pinned=%lld\n",pageinfo[i].real_pinned);
printf("Number of pages in use=%lld\n",pageinfo[i].real_inuse);
printf("Number of page faults=%lld\n",pageinfo[i].pgexct);
printf("Number of pages paged in=%lld\n",pageinfo[i].pgins);
printf("Number of pages paged out=%lld\n",pageinfo[i].pgouts);
printf("Number of page ins from paging space=%lld\n",pageinfo[i].pgspins);
printf("Number of page outs from paging space=%lld\n",pageinfo[i].pgspouts);
}
}
```

```

printf("Number of page scans by clock=%lld\n",pageinfo[i].scans);
printf("Number of page steals=%lld\n",pageinfo[i].pgsteals);
}
}

```

The program produces output that is similar to the following output:

```

Page size in bytes=4096
Number of real memory frames of this page size=572640
Number of pages pinned=143
Number of pages in use=2542
Number of page faults=1613483
Number of pages paged in=1296
Number of pages paged out=58
Number of page ins from paging space=0
Number of page outs from paging space=0
Number of page scans by clock=0
Number of page steals=0
Page size in bytes=65536
Number of real memory frames of this page size=29746
Number of pages pinned=20
Number of pages in use=20
Number of page faults=25294
Number of pages paged in=0
Number of pages paged out=0
Number of page ins from paging space=0
Number of page outs from paging space=0
Number of page scans by clock=0
Number of page steals=0
Page size in bytes=0
Number of real memory frames of this page size=0
Number of pages pinned=0
Number of pages in use=0
Number of page faults=0
Number of pages paged in=0
Number of pages paged out=0
Number of page ins from paging space=0
Number of page outs from paging space=0
Number of page scans by clock=0
Number of page steals=0
Page size in bytes=0
Number of real memory frames of this page size=0
Number of pages pinned=0
Number of pages in use=0
Number of page faults=0
Number of pages paged in=0
Number of pages paged out=0
Number of page ins from paging space=0
Number of page outs from paging space=0
Number of page scans by clock=0
Number of page steals=0

```

The following code shows an example of how `perfstat_memory_page_wpar` is used from the WPAR environment:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(){
int i, psizes, rc;
perfstat_memory_page_wpar_t *pageinfo;
perfstat_id_wpar_t wparid;
perfstat_psize_t psize;

psize.psize = FIRST_PSIZE;
/* Get the number of page sizes */

```

```

psizes = perfstat_memory_page_wpar(&wparid, NULL, NULL, sizeof(perfstat_memory_page_wpar_t),0);
/*check for error */
if (psizes <= 0 ){
    perror("perfstat_memory_page_wpar ");
    exit(-1);
}

/*Allocate enough memory to hold the structures */
pageinfo = (perfstat_memory_page_wpar_t *)calloc(psizes, sizeof(perfstat_memory_page_wpar_t));

/*check for memory allocation */
if (!pageinfo){
    perror("calloc");
    exit(-1);
}

/* call the API and get the data */
rc = perfstat_memory_page_wpar(NULL, &psize, pageinfo ,
sizeof(perfstat_memory_page_wpar_t), psizes);
/* check the return values for any error */
if (rc <= 0){
    perror("perfstat_memory_page_wpar ");
    exit(-1);
}

for(i=0;i<psizes;i++){
    printf("Page size in bytes=%lld\n",pageinfo[i].psize);
    printf("Number of real memory frames of this page size=%lld\n",pageinfo[i].real_total);
    printf("Number of pages pinned=%lld\n",pageinfo[i].real_pinned);
    printf("Number of pages in use=%lld\n",pageinfo[i].real_inuse);
    printf("Number of page faults=%lld\n",pageinfo[i].pgexct);
    printf("Number of pages paged in=%lld\n",pageinfo[i].pgins);
    printf("Number of pages paged out=%lld\n",pageinfo[i].pgouts);
    printf("Number of page ins from paging space=%lld\n",pageinfo[i].pgspins);
    printf("Number of page outs from paging space=%lld\n",pageinfo[i].pgspouts);
    printf("Number of page scans by clock=%lld\n",pageinfo[i].scans);
    printf("Number of page steals=%lld\n",pageinfo[i].pgsteals);
}
}

```

## RSET Interfaces

The RSET interface reports processor metrics related to an RSET.

All of the following AIX 6.1 RSET interfaces use the naming convention **perfstat\_subsystem[\_total]\_rset**, and use a common signature:

Item	Descriptor
<b>perfstat_cpu_total_rset</b>	Retrieves processor summary metrics of the processors in an RSET
<b>perfstat_cpu_rset</b>	Retrieves per processor metrics of the processors in an RSET

The signature used by the previous “perfstat\_memory\_page\_wpar Interface” on page 192 is as follows:

```

int perfstat_cpu_rset(perfstat_wpar_id_t *name,
                    perfstat_cpu_t * userbuff,
                    int sizeof_struct,
                    int desired_number);

int perfstat_cpu_total_rset(perfstat_wpar_id_t *name,
                           perfstat_cpu_total_t * userbuff,

```

```

    int sizeof_struct,
    int desired_number);

```

The usage of the parameters for all of the interfaces is as follows:

Item	Descriptor
<b>perfstat_id_wpar_t *name</b>	Specifies the RSET identifier and the name of the first component (for example, cpu0) for which statistics are desired. A structure containing the specifier, which can be an RSETHANDLE, WPARID, or WPARNAME, a union to specify the wpar ID, or wpar name or rsethandle and a char * field to specify the name of the first component. To start from the first component of a subsystem, set the char* field of the name parameter to "" (empty string). You can also use the macro FIRST_CPU defined in the libperfstat.h file.
<b>perfstat_cpu[_total]_t *userbuff</b>	A pointer to a memory area with enough space for the returned structures.
<b>int sizeof_struct</b>	Should be set to sizeof(perfstat_cpu[_total]_t).
<b>int desired_number</b>	The number of structures of type perfstat_cpu[_total]_t to return in userbuff.

The number of structures copied and returned without errors uses the return value of 1. If there are errors, the return value is -1. The field name is either set to NULL or to the name of the next structure available.

An exception to this scheme is when name=NULL, userbuff=NULL, and desired\_number=0, the total number of structures available is returned.

To retrieve all structures of a given type, either ask first for their number, allocate enough memory to hold them all at once, then call the appropriate API to retrieve them all in one call. Else, allocate a fixed set of structures and repeatedly call the API to get the next such number of structures, each time passing the name returned by the previous call. Start the process with the name set to "" or FIRST\_CPU, and repeat the process until the name returned is equal to "".

The following sections provide examples of the type of data returned and code using each of the interfaces.

### perfstat\_cpu\_rset interface

The **perfstat\_cpu\_rset** interface returns a set of structures of type **perfstat\_cpu\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_cpu\_t** structure include:

Item	Descriptor
<b>name</b>	Logical processor name (cpu0, cpu1, and so on)
<b>user</b>	Number of clock ticks spent in user mode
<b>sys</b>	Number of clock ticks spent in system (kernel) mode
<b>idle</b>	Number of clock ticks spent idle with no I/O pending
<b>wait</b>	Number of clock ticks spent idle with I/O pending
<b>syscall</b>	Number of system call executed

Several other paging-space-related metrics (such as number of forks, reads, writes, and execs) are also returned. For a complete list of other paging-space-related metrics, see the **perfstat\_cpu\_t** section in the **libperfstat.h** header file.

The following code shows an example of how **perfstat\_cpu\_rset** is used from the global environment:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    int i, retcode, rsetcpus;

```

```

perfstat_id_wpar_t wparid;
perfstat_cpu_t *statp;
wparid.spec = WPARNAME;
strcpy(wparid.u.wparname, NULL);

/* give the wparname "wpar1" as the identifier */
strcpy(wparid.u.wparname, "test");

/* check how many perfstat_cpu_t structures are available */
rsetcpus = perfstat_cpu_rset(&wparid, NULL, sizeof(perfstat_cpu_t), 0);

if (rsetcpus < 0 ){
    perror("perfstat_cpu_rset");
    exit(-1);
}

/*allocate memory for perfstat_cpu_t structures */
statp = (perfstat_cpu_t *)calloc(rsetcpus , sizeof(perfstat_cpu_t));

if(!statp){
    perror("calloc");
}

/*call the API and get the values */

retcode = perfstat_cpu_rset(&wparid, statp, sizeof(perfstat_cpu_t), rsetcpus);

if(retcode < 0){
    perror("perfstat_cpu_rset");
}

for(i=0;i<retcode;i++){
printf("Logical processor name=%s\n", statp[i].name);
printf("Raw number of clock ticks spent in user mode=%lld\n", statp[i].user);
printf("Raw number of clock ticks spent in system mode=%lld\n", statp[i].sys);
printf("Raw number of clock ticks spent in idle mode=%lld\n", statp[i].idle);
printf("Raw number of clock ticks spent in wait mode=%lld\n", statp[i].wait);
}
return 0;
}

```

The program displays an output that is similar to the following example output:

```

Logical processor name=cpu0
Raw number of clock ticks spent in user mode=2050
Raw number of clock ticks spent in system mode=22381
Raw number of clock ticks spent in idle mode=6863114
Raw number of clock ticks spent in wait mode=3002
Logical processor name=cpu1
Raw number of clock ticks spent in user mode=10
Raw number of clock ticks spent in system mode=651
Raw number of clock ticks spent in idle mode=6876627
Raw number of clock ticks spent in wait mode=42
Logical processor name=cpu2
Raw number of clock ticks spent in user mode=0
Raw number of clock ticks spent in system mode=610
Raw number of clock ticks spent in idle mode=6876712
Raw number of clock ticks spent in wait mode=0
Logical processor name=cpu3
Raw number of clock ticks spent in user mode=0
Raw number of clock ticks spent in system mode=710
Raw number of clock ticks spent in idle mode=6876612
Raw number of clock ticks spent in wait mode=0
Logical processor name=cpu4
Raw number of clock ticks spent in user mode=243
Raw number of clock ticks spent in system mode=1659
Raw number of clock ticks spent in idle mode=6875427

```

```

Raw number of clock ticks spent in wait mode=62
Logical processor name=cpu5
Raw number of clock ticks spent in user mode=0
Raw number of clock ticks spent in system mode=207327
Raw number of clock ticks spent in idle mode=6848952
Raw number of clock ticks spent in wait mode=0
Logical processor name=cpu6
Raw number of clock ticks spent in user mode=0
Raw number of clock ticks spent in system mode=207904
Raw number of clock ticks spent in idle mode=6849969
Raw number of clock ticks spent in wait mode=0
Logical processor name=cpu7
Raw number of clock ticks spent in user mode=0
Raw number of clock ticks spent in system mode=207375
Raw number of clock ticks spent in idle mode=6848209
Raw number of clock ticks spent in wait mode=0

```

The following code shows an example of how `perfstat_cpu_rset` is used from the WPAR environment:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    int i, retcode, rsetcpus;
    perfstat_id_wpar_t wparid;
    perfstat_cpu_t *statp;

    /* check how many perfstat_cpu_t structures are available */
    rsetcpus = perfstat_cpu_rset(NULL, NULL, sizeof(perfstat_cpu_t), 0);

    if (rsetcpus < 0 ){
        perror("perfstat_cpu_rset");
        exit(-1);
    }

    /*allocate memory for perfstat_cpu_t structures */
    statp = (perfstat_cpu_t *)calloc(rsetcpus , sizeof(perfstat_cpu_t));

    if(!statp){
        perror("calloc");
    }

    /*call the API and get the values */

    retcode = perfstat_cpu_rset(NULL, statp,sizeof(perfstat_cpu_t), rsetcpus);

    if(retcode < 0){
        perror("perfstat_cpu_rset");
    }

    for(i=0;i<retcode;i++){
        printf("Logical processor name=%s\n",statp[i].name);
        printf("Raw number of clock ticks spent in user mode=%lld\n",statp[i].user);
        printf("Raw number of clock ticks spent in system mode=%lld\n",statp[i].sys);
        printf("Raw number of clock ticks spent in idle mode=%lld\n",statp[i].idle);
        printf("Raw number of clock ticks spent in wait mode=%lld\n",statp[i].wait);
    }
    return 0;
}

```

### **perfstat\_cpu\_total\_rset interface**

The `perfstat_cpu_total_rset` interface returns a set of structures of type `perfstat_cpu_total_t`, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_cpu_t` structure include:

Item	Descriptor
processorHz	Processor speed in Hertz (from ODM)
description	Processor type (from ODM)
CPUs	Current number of active processors
ncpus_cfg	Number of configured processors (maximum number of processors that this copy of AIX can handle simultaneously)
ncpus_high	Maximum number of active processors; that is, the maximum number of active processors since the last reboot
User	Total number of clock ticks spent in user mode
Sys	Total number of clock ticks spent in system (kernel) mode
Idle	Total number of clock ticks spent idle with no I/O pending
Wait	Total number of clock ticks spent idle with I/O pending

Several other paging-space-related metrics (such as number of forks, read, writes, and execs) are also returned. For a complete list of other paging-space-related metrics, see the **perfstat\_cpu\_total\_t** section in the **libperfstat.h** header file.

The following code shows an example of how the **perfstat\_cpu\_total\_rset** interface is used from the global environment:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfstat_cpu_total_t *cpustats;
    perfstat_id_wpar_t wparid;
    int rc,i;
    wparid.spec = WPARNAME;

    rc = perfstat_cpu_total_rset(NULL,NULL,sizeof(perfstat_cpu_total_t),0);
    if (rc <= 0) {
        perror("perfstat_cpu_total_rset");
        exit(-1);
    }

    cpustats=calloc(rc,sizeof(perfstat_cpu_total_t));
    if(cpustats==NULL){
        perror("MALLOC error:");
        exit(-1);
    }

    strcpy(wparid.u.wparname,"test");
    rc = perfstat_cpu_total_rset(&wparid, cpustats, sizeof(perfstat_cpu_total_t), rc);

    if (rc <= 0) {
        perror("perfstat_cpu_total_rset");
        exit(-1);
    }
    for(i=0;i<rc;i++){
        printf("Number of active logical processors=%d\n",cpustats[i].ncpus);
        printf("Number of configured processors=%d\n",cpustats[i].ncpus_cfg);
        printf("Processor description=%s\n",cpustats[i].description);
        printf("Processor speed in Hz=%lld\n",cpustats[i].processorHZ);
        printf("Raw total number of clock ticks spent in user mode=%lld\n",cpustats[i].user);
        printf("Raw total number of clock ticks spent in system mode=%lld\n",cpustats[i].sys);
        printf("Raw total number of clock ticks spent idle=%lld\n",cpustats[i].idle);
        printf("Raw total number of clock ticks spent wait=%lld\n",cpustats[i].wait);
    }
    return 0;
}
```

The program produces output that is similar to the following output:

```

Number of active logical processors=8
Number of configured processors=8
Processor description=PowerPC_POWER7
Processor speed in Hz=3304000000
Raw total number of clock ticks spent in user mode=86400
Raw total number of clock ticks spent in system mode=30636100
Raw total number of clock ticks spent idle=2826632699
Raw total number of clock ticks spent wait=852000

```

The following code shows an example of how `perfstat_cpu_total_rset` is used from the WPAR environment:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfstat_cpu_total_t *cpustats;
    perfstat_id_wpar_t wparid;
    int rc,i;

    rc = perfstat_cpu_total_rset(NULL,NULL,sizeof(perfstat_cpu_total_t),0);
    if (rc <= 0) {
        perror("perfstat_cpu_total_rset");
        exit(-1);
    }

    cpustats=calloc(rc,sizeof(perfstat_cpu_total_t));
    if(cpustats==NULL){
        perror("MALLOC error:");
        exit(-1);
    }

    rc = perfstat_cpu_total_rset(NULL, cpustats, sizeof(perfstat_cpu_total_t), rc);

    if (rc <= 0) {
        perror("perfstat_cpu_total_rset");
        exit(-1);
    }
    for(i=0;i<rc;i++){
        printf("Number of active logical processors=%d\n",cpustats[i].ncpus);
        printf("Number of configured processors=%d\n",cpustats[i].ncpus_cfg);
        printf("Processor description=%s\n",cpustats[i].description);
        printf("Processor speed in Hz=%lld\n",cpustats[i].processorHZ);
        printf("Raw total number of clock ticks spent in user mode=%lld\n",cpustats[i].user);
        printf("Raw total number of clock ticks spent in system mode=%lld\n",cpustats[i].sys);
        printf("Raw total number of clock ticks spent idle=%lld\n",cpustats[i].idle);
        printf("Raw total number of clock ticks spent wait=%lld\n",cpustats[i].wait);
    }
    return 0;
}

```

## Cached metrics interfaces

Cached metrics interfaces are used when the system configuration changes to inform the `libperfstat` API that it must reset cached metrics, which consist of values that seldom change such as disk size or processor description.

The following table lists the metrics that are cached:

Object	Content	Sample value
<b>perfstat_cpu_total</b>	char cpu_description [IDENTIFIER_LENGTH] u_longlong_t processorHZ	PowerPC_POWER3375000000
<b>perfstat_diskadapter</b>	The list of disk adapters The number of disk adapters u_longlong_t size u_longlong_t free char description [IDENTIFIER_LENGTH]	scsi0, scsi1, ide0 3 17344 15296 Wide/Ultra-3 SCSI I/O Controller
<b>perfstat_pagingspace</b>	The list of paging spaces The number of paging spaces char automatic char type longlong_t lpsize longlong_t mbsize char hostname [IDENTIFIER_LENGTH] char filename [IDENTIFIER_LENGTH]	hd6 1 1 NFS_PAGING 16 512pompei or rootvg /var/tmp/nfsswap/swapfile1
<b>perfstat_disk</b>	char adapter [IDENTIFIER_LENGTH] char description [IDENTIFIER_LENGTH] char vname [IDENTIFIER_LENGTH] u_longlong_t sizeu_longlong_t free	scsi0 16 Bit LVD SCSI Disk Drive rootvg 17344 15296
<b>perfstat_diskpath</b>	char adapter [IDENTIFIER_LENGTH]	scsi0
<b>perfstat_netinterface</b>	char description [IDENTIFIER_LENGTH]	Standard Ethernet Network Interface
<b>perfstat_logicalvolume</b>	char description [IDENTIFIER_LENGTH]	Logical volume1
<b>perfstat_volumegroup</b>	char description [IDENTIFIER_LENGTH]	Volume group1

You can use the following AIX interfaces to refresh the cached metrics:

Interface	Purpose	Definition of interface
<b>perfstat_reset</b>	Resets every cached metric	void perfstat_reset (void);
<b>perfstat_partial_reset</b>	Resets selected cached metrics or resets the system's minimum and maximum counters for disks	void perfstat_partial_reset (char * name, u_longlong_t resetmask);

The usage of the parameters for all of the interfaces is as follows:

Parameter	Usage
char *name	Identifies the name of the component of the cached metric that must be reset from the <b>libperfstat</b> API cache. If the value of the parameter is NULL, this signifies all of the components.
u_longlong_t resetmask	Identifies the category of the component if the value of the <b>name</b> parameter is not NULL. The possible values are: <ul style="list-style-type: none"> <li>• FLUSH_CPUTOTAL</li> <li>• FLUSH_DISK</li> <li>• RESET_DISK_MINMAX</li> <li>• FLUSH_DISKADAPTER</li> <li>• FLUSH_DISKPATH</li> <li>• FLUSH_NETINTERFACE</li> <li>• FLUSH_PAGINGSPACE</li> <li>• FLUSH_LOGICALVOLUME</li> <li>• FLUSH_VOLUMEGROUP</li> </ul> If the value of the <b>name</b> parameter is NULL, the <b>resetmask</b> parameter value consists of a combination of values. For example: RESET_DISK_MINMAX FLUSH_CPUTOTAL FLUSH_DISK

## The perfstat\_reset interface

The **perfstat\_reset** interface resets every cached metric that is stored by the **libperfstat** API. It also resets the system's minimum and maximum counters related to disks and paths. To be more selective, it is advised to use the **perfstat\_partial\_reset** interface.

## perfstat\_partial\_reset Interface

The `perfstat_partial_reset` interface resets the specified cached metrics that are stored by the `libperfstat` API.

The `perfstat_partial_reset` interface can also reset the system's minimum and maximum counters related to disks and paths. The following table summarizes the various actions of the `perfstat_partial_reset` interface:

The resetmask value	Action taken when the value of name is NULL	Action taken when the value of name is not NULL and a single resetmask value is set
FLUSH_CPUTOTAL	Flushes the speed and description values in the <code>perfstat_cputotal_t</code> structure.	Error. The value of <code>errno</code> is set to <code>EINVAL</code> .
FLUSH_DISK	Flushes the description, adapter, size, free, and <code>vname</code> values in every <code>perfstat_disk_t</code> structure. Flushes the list of disk adapters. Flushes the size, free, and description values in every <code>perfstat_diskadapter_t</code> structure.	Flushes the description, adapter, size, free, and <code>vname</code> values in the specified <code>perfstat_disk_t</code> structure. Flushes the adapter value in every <code>perfstat_diskpath_t</code> structure that matches the disk name that is followed by the <code>_Path</code> identifier. Flushes the size, free, and description values of each <code>perfstat_diskadapter_t</code> structure that is linked to a path leading to the disk or to the disk itself.
RESET_DISK_MINMAX	Resets the following values in every <code>perfstat_diskadapter_t</code> structure: <ul style="list-style-type: none"> <li>• <code>wq_min_time</code></li> <li>• <code>wq_max_time</code></li> <li>• <code>min_rserv</code></li> <li>• <code>max_rserv</code></li> <li>• <code>min_wserv</code></li> <li>• <code>max_wserv</code></li> </ul>	Error. The value of <code>errno</code> is set to <code>ENOTSUP</code> .
FLUSH_DISKADAPTER	Flushes the list of disk adapters. Flushes the size, free, and description values in every <code>perfstat_diskadapter_t</code> structure. Flushes the adapter value in every <code>perfstat_diskpath_t</code> structure. Flushes the description and adapter values in every <code>perfstat_disk_t</code> structure.	Flushes the list of disk adapters. Flushes the size, free, and description values in every <code>perfstat_diskadapter_t</code> structure. Flushes the adapter value in every <code>perfstat_diskpath_t</code> structure. Flushes the description and adapter values in every <code>perfstat_disk_t</code> structure.
FLUSH_DISKPATH	Flushes the adapter value in every <code>perfstat_diskpath_t</code> structure.	Flushes the adapter value in the specified <code>perfstat_diskpath_t</code> structure.
FLUSH_PAGINGSPEACE	Flushes the list of paging spaces. Flushes the automatic, type, <code>lpsize</code> , <code>mbsize</code> , <code>hostname</code> , <code>filename</code> , and <code>vname</code> values in every <code>perfstat_pagingspace_t</code> structure.	Flushes the list of paging spaces. Flushes the automatic, type, <code>lpsize</code> , <code>mbsize</code> , <code>hostname</code> , <code>filename</code> , and <code>vname</code> values in the specified <code>perfstat_pagingspace_t</code> structure.
FLUSH_NETINTERFACE	Flushes the description value in every <code>perfstat_netinterface_t</code> structure.	Flushes the description value in the specified <code>perfstat_netinterface_t</code> structure.
FLUSH_LOGICALVOLUME	Flushes the description value in every <code>perfstat_logicalvolume_t</code> structure.	Flushes the description value in every <code>perfstat_logicalvolume_t</code> structure.
FLUSH_VOLUMEGROUP	Flushes the description value in every <code>perfstat_volumegroup_t</code> structure.	Flushes the description value in every <code>perfstat_volumegroup_t</code> structure.

You can see how to use the `perfstat_partial_reset` interface in the following example code:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(int argc, char *argv[]) {
    int i, retcode;
    perfstat_id_t diskname;
    perfstat_disk_t *statp;
```

```

/* set name of the disk */
strcpy(diskname.name, "hdisk0");

/* we will now reset global system min/max metrics
 * Be careful as this could interact with other programs.
 */
perfstat_partial_reset(NULL, RESET_DISK_MINMAX);

/* min/max values are now reset.
 * We can now wait for some time before checking the variation range.
 */
sleep(10);

retcode = perfstat_disk(NULL, NULL, sizeof(perfstat_disk_t), 0);
statp = calloc (retcode,sizeof(perfstat_disk_t));
/* get disk metrics - min/max counters illustrate variations during the
 * last 60 seconds unless someone else reset these
 * values in the meantime.
 */
retcode = perfstat_disk(&diskname, statp, sizeof(perfstat_disk_t), 1);

/* At this point, we assume the disk free part changes due to chfs for example */

/* if we get disk metrics here, the free field will be wrong as it was
 * cached by the libperfstat.
 */

/* That is why we reset cached metrics */
perfstat_partial_reset("hdisk0", FLUSH_DISK);

/* we can now get updated disk metrics */
retcode = perfstat_disk(&diskname, statp, sizeof(perfstat_disk_t), 1);

for(i=0;i<retcode;i++){
    printf("Name of the disk=%s\n",statp[i].name);
    printf("Disk description=%s\n",statp[i].description);
    printf("Volume group name=%s\n",statp[i].vgname);
    printf("Size of the disk=%lld\n",statp[i].size);
    printf("Free portion of the disk=%lld\n",statp[i].free);
    printf("Disk block size=%lld\n",statp[i].bsize);
}
}

```

The program displays an output that is similar to the following example output:

```

Name of the disk=hdisk0
Disk description=Virtual SCSI Disk Drive
Volume group name=rootvg
Size of the disk=25568
Free portion of the disk=18752
Disk block size=512

```

## Node interfaces

Node interfaces report metrics related to a set of components or individual components of a remote node in the cluster. The components include processors or memory, and individual components include a processor, network interface, or memory page of the remote node in the cluster.

The remote node must belong to one of the clusters of the current node, which uses the perfstat API.

The following node interfaces use the `perfstat_subsystem_node` as the naming convention and a common signature:

Item	Descriptor
<code>perfstat_cpu_node</code>	Retrieves the usage metrics of an individual processor on a remote node.
<code>perfstat_disk_node</code>	Retrieves the usage metrics of an individual disk on a remote node.
<code>perfstat_diskadapter_node</code>	Retrieves the adapter metrics of a disk on a remote node.
<code>perfstat_diskpath_node</code>	Retrieves the path metrics of a disk on a remote node.
<code>perfstat_logicalvolume_node</code>	Retrieves the usage metrics of a logical volume on a remote node.
<code>perfstat_memory_page_node</code>	Retrieves the usage metrics of a memory page size on a remote node.
<code>perfstat_netbuffer_node</code>	Retrieves the buffer allocation metrics of a network on a remote node.
<code>perfstat_netinterface_node</code>	Retrieves the interface metrics of a network on a remote size node.
<code>perfstat_pagingspace_node</code>	Retrieves the space metrics of a page on a remote node.
<code>perfstat_protocol_node</code>	Retrieves the protocol-related metrics of a network on a remote node.
<code>perfstat_tape_node</code>	Retrieves the usage metrics of a tape on a remote node.
<code>perfstat_volumegroup_node</code>	Retrieves the usage metrics of a volume group on a remote node.
<code>perfstat_cpu_total_node</code>	Retrieves the summary on the usage metrics of a processor on a remote node.
<code>perfstat_partition_total_node</code>	Retrieves the partition metrics on a remote node.
<code>perfstat_tape_total_node</code>	Retrieves the summary on the usage metrics of a tape on a remote node.
<code>perfstat_memory_total_node</code>	Retrieves the summary on the usage metrics of a memory on a remote node.
<code>perfstat_netinterface_total_node</code>	Retrieves the summary on the usage metrics of a network interface on a remote node.
<code>perfstat_disk_total_node</code>	Retrieves the summary on the usage metrics of a disk on a remote node.

The following common signature is used by the `perfstat_subsystem_node` interface except the `perfstat_memory_page_node` interface:

```
int perfstat_subsystem_node(perfstat_id_node_t *name,
perfstat_subsystem_t *userbuff,
int sizeof_struct,
int desired_number);
```

The following signature is used by the `perfstat_memory_page_node` interface:

```
int perfstat_memory_page_node(perfstat_id_node_t *name,
perfstat_psize_t *psize;
perfstat_subsystem_t *userbuff,
int sizeof_struct,
int desired_number);
```

The following table describes the usage of the parameters of the `perfstat_subsystem_node` interface:

Item	Descriptor
<code>perfstat_id_node_t *name</code>	Specify the name of the node in <code>name-&gt;u.nodenameformat</code> . The name must contain the name of the first component. For example, <code>hdisk2</code> for <code>perfstat_disk_node()</code> , where <code>hdisk 2</code> is the name of the disk for which you require the statistics. <b>Note:</b> When you specify a <code>nodename</code> , it must be initialized as <code>NODENAME</code> .
<code>perfstat_subsystem_t *userbuff</code>	Points to a memory area that has enough space for the returned structure.
<code>int sizeof_struct</code>	Sets this parameter to the size of <code>perfstat_subsystem_t</code> .
<code>int desired_number</code>	Specifies the number of structures of type <code>perfstat_subsystem_t</code> to return to a <code>userbuff</code> field.

The `perfstat_subsystem_node` interface return -1 value for error. Otherwise it returns the number of structures copied. The field `namename` is set to the name of the next available structure, and an exceptional case when `userbuff` equals `NULL` and `desired_number` equals `0`, the total number of structures available is returned.

The following example shows the usage of the `perfstat_disk_node` interface:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

#define INTERVAL_DEFAULT 2
#define COUNT_DEFAULT 10

int main(int argc, char* argv[])
{
    int i, ret, tot;
```

```

int interval = INTERVAL_DEFAULT, count = COUNT_DEFAULT;
int collect_remote_node_stats = 0;
char nodename[MAXHOSTNAMELEN];
perfstat_disk_t *statp;
perfstat_id_t first;
perfstat_id_node_t nodeid;

/* Process the arguments */
while ((i = getopt(argc, argv, "i:c:n:")) != EOF)
{
    switch(i)
    {
        case 'i': /* Interval */
            interval = atoi(optarg);
            if( interval <= 0 )
                interval = INTERVAL_DEFAULT;
            break;
        case 'c': /* Number of iterations */
            count = atoi(optarg);
            if( count <= 0 )
                count = COUNT_DEFAULT;
            break;
        case 'n': /* Node name in a cluster environment */
            strncpy(nodename, optarg, MAXHOSTNAMELEN);
            nodename[MAXHOSTNAMELEN-1] = '\0';
            collect_remote_node_stats = 1;
            break;
        default:
            /* Invalid arguments. Print the usage and terminate */
            fprintf(stderr, "usage: %s [-i <interval in seconds>] [-c <number of iterations>] [-n <node name in the cluster>]\n", argv[0]);
    }
}

if(collect_remote_node_stats)
{
    /* perfstat_config needs to be called to enable cluster statistics collection */
    ret = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    if( ret == -1 )
    {
        perror("cluster statistics collection is not available");
        exit(-1);
    }
}

/* check how many perfstat_disk_t structures are available */
if(collect_remote_node_stats)
{
    strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
    nodeid.spec = NODENAME;
    tot = perfstat_disk_node(&nodeid, NULL, sizeof(perfstat_disk_t), 0);
}
else
{
    tot = perfstat_disk(NULL, NULL, sizeof(perfstat_disk_t), 0);
}

/* check for error */
if( tot < 0 )
{
    perror("perfstat_disk");
    exit(-1);
}
if( tot == 0 )
{
    printf("No disks found\n");
    exit(-1);
}

/* allocate enough memory for all the structures */
statp = calloc(tot, sizeof(perfstat_disk_t));
if(statp==NULL){
printf("No sufficient memory\n");
exit(-1);
}

if(collect_remote_node_stats)
{
    /* Remember nodename is already set */
    /* Now set name to first interface */
    strcpy(nodeid.name, FIRST_DISK);

    /* ask to get all the structures available in one call */
    /* return code is number of structures returned */
    ret = perfstat_disk_node(&nodeid, statp,
        sizeof(perfstat_disk_t), tot);
}
else
{
    /* set name to first interface */
    strcpy(first.name, FIRST_DISK);

    /* ask to get all the structures available in one call */
    /* return code is number of structures returned */
    ret = perfstat_disk(&first, statp,
        sizeof(perfstat_disk_t), tot);
}

/* check for error */
if( ret <= 0 )
{
    perror("perfstat_disk");
    exit(-1);
}
}

```

```

/* print statistics for each of the disks */
for (i = 0; i < ret; i++) {
    printf("\nStatistics for disk : %s\n", statp[i].name);
    printf("-----\n");
    printf("description      : %s\n", statp[i].description);
    printf("volume group name    : %s\n", statp[i].vgname);
    printf("adapter name        : %s\n", statp[i].adapter);
    printf("size                : %llu MB\n", statp[i].size);
    printf("free space          : %llu MB\n", statp[i].free);
    printf("number of blocks read : %llu blocks of %llu bytes\n", statp[i].rblks, statp[i].bsize);
    printf("number of blocks written : %llu blocks of %llu bytes\n", statp[i].wblks, statp[i].bsize);
}

if(collect_remote_node_stats) {
    /* Now disable cluster statistics by calling perfstat_config */
    perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}
}

```

The program displays an output that is similar to the following example output:

```

Statistics for disk : hdisk0
-----
description      : Virtual SCSI Disk Drive
volume group name : rootvg
adapter name     : vscsi0
size            : 25568 MB
free space      : 19616 MB
number of blocks read : 315130 blocks of 512 bytes
number of blocks written : 228352 blocks of 512 bytes

```

The following program shows the usage of the **vmstat** command and an example of using the `perfstat_memory_total_node` interface to retrieve the virtual memory details of the remote node:

```

#include <stdio.h>
#include <libperfstat.h>

#define INTERVAL_DEFAULT 2
#define COUNT_DEFAULT 10

int main(int argc, char* argv[])
{
    perfstat_memory_total_t minfo;
    perfstat_id_node_t nodeid;
    char nodename[MAXHOSTNAMELEN];
    int interval = INTERVAL_DEFAULT, count = COUNT_DEFAULT;
    int collect_remote_node_stats = 0;
    int i, rc;

    /* Process the arguments */
    while ((i = getopt(argc, argv, "i:c:n:")) != EOF)
    {
        switch(i)
        {
            case 'i': /* Interval */
                interval = atoi(optarg);
                if (interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c': /* Number of iterations */
                count = atoi(optarg);
                if (count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'n': /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                collect_remote_node_stats = 1;
                break;
            default:
                /* Invalid arguments. Print the usage and end */
                fprintf(stderr, "usage: %s [-i <interval in seconds>] [-c <number of iterations>] [-n <node name in the cluster>]\n", argv[0]);
        }
    }

    if(collect_remote_node_stats)
    {
        /* perfstat_config needs to be called to enable cluster statistics collection */
        rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
        if (rc == -1)
        {
            perror("cluster statistics collection is not available");
            exit(-1);
        }
    }

    if(collect_remote_node_stats)
    {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        rc = perfstat_memory_total_node(&nodeid, &minfo, sizeof(perfstat_memory_total_t), 1);
    }
    else
    {
        rc = perfstat_memory_total(NULL, &minfo, sizeof(perfstat_memory_total_t), 1);
    }
}

```

```

if (rc != 1) {
    perror("perfstat_memory_total");
    exit(-1);
}
printf("Memory statistics\n");
printf("-----\n");
printf("real memory size          : %llu MB\n",
       minfo.real_total*4096/1024/1024);
printf("reserved paging space    : %llu MB\n",minfo.pgsp_rsvd);
printf("virtual memory size       : %llu MB\n",
       minfo.virt_total*4096/1024/1024);
printf("number of free pages      : %llu\n",minfo.real_free);
printf("number of pinned pages    : %llu\n",minfo.real_pinned);
printf("number of pages in file cache : %llu\n",minfo.numperm);
printf("total paging space pages    : %llu\n",minfo.pgsp_total);
printf("free paging space pages     : %llu\n", minfo.pgsp_free);
printf("used paging space          : %3.2f%\n",
       (float)(minfo.pgsp_total-minfo.pgsp_free)*100.0/
       (float)minfo.pgsp_total);
printf("number of paging space page ins : %llu\n",minfo.pgspins);
printf("number of paging space page outs : %llu\n",minfo.pgspouts);
printf("number of page ins         : %llu\n",minfo.pgins);
printf("number of page outs        : %llu\n",minfo.pgouts);

if(collect_remote_node_stats) {
    /* Now disable cluster statistics by calling perfstat_config */
    perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}
}

```

The program displays an output that is similar to the following example output:

```

Memory statistics
-----
real memory size          : 4096 MB
reserved paging space    : 512 MB
virtual memory size       : 4608 MB
number of free pages      : 768401
number of pinned pages    : 237429
number of pages in file cache : 21473
total paging space pages  : 131072
free paging space pages   : 128821
used paging space         : 1.72%
number of paging space page ins : 0
number of paging space page outs : 0
number of page ins       : 37301
number of page outs      : 9692

```

The `perfstat_cluster_total` interface is used to retrieve cluster statistics from the `perfstat_cluster_total_t` structure, which is defined in the `libperfstat.h` file. The following selected fields are from the `perfstat_cpu_total_t` structure:

Item	Descriptor
<b>name</b>	Specifies the name of the cluster.
<b>Type</b>	Specifies the set of bits that describes the cluster.
<b>num_nodes</b>	Specifies the number of nodes in the cluster.
<b>node_data</b>	Points to a memory area that describes the details of all the nodes.
<b>num_disks</b>	Specifies the number of disks in the cluster.
<b>disk_data</b>	Points to a memory area that describes the details of all the disks.

For a complete list of parameters related to the `perfstat_cluster_total_t` structure, see the `libperfstat.h` header file.

The following code example shows the usage of the `perfstat_cluster_total` interface:

```

#include <stdio.h>
#include <libperfstat.h>

typedef enum {
    DISPLAY_DEFAULT = 0,
    DISPLAY_NODE_DATA = 1,
    DISPLAY_DISK_DATA = 2
} display_t;

int main(int argc, char* argv[])
{

```

```

perfstat_cluster_total_t cstats;
perfstat_node_data_t *node_details;
perfstat_disk_data_t *disk_details;
perfstat_id_node_t nodeid;
display_t display = DISPLAY_DEFAULT;
int num_nodes;
int i, rc;

/* Process the arguments */
while ((i = getopt(argc, argv, "lnd")) != EOF)
{
    switch(i)
    {
        case 'n': /* Request to display node data */
            display |= DISPLAY_NODE_DATA;
            break;
        case 'd': /* Request to display disk data */
            display |= DISPLAY_DISK_DATA;
            break;
        case 'h': /* Print help message */
        default:
            /* Print the usage and end */
            fprintf(stderr, "usage: %s [-n] [-d]\n", argv[0]);
            exit(-1);
    }
}

/* perfstat_config needs to be called to enable cluster statistics collection */
rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
if (rc == -1)
{
    perror("cluster statistics collection is not available");
    exit(-1);
}

/* Collect cluster statistics */
strncpy(nodeid.u.nodename, FIRST_CLUSTERNAME, MAXHOSTNAMELEN);
nodeid.spec = CLUSTERNAME;
cstats.node_data = NULL; /* To indicate no interest in node details */
cstats.disk_data = NULL; /* To indicate no interest in disk details */
rc = perfstat_cluster_total(&nodeid, &cstats, sizeof(perfstat_cluster_total_t), 1);
if (rc == -1)
{
    perror("perfstat_cluster_total failed");
    exit(-1);
}
fprintf(stdout, "Cluster statistics\n");
fprintf(stdout, "-----\n");
fprintf(stdout, "Cluster Name : %s\n", cstats.name);
fprintf(stdout, "Cluster type : ");
if (cstats.type.b.is_local)
    fprintf(stdout, "LOCAL\n");
else if (cstats.type.b.is_zone)
    fprintf(stdout, "ZONE\n");
else if (cstats.type.b.is_link)
    fprintf(stdout, "LINK\n");
fprintf(stdout, "Number of nodes : %u\n", cstats.num_nodes);
fprintf(stdout, "Number of disks : %u\n", cstats.num_disks);

/* check if the user requested node data */
if(((display & DISPLAY_NODE_DATA) && (cstats.num_nodes > 0)) ||
    ((display & DISPLAY_DISK_DATA) && (cstats.num_disks > 0)))
{
    if(display & DISPLAY_NODE_DATA)
    {
        cstats.sizeof_node_data = sizeof(perfstat_node_data_t);
        /* Make sure you allocate at least cstats.num_nodes */
        /* Otherwise, perfstat_cluster_total() fails with ENOSPC */
        cstats.node_data = (perfstat_node_data_t *) malloc(cstats.sizeof_node_data * cstats.num_nodes);
        if(cstats.node_data == NULL)
        {
            perror("malloc failed for node_data");
            exit(-1);
        }
    }
    if(display & DISPLAY_DISK_DATA)
    {
        cstats.sizeof_disk_data = sizeof(perfstat_disk_data_t);
        /* Make sure you allocate at least cstats.num_disks */
    }
}

```

```

/* Otherwise, perfstat_cluster_total() fails with ENOSPC */
cstats.disk_data = (perfstat_disk_data_t *) malloc(cstats.sizeof_disk_data * cstats.num_disks);
if(cstats.disk_data == NULL)
{
    perror("malloc failed for disk_data");
    exit(-1);
}
}

rc = perfstat_cluster_total(&nodeid, &cstats, sizeof(perfstat_cluster_total_t), 1);
if (rc == -1)
{
    perror("perfstat_cluster_total failed");
    exit(-1);
}
if(display & DISPLAY_NODE_DATA)
{
    fprintf(stdout, "\nNode details:\n");
    fprintf(stdout, "-----\n");
    node_details = cstats.node_data;
    for (i = 0; i < cstats.num_nodes; i++, node_details++)
    {
        fprintf(stdout, "Node name : %s\n", node_details->name);
        fprintf(stdout, "Node shorthand id : %llu\n",
            node_details->shorthand_id);
        fprintf(stdout, "Status of the node : ");
        if (node_details->status.b.is_up)
            fprintf(stdout, "UP\n");
        else if (node_details->status.b.is_down)
            fprintf(stdout, "DOWN\n");
        fprintf(stdout, "Number of clusters the node is participating : %u\n", node_details->num_clusters);
        fprintf(stdout, "Number of zones the node is participating : %u\n", node_details->num_zones);
        fprintf(stdout, "Number of points of contact to the node : %u\n", node_details->num_points_of_contact);
        fprintf(stdout, "\n");
    }
}

if(display & DISPLAY_DISK_DATA)
{
    fprintf(stdout, "\nDisk details:\n");
    fprintf(stdout, "-----\n");
    disk_details = cstats.disk_data;
    for (i = 0; i < cstats.num_disks; i++, disk_details++)
    {
        fprintf(stdout, "Disk name : %s\n", disk_details->name);
        fprintf(stdout, "Status of the disk :");
        if (disk_details->status.b.is_found)
        {
            fprintf(stdout, " FOUND");
            if (disk_details->status.b.is_ready)
                fprintf(stdout, " | READY");
            else
                fprintf(stdout, " | NOT READY");
        }
        else
            fprintf(stdout, " NOT FOUND");
        fprintf(stdout, "\n");
        fprintf(stdout, "\n");
    }
}

/* Now disable cluster statistics by calling perfstat_config */
perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}

```

The `perfstat_node_list` interface is used to retrieve the list of nodes in the `perfstat_node_t` structure, which is defined in the `libperfstat.h` file. The following selected fields are from the `perfstat_node_t` structure:

Item	Descriptor
<b>nodeid</b>	Specifies the identifier of the node.
<b>nodename</b>	Specifies the name of the node.

The following code example shows the usage of the `perfstat_node_list` interface:

```
#include <stdio.h>
#include <libperfstat.h>

int main(int argc, char* argv[])
{
    perfstat_id_node_t nodeid;
    perfstat_node_t *node_list;
    int num_nodes;
    int i, rc;

    /* perfstat_config needs to be called to enable cluster statistics collection */
    rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
        exit(-1);
    }

    strncpy(nodeid.u.nodename, FIRST_CLUSTERNAME, MAXHOSTNAMELEN);
    nodeid.spec = CLUSTERNAME;
    num_nodes = perfstat_node_list(&nodeid, NULL, sizeof(perfstat_node_t), 0);
    if (num_nodes == -1)
    {
        perror("perfstat_node_list failed");
        exit(-1);
    }
    if (num_nodes == 0)
    {
        /* This cannot happen */
        fprintf(stdout, "No nodes in the cluster.\n");
        exit(-1);
    }
    node_list = (perfstat_node_t *) malloc(sizeof(perfstat_node_t) * num_nodes);
    num_nodes = perfstat_node_list(&nodeid, node_list, sizeof(perfstat_node_t), num_nodes);
    if (num_nodes == -1)
    {
        perror("perfstat_node_list failed");
        exit(-1);
    }
    fprintf(stdout, "Number of nodes : %d\n\n", num_nodes);
    for (i = 0; i < num_nodes; i++)
    {
        fprintf(stdout, "Node name : %s\n", node_list[i].nodename);
        fprintf(stdout, "Node id : %llu\n", node_list[i].nodeid);
        fprintf(stdout, "\n");
    }

    /* Now disable cluster statistics by calling perfstat_config */
    perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);

    return (0);
}
```

The `perfstat_cluster_disk` interface is used to retrieve the list of disks in the `perfstat_disk_data_t` structure. The `perfstat_cluster_disk` interface is defined in the `libperfstat.h` file.

The following example code shows the usage of the `perfstat_cluster_disk` subroutine:

```

#include <stdio.h>
#include <libperfstat.h>

typedef enum {
    DISPLAY_NODE_DATA = 1,
    DISPLAY_DISK_DATA = 2,
} display_t;

int main(int argc, char* argv[])
{
    perfstat_node_data_t *node_details;
    perfstat_disk_data_t *disk_details;
    perfstat_id_node_t nodeid;
    char nodename[MAXHOSTNAMELEN];
    display_t display = DISPLAY_DISK_DATA;
    int num_nodes;
    int i, rc, num_of_disks = 0;

    /* Process the arguments */
    while ((i = getopt(argc, argv, "n:d")) != EOF)
    {
        switch(i)
        {
            case 'n':                /* Request to display node data */
                display |= DISPLAY_NODE_DATA;
                strncpy(nodename,optarg,MAXHOSTNAMELEN);
                break;
            case 'd':                /* Request to display disk data */
                display |= DISPLAY_DISK_DATA;
                break;

            case 'h':                /* Print help message */
            default:
                /* Print the usage and terminate */
                fprintf(stderr, "usage: %s [-n <nodename>] [-d]\n", argv[0]);
                exit(-1);
        }
    }

    /* perfstat_config needs to be called to enable cluster statistics collection */
    rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
        exit(-1);
    }
    /*If Node details are specified pass that data as input to get the disk details
    for that node . Else pass FIRST_NODENAME */
    if (display & DISPLAY_NODE_DATA)
    {
        strncpy(nodeid.u.nodename,nodename,MAXHOSTNAMELEN);
    }
    else
        strncpy(nodeid.u.nodename, FIRST_NODENAME, MAXHOSTNAMELEN);

    nodeid.spec = NODENAME;
    /*Get the number of disks for that node */
    num_of_disks = perfstat_cluster_disk(&nodeid,NULL, sizeof(perfstat_disk_data_t), 0);
    if (num_of_disks == -1)
    {
        perror("perfstat_cluster_disk failed");
        exit(-1);
    }

    disk_details = (perfstat_disk_data_t *)calloc(num_of_disks,sizeof(perfstat_disk_data_t));
    /* collect all the disk data for the node */
    if(!disk_details){

```

```

    perror("calloc");
    exit(-1);
}
num_of_disks = perfstat_cluster_disk(&nodeid,disk_details,sizeof(perfstat_disk_data_t),num_of_disks);
fprintf(stdout, "Disk Details\n");
fprintf(stdout, "-----\n");
for(i = 0; i < num_of_disks; i++)
{
    fprintf(stdout,"Disk Name:%s\t UDID:%s\n",disk_details[i].name,disk_details[i].uuid);
}

/* Now disable cluster statistics by calling perfstat config */
perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
free(disk_details);
disk_details = NULL;
}

```

## Change history of the perfstat API

The following changes and additions have been made to the perfstat APIs.

### Interface changes

With the following filesets the **rblks** and **wblks** fields of **libperfstat** are represented by blocks of 512 bytes in the **perfstat\_disk\_total\_t**, **perfstat\_diskadapter\_t** and **perfstat\_diskpath\_t** structures, regardless of the actual block size used by the device for which metrics are being retrieved.

- **bos.perf.libperfstat 4.3.3.4**
- **bos.perf.libperfstat 5.1.0.50**
- **bos.perf.libperfstat 5.2.0.10**

### Interface additions

Review the specific interfaces that are available for a fileset.

The following interfaces were added in the **bos.perf.libperfstat 5.2.0** file set:

- **perfstat\_netbuffer**
- **perfstat\_protocol**
- **perfstat\_pagingspace**
- **perfstat\_diskadapter**
- **perfstat\_reset**

The **perfstat\_diskpath** interface was added in the **bos.perf.libperfstat 5.2.0.10** file set.

The **perfstat\_partition\_total** interface was added in the **bos.perf.libperfstat 5.3.0.0** file set.

The **perfstat\_partial\_reset** interface was added in the **bos.perf.libperfstat 5.3.0.10** file set.

The following interfaces were added in the **bos.perf.libperfstat 6.1.2** file set:

- **perfstat\_cpu\_total\_wpar**
- **perfstat\_memory\_total\_wpar**
- **perfstat\_cpu\_total\_rset**
- **perfstat\_cpu\_rset**
- **perfstat\_wpar\_total**
- **perfstat\_tape**
- **perfstat\_tape\_total**
- **perfstat\_memory\_page**

- `perfstat_memory_page_wpar`
- `perfstat_logicalvolume`
- `perfstat_volumegroup`
- `perfstat_config`

The following interfaces were added in the `bos.perf.libperfstat 6.1.6.0` file set:

- `perfstat_cpu_node`
- `perfstat_disk_node`
- `perfstat_diskadapter_node`
- `perfstat_diskpath_node`
- `perfstat_logicalvolume_node`
- `perfstat_memory_page_node`
- `perfstat_netbuffer_node`
- `perfstat_netinterface_node`
- `perfstat_protocol_node`
- `perfstat_volumegroup_node`
- `perfstat_cpu_total_node`
- `perfstat_disk_total_node`
- `perfstat_memory_total_node`
- `perfstat_netinterface_total_node`
- `perfstat_partition_total_node`
- `perfstat_tape_total_node`
- `perfstat_cluster_total`
- `perfstat_node_list`

The following interfaces were added in the `bos.perf.libperfstat 6.1.7.0` file set:

- `perfstat_hfistat`
- `perfstat_hfistat_window`

## Field additions

The following additions have been made to the specified file set levels.

### The `bos.perf.libperfstat 5.1.0.15` file set:

The following fields were added to `perfstat_cpu_total_t`:

```
u_longlong_t bread
u_longlong_t bwrite
u_longlong_t lread
u_longlong_t lwrite
u_longlong_t phread
u_longlong_t phwrite
```

Support for C++ was added in this file set level.

### The `bos.perf.libperfstat 5.1.0.25` file set:

The following fields were added to `perfstat_cpu_t`:

```
u_longlong_t bread
u_longlong_t bwrite
u_longlong_t lread
u_longlong_t lwrite
u_longlong_t phread
u_longlong_t phwrite
```

### The **bos.perf.libperfstat 5.2.0** file set:

The following fields were added to **perfstat\_cpu\_t**:

```
u_longlong_t iget
u_longlong_t namei
u_longlong_t dirblk
u_longlong_t msg
u_longlong_t sema
```

The **name** field which returns the logical processor name is now of the form *cpu0*, *cpu1*, instead of *proc0*, *proc1* as it was in previous releases.

The following fields were added to **perfstat\_cpu\_total\_t**:

```
u_longlong_t runocc
u_longlong_t swpocc
u_longlong_t iget
u_longlong_t namei
u_longlong_t dirblk
u_longlong_t msg
u_longlong_t sema
u_longlong_t rcvint
u_longlong_t xmtint
u_longlong_t mdmint
u_longlong_t tty_rawinch
u_longlong_t tty_caninch
u_longlong_t tty_rawoutch
u_longlong_t ksched
u_longlong_t koverf
u_longlong_t kexit
u_longlong_t rbread
u_longlong_t rcread
u_longlong_t rbwrt
u_longlong_t rcwrt
u_longlong_t traps
int ncpus_high
```

The following field was added to **perfstat\_disk\_t**:

```
char adapter[IDENTIFIER_LENGTH]
```

The following field was added to **perfstat\_netinterface\_t**:

```
u_longlong_t bitrate
```

The following fields were added to **perfstat\_memory\_total\_t**:

```
u_longlong_t real_system
u_longlong_t real_user
u_longlong_t real_process
```

The following defines were added to **libperfstat.h**:

```
#define FIRST_CPU      ""
#define FIRST_DISK    ""
#define FIRST_DISKADAPTER ""
#define FIRST_NETINTERFACE ""
#define FIRST_PAGINGSPACE ""
#define FIRST_PROTOCOL ""
#define FIRST_ALLOC    ""
```

### The **bos.perf.libperfstat 5.2.0.10** file set:

The following field was added to the **perfstat\_disk\_t** interface:

```
uint paths_count
```

The following define was added to **libperfstat.h**:

```
#define FIRST_DISKPATH ""
```

### The `bos.perf.libperfstat 5.3.0.0` file set:

The following fields were added to the `perfstat_cpu_t` interface:

```
u_longlong_t puser
u_longlong_t psyss
u_longlong_t pidle
u_longlong_t pwait
u_longlong_t redisp_sd0
u_longlong_t redisp_sd1
u_longlong_t redisp_sd2
u_longlong_t redisp_sd3
u_longlong_t redisp_sd4
u_longlong_t redisp_sd5
u_longlong_t migration_push
u_longlong_t migration_S3grq
u_longlong_t migration_S3pul
u_longlong_t invol_cswitch
u_longlong_t vol_cswitch
u_longlong_t runque
u_longlong_t bound
u_longlong_t decrintrs
u_longlong_t mpcrintrs
u_longlong_t mpcsintrs
u_longlong_t devintrs
u_longlong_t softintrs
u_longlong_t phantintrs
```

The following fields were added to the `perfstat_cpu_total_t` interface:

```
u_longlong_t puser
u_longlong_t psys
u_longlong_t pidle
u_longlong_t pwait
u_longlong_t decrintrs
u_longlong_t mpcrintrs
u_longlong_t mpcsintrs
u_longlong_t phantintrs
```

### The `bos.perf.libperfstat 5.3.0.10` file set:

The following fields were added to both the `perfstat_disk_t` and `perfstat_diskpath_t` interfaces:

```
u_longlong_t q_full
u_longlong_t rserv
u_longlong_t rtimeout
u_longlong_t rfailed
u_longlong_t min_rserv
u_longlong_t max_rserv
u_longlong_t wserv
u_longlong_t wtimeout
u_longlong_t wfailed
u_longlong_t min_wserv
u_longlong_t max_wserv
u_longlong_t wq_depth
u_longlong_t wq_sampled
u_longlong_t wq_time
u_longlong_t wq_min_time
u_longlong_t wq_max_time
u_longlong_t q_sampled
```

In addition, the `xrate` field in the following data structures has been renamed to `_rxfers` and contains the number of read transactions when used with selected device drivers or zero:

```
perfstat_disk_t
perfstat_disk_total_t
perfstat_diskadapter_t
perfstat_diskpath_t
```

The following definitions were added to the **libperfstat.h** header file:

```
#define FLUSH_CPUOTOTAL
#define FLUSH_DISK
#define RESET_DISK_MINMAX
#define FLUSH_DISKADAPTER
#define FLUSH_DISKPATH
#define FLUSH_PAGINGSPACE
#define FLUSH_NETINTERFACE
```

#### The **bos.perf.libperfstat 5.3.0.50** file set:

The following fields were added to **perfstat\_partition\_total\_t**:

```
u_longlong_t reserved_pages
u_longlong_t reserved_pagesize
```

#### The **bos.perf.libperfstat 5.3.0.60** file set:

The following fields were added to **perfstat\_cpu\_t**, **perfstat\_cpu\_total\_t** and **perfstat\_partition\_total\_t**:

```
u_longlong_t idle_donated_purr
u_longlong_t idle_donated_spurr
u_longlong_t busy_donated_purr
u_longlong_t busy_donated_spurr
u_longlong_t idle_stolen_purr
u_longlong_t idle_stolen_spurr
u_longlong_t busy_stolen_purr
u_longlong_t busy_stolen_spurr
```

The following flags were added to **perfstat\_partition\_type\_t**:

```
unsigned donate_capable
unsigned donate_enabled
```

#### The **bos.perf.libperfstat 6.1.6.0** file set:

The following field is added to all existing interfaces:

```
u_longlong_t version
```

## Structure additions

Review the specific structure additions that are available for different file sets.

The following structures are added in the **bos.perf.libperfstat 6.1.2.0** file set:

```
perfstat_cpu_total_wpar_t
perfstat_cpu_total_rset_t
perfstat_cpu_rset_t
perfstat_wpar_total_t
perfstat_tape_t
perfstat_tape_total_t
perfstat_memory_page_t
perfstat_memory_page_wpar_t
perfstat_logicalvolume_t
perfstat_volumegroup_t
```

The following structures are added in the **bos.perf.libperfstat 6.1.6.0** file set:

```
perfstat_id_node_t
perfstat_node_t
perfstat_cluster_total_t
perfstat_cluster_type_t
perfstat_node_data_t
perfstat_disk_data_t
perfstat_disk_status_t
perfstat_ip_addr_t
```

The following structures are added in the **bos.perf.libperfstat 6.1.7.0** file set:

## Kernel tuning

You can make permanent kernel-tuning changes without having to edit any **rc** files. This is achieved by centralizing the reboot values for all tunable parameters in the **/etc/tunables/nextboot** stanza file. When a system is rebooted, the values in the **/etc/tunables/nextboot** file are automatically applied.

The following commands are used to manipulate the **nextboot** file and other files containing a set of tunable parameter values:

- The **tunchange** command is used to change values in a stanza file.
- The **tunsave** command is used to save values to a stanza file.
- The **tunrestore** is used to apply a file; that is, to change all tunables parameter values to those listed in a file.
- The **tuncheck** command must be used to validate a file created manually.
- The **tundefault** is available to reset tunable parameters to their default values.

The preceding commands work on both current and reboot values.

All six tuning commands (**no**, **nfso**, **vmo**, **ioo**, **raso**, and **schedo**) use a common syntax and are available to directly manipulate the tunable parameter values. Available options include making permanent changes and displaying detailed help on each of the parameters that the command manages. A large majority of tunable parameter values are not modifiable when the login session is initiated outside of the global WPAR partition. Attempts to modify such a read only tunable parameter value is refused by the command and a diagnostic message written to standard error output.

SMIT panels and Web-based System Manager plug-ins are also available to manipulate current and reboot values for all tuning parameters, as well as the files in the **/etc/tunables** directory.

### Related information:

bosboot command

no command

tunables command

## Migration and compatibility

When machines are migrated from a previous release of AIX, the tuning commands are automatically set to run in compatibility mode.

Most of the information in this section does not apply to compatibility mode. For more information, see compatibility mode in *Files Reference*.

When a machine is initially installed with AIX, it is automatically set to run in the tuning mode, which is described in this chapter. The tuning mode is controlled by the **sys0** attribute called **pre520tune**, which can be set to enable to run in compatibility mode and disable to run in the tuning mode.

To retrieve the current setting of the **pre520tune** attribute, run the following command:

```
lsattr -E -l sys0
```

To change the current setting of the **pre520tune** attribute, run the following command:

```
chdev -l sys0 -a pre520tune=enable
```

OR

use SMIT or Web-based System Manager.

## Tunables file directory

Information about tunable parameter values is located in the `/etc/tunables` directory. Except for a log file created during each reboot, this directory only contains ASCII stanza files with sets of tunable parameters.

These files contain **parameter=value** pairs specifying tunable parameter changes, classified in six stanzas corresponding to the six tuning commands : **schedo**, **vmo**, **ioo**, **no**, **raso**, and **nfso**. Additional information about the level of AIX, when the file was created, and a user-provided description of file usage is stored in a special stanza in the file. For detailed information on the file's format, see the **tunables** file.

The main file in the tunables directory is called **nextboot**. It contains all the tunable parameter values to be applied at the next reboot. The **lastboot** file in the tunables directory contains all the tunable values that were set at the last machine reboot, a *timestamp* for the last reboot, and *checksum* information about the matching **lastboot.log** file, which is used to log any changes made, or any error messages encountered, during the last rebooting. The **lastboot** and **lastboot.log** files are set to be read-only and are owned by the root user, as are the directory and all of the other files.

Users can create as many `/etc/tunables` files as needed, but only the **nextboot** file is ever automatically applied. Manually created files must be validated using the **tuncheck** command. Parameters and stanzas can be missing from a file. Only tunable parameters present in the file will be changed when the file is applied with the **tunrestore** command. Missing tunables will simply be left at their current or default values. To force resetting of a tunable to its default value with **tunrestore** (presumably to force other tunables to known values, otherwise **tundefault**, which sets all parameters to their default value, could have been used), **DEFAULT** can be specified. Specifying **DEFAULT** for a tunable in the **nextboot** file is the same as not having it listed in the file at all because the reboot tuning procedure enforces default values for missing parameters. This will guarantee to have all tunables parameters set to the values specified in the **nextboot** file after each reboot.

Tunable files can have a special stanza named **info** containing the parameters **AIX\_level**, **Kernel\_type** and **Last\_validation**. Those parameters are automatically set to the level of AIX and to the type of kernel (MP64) running when the **tuncheck** or **tunsave** is run on the file. Both commands automatically update those fields. However, the **tuncheck** command will only update if no error was detected.

The **lastboot** file always contains values for every tunable parameters. Tunables set to their default value will be marked with the comment **DEFAULT VALUE**. Restricted tunables modified from their default value are marked, after the value, with an additional comment **# RESTRICTED not at default value**. The **Logfile\_checksum** parameter only exists in that file and is set by the tuning reboot process (which also sets the rest of the info stanza) after closing the log file.

Tunable files can be created and modified using one of the following options:

- Using SMIT or Web-based System Manager, to modify the next reboot value for tunable parameters, or to ask to save all current values for next boot, or to ask to use an existing tunable file at the next reboot. All those actions will update the `/etc/tunables/nextboot` file. A new file in the `/etc/tunables` directory can also be created to save all current or all **nextboot** values.
- Using the tuning commands (**ioo**, **raso**, **vmo**, **schedo**, **no** or **nfso**) with the **-p** or **-r** options, which will update the `/etc/tunables/nextboot` file.
- A new file can also be created directly with an editor or copied from another machine. Running **tuncheck [-r | -p] -f** must then be done on that file.
- Using the **tunsave** command to create or overwrite files in the `/etc/tunables` directory
- Using the **tunrestore -r** command to update the **nextboot** file.

## Tunable parameters type

The manual page for each of the six tuning commands contains the complete list of all the parameter manipulated by each of the commands and for each parameter, its type, range, default value, and any dependencies on other parameters.

All the tunable parameters manipulated by the tuning commands (**no**, **nfso**, **vmo**, **ioo**, **raso**, and **schedo**) have been classified into the following categories:

- **Dynamic**: if the parameter can be changed at any time
- **Static**: if the parameter can never be changed
- **Reboot**: if the parameter can only be changed during reboot
- **Bosboot**: if the parameter can only be changed by running **bosboot** and rebooting the machine
- **Mount**: if changes to the parameter are only effective for future file systems or directory mounts
- **Incremental**: if the parameter can only be incremented, except at boot time
- **Connect**: if changes to the parameter are only effective for future socket connections
- **Deprecated**: if changing this parameter is no longer supported by the current release of AIX

For parameters of type **Bosboot**, whenever a change is performed, the tuning commands automatically prompt the user to ask if they want to execute the **bosboot** command. When specifying a restricted tunable for modification in association with the option **-p** or **-r**, you are also prompted to confirm the change. For parameters of type **Connect**, the tuning commands automatically restart the **inetd** daemon.

The tunables classified as restricted use tunables exist primarily for specialized intervention by the support or development teams and are not recommended for end user modification. For this reason, they are not displayed by default and require the force option on the command line. When modifying a restricted tunable, a warning message is displayed and confirmation required if the change is specified for reboot or permanent.

## Common syntax for tuning commands

Review the syntax for all the tuning commands.

The **no**, **nfso**, **vmo**, **ioo**, **raso**, and **schedo** tuning commands all support the following syntax:

```
command [-p|-r] {-o tunable[=newvalue]}
command [-p|-r] {-d tunable}
command [-p|-r] -D
command [-p|-r] [-F]-a
command -h [tunable]
command [-F] -L [tunable]
command [-F] -x [tunable]
```

The flags of the tuning command are:

Item	Descriptor
<b>-a</b>	Displays current, reboot (when used in conjunction with <b>-r</b> ) or permanent (when used in conjunction with <b>-p</b> ) value for all tunable parameters, one per line in pairs <code>tunable = value</code> . For the permanent options, a value is displayed for a parameter only if its reboot and current values are equal. Otherwise, <b>NONE</b> is displayed as the value. If a tunable is not supported by the running kernel or the current platform, "n/a" is displayed as the value.
<b>-d tunable</b>	Resets <code>tunable</code> to default value. If a tunable needs to be changed (that is, it is currently not set to its default value) and is of type <b>Bosboot</b> or <b>Reboot</b> , or if it is of type <b>Incremental</b> and has been changed from its default value, and <b>-r</b> is not used in combination, it is not changed, but a message displays instead.
<b>-D</b>	Resets all tunables to their default value. If tunables needing to be changed are of type <b>Bosboot</b> or <b>Reboot</b> , or are of type <b>Incremental</b> and have been changed from their default value, and <b>-r</b> is not used in combination, they are not changed, but a message displays instead.
<b>-F</b>	Forces display of restricted tunable parameters when the options <b>-a</b> , <b>-L</b> , or <b>-x</b> are specified alone on the command line to list all tunables. When <b>-F</b> is not specified, restricted tunables are not included in a display unless specifically named in association with a display option.

The flags of the tuning command are:

Item	Descriptor
<b>-h</b> [ <i>tunable</i> ]	Displays help about tunable parameter. Otherwise, displays the command usage statement.
<b>-o</b> <i>tunable</i> [= <i>newvalue</i> ]	Displays the value or sets <i>tunable</i> to <i>newvalue</i> . If a tunable needs to be changed (the specified value is different than current value), and is of type <b>Bosboot</b> or <b>Reboot</b> , or if it is of type Incremental and its current value is bigger than the specified value, and <b>-r</b> is not used in combination, it is not changed, but a message displays instead.  When <b>-r</b> is used in combination without a new value, the <b>nextboot</b> value for <i>tunable</i> is displayed. When <b>-p</b> is used in combination without a new value, a value is displayed only if the current and next boot values for <i>tunable</i> are the same. Otherwise, NONE is displayed as the value. If a tunable is not supported by the running kernel or the current platform, "n/a" is displayed as the value.
<b>-p</b>	When used in combination with <b>-o</b> , <b>-d</b> or <b>-D</b> , makes changes apply to both current and reboot values; that is, turns on the updating of the <b>/etc/tunables/nextboot</b> file in addition to the updating of the current value. This flag cannot be used on <b>Reboot</b> and <b>Bosboot</b> type parameters because their current value cannot be changed.  When used with <b>-a</b> or <b>-o</b> flag without specifying a new value, values are displayed only if the current and next boot values for a parameter are the same. Otherwise, NONE is displayed as the value.
<b>-r</b>	When used in combination with <b>-o</b> , <b>-d</b> or <b>-D</b> flags, makes changes apply to reboot values only; that is, turns on the updating of the <b>/etc/tunables/nextboot</b> file. If any parameter of type <b>Bosboot</b> is changed, the user will be prompted to run <b>bosboot</b> .  When used with <b>-a</b> or <b>-o</b> without specifying a new value, next boot values for tunables are displayed instead of current values.
<b>-x</b> [ <i>tunable</i> ]	Lists the characteristics of one or all tunables, one per line, using the following format: tunable,current,default,reboot, min,max,unit,type,{dtunable }

where:

```

current = current value
default = default value
reboot = reboot value
min = minimal value
max = maximum value
unit = tunable unit of measure
type = parameter type: D(for Dynamic), S(for Static),
                    R(for Reboot), B(for Bosboot), M(for Mount),
                    I(for Incremental), C (for Connect), and
                    d (for Deprecated)
dtunable = space separated list of dependent tunable
           parameters

```

**-L** [*tunable*] Lists the characteristics of one or all tunables, one per line, using the following format:

NAME	CUR	DEF	BOOT	MIN	MAX	UNIT	TYPE
DEPENDENCIES							
-----	-----	-----	-----	-----	-----	-----	-----
memory_frames	128K	128K				4KB pages	S
-----	-----	-----	-----	-----	-----	-----	-----
maxfree	128	128	128	16	200K	4KB pages	D
minfree							
memory_frames							
-----	-----	-----	-----	-----	-----	-----	-----

where:

```

CUR = current value
DEF = default value
BOOT = reboot value
MIN = minimal value
MAX = maximum value
UNIT = tunable unit of measure
TYPE = parameter type: D (for Dynamic),S (for Static),
                    R (for Reboot),B (for Bosboot),
                    M (for Mount), I (for Incremental),
                    C (for Connect), and d (for Deprecated)
DEPENDENCIES = list of dependent tunable parameters,
              one per line

```

Any change (with **-o**, **-d** or **-D**) to a restricted tunable parameter will result in a message being displayed to warn the user that a tunable of the restricted use type has been modified and, if the **-r** or **-p** options are also specified on the command line, the user will be prompted for confirmation of the change. In addition, at system reboot, the presence of restricted tunables modified to a value different from their default using a command line specifying the **-r** or **-p** options will cause the addition of an error log entry identifying the list of these modified tunables.

Any change (with **-o**, **-d** or **-D** flags) to a parameter of type **Mount** will result in a message displays to warn the user that the change is only effective for future mountings.

Any change (with **-o**, **-d** or **-D** flags) to a parameter of type **Connect** will result in the **inetd** daemon being restarted, and a message will display to warn the user that the change is only effective for socket connections.

Any attempt to change (with **-o**, **-d** or **-D** flags ) a parameter of type **Bosboot** or **Reboot** without **-r**, will result in an error message.

Any attempt to change (with **-o**, **-d** or **-D** flags but without **-r**) the current value of a parameter of type **Incremental** with a new value smaller than the current value, will result in an error message.

## Tunable file-manipulation commands

The following commands normally manipulate files in the **/etc/tunables** directory, but the files can be located anywhere. Therefore, as long as the file name does not contain a forward slash (/), all the file names specified are expanded to **/etc/tunables/filename**.

To guarantee the consistency of their content, all the files are locked before any updates are made. The commands **tunsave**, **tuncheck** (only if successful), and **tundefault -r** all update the info stanza.

### tunchange Command

The **tunchange** command is used to update one or more tunable stanzas in a file.

The following is the syntax for the **tunchange** command:

```
tunchange -f filename ( -t stanza ( {-o parameter[=value]} | -D ) | -m filename2 )
```

where stanza is **schedo**, **vmo**, **ioo**, **raso**, **no**, or **nfso**.

The following is an example of how to update the **pacefork** parameter in the **/etc/tunables/mytunable** directory:

```
tunchange -f mytunable -t schedo -o pacefork=10
```

The following is an example of how to unconditionally update the **pacefork** parameter in the **/etc/tunables/nextboot** directory. This should be done with caution because no warning will be printed if a parameter of type **bosboot** was changed.

```
tunchange -f nextboot -t schedo -o pacefork=10
```

The following is an example of how to clear the **schedo** stanza in the **nextboot** file.

```
tunchange -f nextboot -t schedo -D
```

The following is an example of how to merge the **/home/admin/schedo\_conf** file with the current **nextboot** file. If the file to merge contains multiple entries for a parameter, only the first entry will be applied. If both files contain an entry for the same tunable, the entry from the file to merge will replace the current **nextboot** file's value.

```
tunchange -f nextboot -m /home/admin/schedo_conf
```

The **tunchange** command is called by the tuning commands to implement the **-p** and **-r** flags using **-f nextboot**.

## tuncheck Command

The **tuncheck** command is used to validate a file.

The following is the syntax for the **tuncheck** command:

```
tuncheck [-r|-p] -f filename
```

The following is an example of how to validate the **/etc/tunables/mytunable** file for usage on current values.

```
tuncheck -f mytunable
```

The following is an example of how to validate the **/etc/tunables/nextboot** file or **my\_nextboot** file for usage during reboot. Note that the **-r** flag is the only valid option when the file to check is the **nextboot** file.

```
tuncheck -r -f nextboot
```

```
tuncheck -r -f /home/bill/my_nextboot
```

All parameters in the **nextboot** or **my\_nextboot** file are checked for range, and dependencies, and if a problem is detected, a message similar to: "Parameter X is out of range" or "Dependency problem between parameter A and B" is issued. The **-r** and **-p** options control the values used in dependency checking for parameters not listed in the file and the handling of proposed changes to parameters of type **Incremental**, **Bosboot**, and **Reboot**.

Except when used with the **-r** option, checking is performed on parameter of type **Incremental** to make sure the value in the file is not less than the current value. If one or more parameters of type **Bosboot** are listed in the file with a different value than its current value, the user will either be prompted to run **bosboot** (when **-r** is used) or an error message will display.

Parameters having dependencies are checked for compatible values. When one or more parameters in a set of interdependent parameters is not listed in the file being checked, their values are assumed to either be set at their current value (when the **tuncheck** command is called without **-p** or **-r**), or their default value. This is because when called without **-r**, the file is validated to be applicable on the current values, while with **-r**, it is validated to be used during reboot when parameters not listed in the file will be left at their default value. Calling this command with **-p** is the same as calling it twice; once with no argument, and once with the **-r** flag. This checks whether a file can be used both immediately, and at reboot time.

**Note:** Users creating a file with an editor, or copying a file from another machine, must run the **tuncheck** command to validate their file.

## tunrestore Command

The **tunrestore** command is used to restore all the parameters from a file.

The following is the syntax for the **tunrestore** command:

```
tunrestore -R | [-r] -f filename
```

For example, the following will change the current values for all tunable parameters present in the file if ranges, dependencies, and incremental parameter rules are all satisfied.

```
tunrestore -f mytunable
```

```
tunrestore -f /etc/tunables/mytunable
```

In case of problems, only the changes possible will be made.

For example, the following will change the **reboot** values for all tunable parameters present in the file if ranges and dependencies rules are all satisfied. In other words, they will be copied to the **/etc/tunables/nextboot** file.

```
tunrestore -r -f mytunable
```

If changes to parameters of type **Bosboot** are detected, the user will be prompted to run the **bosboot** command.

The following command can only be called from the **/etc/inittab** file and changes tunable parameters to values from the **/etc/tunables/nextboot** file.

```
tunrestore -R
```

Any problem found or change made is logged in the **/etc/tunables/lastboot.log** file. A new **/etc/tunables/lastboot** file is always created with the list of current values for all parameters. Any change to restricted tunables from their default values will cause the addition of an error log entry identifying the list of these modified tunables.

If *filename* does not exist, an error message displays. If the **nextboot** file does not exist, an error message displays if **-r** was used. If **-R** was used, all the tuning parameters of a type other than **Bosboot** will be set to their default value, and a **nextboot** file containing only an info stanza will be created. A warning will also be logged in the **lastboot.log** file.

Except when **-r** is used, parameters requiring a call to **bosboot** and a **reboot** are not changed, but an error message is displayed to indicate they could not be changed. When **-r** is used, if any parameter of type **Bosboot** needs to be changed, the user will be prompted to run **bosboot**. Parameters missing from the file are simply left unchanged, except when **-R** is used, in which case missing parameters are set to their default values. If the file contains multiple entries for a parameter, only the first entry will be applied, and a warning will be displayed or logged (if called with **-R**).

## tunsave Command

The **tunsave** command is used to save current tunable parameter values into a file.

The following is the syntax for the **tunsave** command:

```
tunsave [-a|-A] -f|-F filename
```

For example, the following saves all of the current tunable parameter values that are different from their default into the **/etc/tunables/mytunable** file.

```
tunsave -f mytunable
```

If the file already exists, an error message is printed instead. The **-F** flag must be used to overwrite an existing file.

For example, the following saves all of the current tunable parameter values different from their default into the **/etc/tunables/nextboot** file.

```
tunsave -f nextboot
```

If necessary, the **tunsave** command will prompt the user to run **bosboot**.

For example, the following saves all of the current tunable parameters values (including parameters for which default is their value) into the **mytunable** file.

```
tunsave -A -f mytunable
```

This permits you to save the current setting. This setting can be reproduced at a later time, even if the default values have changed (default values can change when the file is used on another machine or when running another version of AIX).

For example, the following saves all current tunable parameter values into the `/etc/tunables/mytunable` file or the **mytunable** file in the current directory.

```
tunsave -a -f mytunable
```

```
tunsave -a -f ./mytunable
```

For the parameters that are set to default values, a line using the keyword `DEFAULT` will be put in the file. This essentially saves only the current changed values, while forcing all the other parameters to their default values. This permits you to return to a known setup later using the **tunrestore** command.

## tundefault Command

The **tundefault** command is used to force all tuning parameters to be reset to their default value. The **-p** flag makes changes permanent, while the **-r** flag defers changes until the next reboot.

The following is the syntax for the **tundefault** command:

```
tundefault [-p|-r]
```

For example, the following example resets all tunable parameters to their default value, except the parameters of type **Bosboot** and **Reboot**, and parameters of type **Incremental** set at values bigger than their default value.

```
tundefault
```

Error messages will be displayed for any parameter change that is not permitted.

For example, the following example resets all the tunable parameters to their default value. It also updates the `/etc/tunables/nextboot` file, and if necessary, offers to run **bosboot**, and displays a message warning that rebooting is needed for all the changes to be effective.

```
tundefault -p
```

This command permanently resets *all* tunable parameters to their default values, returning the system to a consistent state and making sure the state is preserved after the next reboot.

For example, the following example clears all the command stanzas in the `/etc/tunables/nextboot` file, and proposes **bosboot** if necessary.

```
tundefault -r
```

## Initial setup

Installing the **bos.perf.tune** fileset automatically creates an initial `/etc/tunables/nextboot` file.

When you install the **bos.perf.tune** fileset the following line is added at the beginning of the `/etc/inittab` file:

```
tunable:23456789:wait:/usr/bin/tunrestore -R > /dev/console 2>&1
```

This entry sets the **reboot** value of all tunable parameters to their default. For more information about migration from a previous version of AIX and the compatibility mode automatically setup in case of migration, see the *Files Reference* guide.

## Reboot tuning procedure

Parameters of type **Bosboot** are set by the **bosboot** command, which retrieves their values from the `nextboot` file when creating a new boot image.

Parameters of type **Reboot** are set during the reboot process by the appropriate configuration methods, which also retrieve the necessary values from the **nextboot** file. In both cases, if there is no **nextboot** file, the parameters will be set to their default values. All other parameters are set using the following process:

1. When **tunrestore -R** is called, any tunable changed from its default value is logged in the **lastboot.log** file. The parameters of type **Reboot** and **Bosboot** present in the **nextboot** file, and which should already have been changed by the time **tunrestore -R** is called, will be checked against the value in the file, and any difference will also be logged.
2. The **lastboot** file will record all the tunable parameter settings, including default values, which will be flagged using **# DEFAULT VALUE**, and the **AIX\_level**, **Kernel\_type**, **Last\_validation**, and **Logfile\_checksum** fields will be set appropriately.
3. If there is no **/etc/tunables/nextboot** file, all tunable parameters, except those of type **Bosboot**, will be set to their default value, a **nextboot** file with only an info stanza will be created, and the following warning: "cannot access the **/etc/tunables/nextboot** file" will be printed in the log file. The **lastboot** file will be created as described in step 2.
4. If the desired value for a parameter is found to be out of range, the parameter will be left to its default value, and a message similar to the following: "Parameter A could not be set to X, which is out of range, and was left to its current value (Y) instead" will be printed in the log file. Similarly, if a set of interdependent parameters have values incompatible with each other, they will all be left at their default values and a message similar to the following: "Dependent parameter A, B and C could not be set to X, Y and Z because those values are incompatible with each other. Instead, they were left to their current values (T, U and V)" will be printed in the log file. All of these error conditions could exist if a user modified the **/etc/tunables/nextboot** file with an editor or copied it from another machine, possibly running a different version of AIX with different valid ranges, and did not run **tuncheck -r -f** on the file. Alternatively, **tuncheck -r -f** prompted the user to run **bosboot**, but this was not done.


## Recovery Procedure

If the machine becomes unstable with a given **nextboot** file, users should put the system into maintenance mode, make sure the **sys0 pre520tune** attribute is set to disable, delete the **nextboot** file, run the **bosboot** command and reboot. This action will guarantee that all tunables are set to their default value.

## Kernel tuning using the SMIT interface

To start the SMIT panels that manage AIX kernel tuning parameters, use the SMIT fast path **smitty tuning**.

The following is a view of the tuning panel:



Select **Save/Restore All Kernel & Network Parameters** to manipulate all tuning parameter values at the same time. To individually change tuning parameters managed by one of the tuning commands, select any of the other lines.

## Global manipulation of tuning parameters

Review the following steps to globally manipulate tuning parameters.

The main panel to manipulate all tunable parameters by sets looks similar to the following:

```
Save/Restore All Kernel Tuning Parameters

View Last Boot Parameters
View Last Boot Log File

Save All Current Parameters for Next Boot
Save All Current Parameters
Restore All Current Parameters from Last Boot Values
Restore All Current Parameters from Saved Values
Reset All Current Parameters To Default Value

Save All Next Boot Parameters
Restore All Next Boot Parameters from Last Boot Values
Restore All Next Boot Parameters from Saved Values
Reset All Next Boot Parameters To Default Value
```

Each of the options in this panel are explained in the following sections.

1. View Last Boot Parameters All last boot parameters are listed stanza by stanza, retrieved from the `/etc/tunables/lastboot` file.
2. View Last Boot Log File Displays the content of the file `/etc/tunables/lastboot.log`.
3. Save All Current Parameters for Next Boot

```
Save All Current Kernel Tuning Parameters for Next Boot

ARE YOU SURE ?
```

After selecting **yes** and pressing **ENTER**, all the current tuning parameter values are saved in the `/etc/tunables/nextboot` file. **Bosboot** will be offered if necessary.

4. Save All Current Parameters

```
Save All Current Kernel Tuning Parameters

File name      []
Description    []
```

Type or select values for the two entry fields:

- **File name:** F4 will show the list of existing files. This is the list of all files in the `/etc/tunables` directory except the files `nextboot`, `lastboot` and `lastboot.log` which all have special purposes. File names entered cannot be any of the above three reserved names.
- **Description:** This field will be written in the info stanza of the selected file.

After pressing **ENTER**, all of the current tuning parameter values will be saved in the selected stanza file of the `/etc/tunables` directory.

5. Restore All Current Parameters from Last Boot Values

```
Restore All Current Parameters from Last Boot Values

ARE YOU SURE ?
```

After selecting **yes** and pressing **ENTER**, all the tuning parameters will be set to values from the `/etc/tunables/lastboot` file. Error messages will be displayed if any parameter of type **Bosboot** or **Reboot** would need to be changed, which can only be done when changing reboot values.

## 6. Restore All Current Parameters from Saved Values

```
Restore Saved Kernel Tuning Parameters

Move cursor to desired item and press Enter.

mytunablefile  Description field of mytunable file
tun1           Description field of lastweek file
```

A select menu shows existing files in the `/etc/tunables` directory, except the files `nextboot`, `lastboot` and `lastboot.log` which all have special purposes. After pressing **ENTER**, the parameters present in the selected file in the `/etc/tunables` directory will be set to the value listed if possible. Error messages will be displayed if any parameter of type **Bosboot** or **Reboot** would need to be changed, which can't be done on the current values. Error messages will also be displayed for any parameter of type **Incremental** when the value in the file is smaller than the current value, and for out of range and incompatible values present in the file. All possible changes will be made.

## 7. Reset All Current Parameters To Default Value

```
Reset All Current Kernel Tuning Parameters To Default Value

ARE YOU SURE ?
```

After pressing **ENTER**, each tunable parameter will be reset to its default value. Parameters of type **Bosboot** and **Reboot**, are never changed, but error messages are displayed if they should have been changed to get back to their default values.

## 8. Save All Next Boot Parameters

```
Save All Next Boot Kernel Tuning Parameters

File name 
```

Type or a select values for the entry field. Pressing **F4** displays a list of existing files. This is the list of all files in the `/etc/tunables` directory except the files `nextboot`, `lastboot` and `lastboot.log` which all have special purposes. File names entered cannot be any of those three reserved names. After pressing **ENTER**, the `nextboot` file, is copied to the specified `/etc/tunables` file if it can be successfully **tunchecked**.

## 9. Restore All Next Boot Parameters from Last Boot Values

```
Restore All Next Boot Kernel Tuning Parameters from Last Boot Values

ARE YOU SURE ?
```

After selecting **yes** and pressing **ENTER**, all values from the `lastboot` file will be copied to the `nextboot` file. If necessary, the user will be prompted to run **bosboot**, and warned that for all the changes to be effective, the machine must be rebooted.

## 10. Restore All Next Boot Parameters from Saved Values

```
Restore All Next Boot Kernel Tuning Parameters from Saved Values

Move cursor to desired item and press Enter.

mytunablefile  Description field of mytunablefile file
tun1           Description field of tun1 file
```

A select menu shows existing files in the `/etc/tunables` directory, except the files `nextboot`, `lastboot` and `lastboot.log` which all have special purposes. After selecting a file and pressing **ENTER**, all

values from the selected file will be copied to the **nextboot** file, if the file was successfully **tunchecked** first. If necessary, the user will be prompted to run **bosboot**, and warned that for all the changes to be effective, rebooting the machine is necessary.

#### 11. Reset All Next Boot Parameters To Default Value

```

Reset All Next Boot Kernel Tuning Parameters To Default Value
ARE YOU SURE ?
  
```

After hitting **ENTER**, the `/etc/tunables/nextboot` file will be cleared. If necessary **bosboot** will be proposed and a message indicating that a reboot is needed will be displayed.

### Changing individual parameters managed by a tuning command

All the panels for all six commands behave the same way. In the following sections, we will use the example of the Scheduler and Memory Load Control (i.e. **schedo**) panels to explain the behavior.

Here is the main panel to manipulate parameters managed by the **schedo** command:

```

Tuning Scheduler and Memory Load Control Parameters

List All Characteristics of Current Parameters
Change / Show Current Parameters
Change / Show Parameters for next boot
Save Current Parameters for Next Boot
Reset Current Parameters to Default value
Reset Next Boot Parameters To Default Value
  
```

### Interaction between parameter types and the different SMIT sub-panels

Review the following information to learn about the SMIT panel actions.

The following table shows the interaction between parameter types and the different SMIT sub-panels:

Sub-panel name	Action
List All Characteristics of Current Parameters	Lists current, default, reboot, limit values, unit, type and dependencies. This is the output of a tuning command called with the <b>-L</b> option.
Change / Show Current Parameters	Displays and changes current parameter value, except for parameter of type Static, Bosboot and Reboot which are displayed without surrounding square brackets to indicate that they cannot be changed.
Change / Show Parameters for Next Boot	Displays values from and rewrite updated values to the <b>nextboot</b> file. If necessary, <b>bosboot</b> will be proposed. Only parameters of type Static cannot be changed (no brackets around their value).
Save Current Parameters for Next Boot	Writes current parameters in the <b>nextboot</b> file, <b>bosboot</b> will be proposed if any parameter of type Bosboot was changed.
Reset Current Parameters to Default value	Resets current parameters to default values, except those which need a <b>bosboot</b> plus reboot or a reboot (bosboot and reboot type).
Reset Next Boot Parameters to Default value	Clears values in the <b>nextboot</b> file, and propose <b>bosboot</b> if any parameter of type Bosboot was different from its default value.

Each of the sub-panels behavior is explained in the following sections using examples of the scheduler and memory load control sub-panels:

1. List All Characteristics of Tuning Parameters The output of **schedo -L** is displayed.
2. Change/Show Current Scheduler and Memory Load Control Parameters

**Change / Show Current Scheduler and Memory Load Control Parameters**

[Entry Field]

affinity_lim	[7]
idle_migration_barrier	[4]
fixed_pri_global	[0]
maxspin	[1]
pacefork	[10]
sched_D	[16]
sched_R	[16]
timeslice	[1]
%usDelta	[100]
v_exempt_secs	[2]
v_min_process	[2]
v_repage_hi	[2]
v_repage_proc	[6]
v_sec_wait	[4]

This panel is initialized with the current **schedo** values (output from the **schedo -a** command). Any parameter of type **Bosboot**, **Reboot** or **Static** is displayed with no surrounding square bracket indicating that it cannot be changed. From the F4 list, type or select values for the entry fields corresponding to parameters to be changed. Clearing a value results in resetting the parameter to its default value. The F4 list also shows minimum, maximum, and default values, the unit of the parameter and its type. Selecting F1 displays the help associated with the selected parameter. The text displayed will be identical to what is displayed by the tuning commands when called with the **-h** option. Press **ENTER** after making all the required changes. Doing so will launch the **schedo** command to make the changes. Any error message generated by the command, for values out of range, incompatible values, or lower values for parameter of type **Incremental**, will be displayed to the user.

3. The following is an example of the Change / Show Scheduler and Memory Load Control Parameters for next boot panel.

**Change / Show Scheduler and Memory Load Control Parameters for next boot**

[Entry Field]

affinity_lim	[7]
idle_migration_barrier	[4]
fixed_pri_global	[0]
maxpin	[1]
pacefork	[10]
sched_D	[16]
sched_R	[16]
timeslice	[1]
%usDelta	[100]
v_exempt_secs	[2]
v_min_process	[2]
v_repage_hi	[2]
v_repage_proc	[6]
v_sec_wait	[4]

This panel is similar to the previous panel, in that, any parameter value can be changed except for parameters of type **Static**. It is initialized with the values listed in the **/etc/tunables/nextboot** file, completed with default values for the parameter not listed in the file. Type or select (from the F4 list) values for the entry field corresponding to the parameters to be changed. Clearing a value results in resetting the parameter to its default value. The F4 list also shows minimum, maximum, and default values, the unit of the parameter and its type. Pressing F1 displays the help associated with the selected parameter. The text displayed will be identical to what is displayed by the tuning commands when called with the **-h** option. Press **ENTER** after making all desired changes. Doing so will result in

the `/etc/tunables/nextboot` file being updated with the values modified in the panel, except for out of range, and incompatible values for which an error message will be displayed instead. If necessary, the user will be prompted to run **bosboot**.

4. The following is an example of the Save Current Scheduler and Memory Load Control Parameters for Next Boot panel.

**Save Current Scheduler and Memory Load Control Parameters for Next Boot**

ARE YOU SURE ?

After pressing **ENTER** on this panel, all the current **schedo** parameter values will be saved in the `/etc/tunables/nextboot` file . If any parameter of type **Bosboot** needs to be changed, the user will be prompted to run **bosboot**.

5. The following is an example of the Reset Current Scheduler and Memory Load Control Parameters to Default Values

**Reset Current Scheduler and Memory Load Control Parameters to Default Value**

ARE YOU SURE ?

After selecting **yes** and pressing **ENTER** on this panel, all the tuning parameters managed by the **schedo** command will be reset to their default value. If any parameter of type **Incremental**, **Bosboot** or **Reboot** should have been changed, and error message will be displayed instead.

6. The following is an example of the Reset Scheduler and Memory Load Control Next Boot Parameters To Default Values

**Reset Next Boot Parameters To Default Value**

ARE YOU SURE ?

After pressing **ENTER**, the **schedo** stanza in the `/etc/tunables/nextboot` file will be cleared. This will defer changes until next reboot. If necessary, **bosboot** will be proposed.

## Kernel Tuning using the Performance Plug-In for Web-based System Manager

AIX kernel tuning parameters can be managed using the Web-based System Manager System Tuning Plug-in, which is a sub-plugin of the Web-based System Manager Performance plug-in.

The Performance Plug-in is available from the Web-based System Manager main console which looks similar to the following:




Figure 1. Performance Plug-in shown in Web-based System Manager main console

The Performance plug-in is organized into the following sub-plugins:

- Performance Monitoring plug-in
- System Tuning plug-in

The Performance Monitoring sub-plugin gives access to a variety of performance-monitoring and report-generation tools. The System Tuning sub-plugin consists of CPU, Memory, RAS, Disk I/O, and Network I/O sub-plugins, which present tuning tables from which AIX tuning parameters can be visualized and changed.

The Navigation Area for the System Tuning plug-in contains three levels of sub-plugins as seen in the following:




Figure 2. System Tuning plug-in Performance window

These intermediate levels represent tuning resources. They are further split into sub-plugins but have no specific actions associated with them and only exist to group access to tunable parameters in a logical way. Actions on tunable parameters can be applied at the following levels:

### System-Tuning level

Global actions applicable to all tunable parameters are provided at this level.

### Leaf Levels

Leaves are represented by a folder icon (see navigation area in Figure 2). When selecting a leaf, a tuning table is displayed in the content area. A table represents a logical group of tunable parameters, all managed by one of the tunable commands (**schedo**, **vmo**, **ioo**, **raso**, **no**, and **nfso**). Specific actions provided at this level apply only to the tunable parameters displayed in the current table.

The **CPU/All Processes** sub-plugin is a link to the **All Processes** sub-plugin of the Processes application. Its purpose is not to manipulate tuning parameters and will not be discussed.

### Files

Item	Descriptor
<code>/etc/tunables/lastboot</code>	Contains tuning parameter stanzas from the last boot.
<code>/etc/tunables/lastboot.log</code>	Contains logging information from the last boot.
<code>/etc/tunables/nextboot</code>	Contains tuning parameter stanzas for the next system boot.

## Global actions on tunable parameters

Only the Web-based System Manager **Tuning** menu has specific actions associated with it.




Figure 3. Web-based System Manager Tuning menu

The specific actions available at this level are global, in that they apply to all the performance tunable parameters.

1. **View Last Boot Parameters** This action displays the `/etc/tunables/lastboot` file in an open working dialog.
2. **View Last Boot Log File** This action displays the `/etc/tunables/lastboot.log` file in an open working dialog.
3. **Save All Current Parameters for Next Boot** The Save All Current Parameters warning dialog is opened.



Figure 4. Save All Current Parameters for next boot dialog

After clicking **Yes**, all the current tuning parameter values will be saved in the `/etc/tunables/nextboot` file. **Bosboot** will be offered if necessary.

4. **Save All Current Parameters** The Save All Current Parameters dialog with a Filename field and a Description field is opened.




Figure 5. Save All Current Parameters to file dialog

The **Filename** editable combobox, lists all the tunable files present in the `/etc/tunables` directory, except the `nextboot`, `lastboot` and `lastboot.log` files, which all have special purposes. If no file is present, the combobox list is empty. The user can choose an existing file, or create a new file by entering a new name. File names entered cannot be any of the three reserved names. The **Description** field will be written in the info stanza of the selected file. After clicking **OK**, all the current tuning parameter values will be saved in the selected file in the `/etc/tunables` directory.

5. **Save All Next Boot Parameters**




Figure 6. Save All Next Boot Parameters to file dialog

This action opens an editable combobox which lists all the tunable files present in the `/etc/tunables` directory, except the `nextboot`, `lastboot` and `lastboot.log` files, which all have special purposes. If no file is present, the combobox list is empty. The user can choose an existing file, or create a new file by entering a new name. File names entered cannot be any of the three reserved names. After clicking **OK**, the `nextboot` file, is copied to the specified `/etc/tunables` file it can be successfully checked using the `tuncheck` command.

6. **Restore All Current Parameters** This action opens an editable combobox showing the list of all existing files in the `/etc/tunables` directory, except the files `nextboot`, and `lastboot.log` which have special purposes.




Figure 7. Restore All Current Parameters dialog

The user selects the file to use for restoring the current values of tuning parameters. The `lastboot` file is proposed as the default (first element of the combo list). Files can have a description which is displayed after the name in the combobox items, separated from the file name by a dash character. After clicking **OK**, the parameters present in the selected file in the `/etc/tunables` directory will be set to the value listed if possible. Error messages will be displayed if any parameter of type **Bosboot** or **Reboot** would need to be changed, which cannot be done on the current values. Error messages will also be displayed for any parameter of type **Incremental** when the value in the file is smaller than the current value, and for out of range and incompatible values present in the file. All possible changes will be made.

7. **Restore All Next Boot Parameters** A combobox is opened to display the list of all existing files in the `/etc/tunables` directory, except the files `nextboot`, and `lastboot.log` which have special purposes.




Figure 8. Restore All Next Boot Parameters dialog

The user selects the file to use for restoring the **nextboot** values of tuning parameters. The **lastboot** file is proposed as the default (first element of the combo list). Files can have a description which is displayed after the name in the combobox items, separated from the file name by a dash character. After clicking **OK**, all values from the selected file will be copied to the **/etc/tunables/nextboot** file. Incompatible dependent parameter values or out of range values will not be copied to the file (this could happen if the file selected was not previously **tunchecked**). Error messages will be displayed instead. If necessary, the user will be prompted to run **bosboot**, and warned that for all the changes to be effective, rebooting the machine is necessary.

8. **Reset All Current Parameters to Default Values** A warning dialog is opened and after clicking **Yes**, a working dialog is displayed. Each tunable parameter is reset to its default value. Parameters of type **Incremental**, **Bosboot** and **Reboot**, are never changed, but error messages are displayed if they should have been changed to revert to default values.
9. **Reset All Next Boot Parameters to Default Values** A warning dialog is opened and after clicking **Yes**, an interactive working dialog is displayed and the **/etc/tunables/nextboot** file is cleared. If necessary **bosboot** will be proposed and a message indicating that a reboot is needed will be displayed.

### Using tuning tables to change individual parameter values

Each tuning table in the content area has the same structure. It enables all the characteristics of the tunable parameters to be viewed at a glance.

The table has two editable columns, **Current Value** and **Next Boot Value**. Each cell in these two columns is an editable combobox, with only one predefined value of **Default**, for the capture of new value for a parameter. Data entered in these columns is validated when pressing **ENTER**.




Figure 9. Memory VMM window

The parameters are grouped as they are in the SMIT panels with two small exceptions. First, the Network related parameters are all presented in one SMIT panel, but subdivided in six sections. The Web-based System Manager interface uses six separate tables instead.

Lastly, the parameters managed by the **schedo** command are available from two sub-plugins: CPU/scheduling and memory/scheduling.

Actions permitted vary according to parameter types:

- Static parameters do not have an editable cell.
- New values for Dynamic parameters can be applied now or saved for next boot.
- New values for **Reboot** parameters can only be saved for next boot.
- New values for **Bosboot** parameters can only be saved for next boot, and users are prompted to run bosboot.
- New values for **Mount** parameters can be applied now or saved for next boot, but when applied immediately, a warning will be displayed to tell the user that changes will only be effective for future file systems or directory mountings.
- New values for **Incremental** parameters can be applied now or saved for next boot. If applied now, they will only be accepted if the new value is bigger than the current value.

### Tunable tables actions

The actions available for each tunable table are **Save Changes**, **Save Current Parameters for Next Boot**, **Reset Parameters to System Default**, **Parameter Details**, and **Monitor**. The **Monitor** action enables related monitoring tools to start from each of the plug-ins and is not discussed in this section.




Figure 10. Tables Menus window

### 1. Save Changes

This option opens a dialog enabling you to save new values for the parameters listed in the **Current Value** and **Next Boot Value** columns of the table. The two options are checked by default. They are:




Figure 11. Save Changes dialog

- Selecting **Update and apply current values** and clicking **OK**, launches the tuning command corresponding to the parameters shown in the table to make all the desired changes. Selecting **Default** in the combobox as the new value resets the parameter to its default value. If a parameter of type **Incremental** has a new value smaller than its current value, an error message will be displayed. If incompatible dependent parameter values or out of range values have been entered, an error message will also be displayed. All the acceptable changes will be made.
- Selecting **Update next boot values** and clicking **OK**, writes the desired changes to the `/etc/tunables/nextboot` file. If necessary, the user will be prompted to run **bosboot**. If incompatible dependent parameter values or out of range values have been entered, an error message will be displayed, and those parameter values will not be copied to the **nextboot** file.
- Selecting both options makes all the desired changes now and for the next reboot.
- 

## 2. Save Current Parameters for Next Boot

A warning dialog is opened.




Figure 12. Save All Current Parameters to file dialog

After clicking **Yes**, all the current parameter values listed in the table will be saved in the `/etc/tunables/nextboot` file. If any parameter of type **Bosboot** needs to be changed, the user will be prompted to run **bosboot**.

## 3. Reset Parameters to System Default

This dialog permits resetting of current or next boot values for all the parameters listed in the table to their default value.




Figure 13. Reset All Parameters to System Defaults dialog

You can select one of the following options:

- Selecting **Reset current parameters to system default** and clicking **OK**, will reset all the tuning parameters listed in the table to their default value. If any parameter of type **Incremental**, **Bosboot** or **Reboot** should have been changed, an error message will be displayed and the parameter will not be changed.
- Selecting **Reset next boot parameters to system default** and clicking **OK** deletes the parameter listed in the table from the `/etc/tunables/nextboot` file. This action will defer changes until next reboot. If necessary, **bosboot** will be proposed.

## Parameter details

Clicking on **Parameter Details** in the toolbar or selecting the equivalent menu item, followed by a click on a parameter in the table will display the help information available in a help dialog.




Figure 14. Help dialog

## Show restricted parameters:

Clicking on the **Show Restricted Parameters** check box in the tunable type menu will redisplay the list of tunable parameters to include the restricted use development parameters. The name of a development parameter is followed by the indication "(R)" to distinguish them from others.




Figure 15. RAS Table Menus dialog

## The procmon tool

This section provides detailed information about the **procmon** tool.

### Overview of the procmon tool

You can use the **procmon** tool on systems running AIX.

The **procmon** tool enables you to view and manage the processes running on a system. The **procmon** tool has a graphical interface and displays a table of process metrics that you can sort on the different fields that are provided. The default number of processes listed in the table is 20, but you can change the value in the **Table Properties** panel from the main menu. Only the top processes based on the sorting metric are displayed and the default sorting key is CPU consumption.

The default value of the refresh rate for the table of process metrics is 5 seconds, but you can change the refresh rate by either using the **Table Properties** panel in the main menu or by clicking on the **Refresh** button.

By default, the **procmon** tool displays the following:

- How long a process has been running
- How much CPU resource the processes are using
- Whether processes are being penalized by the system
- How much memory the processes are using
- How much I/O a process is performing
- The priority and nice values of a process
- Who has created a particular process

You can choose other metrics to display from the **Table Properties** panel in the main menu. For more information, see “The process table of the procmon tool.”

You can filter any of the processes that are displayed. For more information, see “Filtering processes” on page 244.

You can also perform certain AIX performance commands on these processes. For more information, see “Performing AIX commands on processes” on page 244.

The **procmon** tool is a Performance Workbench plugin, so you can only launch the **procmon** tool from within the Performance Workbench framework. You must install the **bos.perf.gtools** fileset by either using the **smitty** tool or the **installp** command. You can then access the Performance Workbench by running the **/usr/bin/perfwb** script.

**Note:** Do not run the **/opt/perfwb/perfwb** binary file.

## Components of the procmon tool

The graphical interface of the **procmon** tool consists of the following components.

### The global statistics area of the procmon tool

The global statistics area is a table that is displayed at the top of the **procmon** tool window. The global statistics area displays the amount of CPU and memory that is being used by the system.

You can refresh the statistics data by either clicking on the **Refresh** button in the menu bar or by activating the automatic refresh option through the menu bar. To save the statistics information, you can export the table to any of the following file formats:

- XML
- HTML
- CSV

### The process table of the procmon tool

The process table is the main component of the **procmon** tool. The process table displays the various processes that are running on the system, ordered and filtered according to the user configuration.

The default value of the number of processes listed in the process table is 20, but you can change this value from the **Table Properties** panel from the main menu.

The yellow arrow key in the column header indicates the sort key for the process table. The arrow points either up or down, depending on whether the sort order is ascending or descending, respectively. You can change the sort key by clicking on any of the column headers.

You can customize the process table, modify the information on the various processes, and run commands on the displayed processes. By default, the **procmon** tool displays the following columns:

PID	Process identifier
CPUPER	Percentage of CPU used per process since the last refresh
PRM	Percent real memory usage
ELOGIN	Effective login of the process user
COMMAND	Short name of the process launched
WPAR	WPAR of the process

You can choose to display other metrics, like the following:

Item	Descriptor
PPID	Parent process identifier
NICE	Nice value for the process
PRI	Priority of the process
DRSS	Data resident set size
TRSS	Text resident set size
STARTTIME	Time when the command started
EUID	Effective user identifier
RUID	Real user identifier
EGID	Effective group identifier
RGID	Real group identifier
THCOUNT	Number of threads used
CLASSID	Identifier of the class which pertains to the WLM process
CLASSNAME	Name of the class which pertains to the WLM process
TOTDISKIO	Disk I/O for that process
NVCSW	N voluntary context switches
NIVCSW	N involuntary context switches
MINFLT	Minor page faults
MAJFLT	Major page faults
INBLK	Input blocks
OUBLK	Output blocks
MSGSEND	Messages sent
MSGRECV	Messages received
EGROUP	Effective group name
RGROUP	Real group name

You can use either the table properties or preference to display the metrics you are interested in. If you choose to change the table properties, the new configuration values are set for the current session only. If you change the preferences, the new configuration values are set for the next session of the **procmon** tool.

There are two types of values listed in the process table:

- Real values
- Delta values

Real values are retrieved from the kernel and displayed in the process table. An example of a real value is the PID, PPID, or TTY.

Delta values are values that are computed from the last-stored measurements. An example of a delta value is the CPU percent for each process, which is computed using the values measured between refreshes.

Below the process table, there is another table that displays the sum of the values for each column of the process table. For example, this table might provide a good idea of the percentage of total CPU used by the top 20 CPU-consuming processes.

You can refresh the data by either clicking on the **Refresh** button in the menu bar or by activating the automatic refresh option through the menu bar. To save the statistics information, you can export the table to any of the following file formats:

- XML
- HTML
- CSV

### The status line of the Performance Workbench

The Performance Workbench status line displays the date on which the information was retrieved, as well as the name of the system. The status line is hidden if you activate another view or perspective, but automatically reappears if you refresh the information.

### The WPAR table of the procmon tool

A WPAR tabulation displays all the WPAR defined on the system in a table.

By default, the procmon tool displays the following columns:

Item	Descriptor
Name	WPAR name
Hostname	WPAR hostname
Type	WPAR type, either System or Application
State	WPAR state—this can have one of the following values: Active, Defined, Transitional, Broken, Paused, Loaded, Error
Directory	WPAR root directory
Nb. virtual PIDs	Number of virtual PIDs running in this WPAR

### Filtering processes

You can filter processes based on the various criteria that is displayed in the process table. To create a filter, select **Table Filters** from the menu bar. A new window opens and displays a list of filters.

### Performing AIX commands on processes

To run any of the following commands on one or more processes, select the processes in the process table and right click your mouse, and select either **Commands** or **Modify** and then select the command you want to run. A new window opens, which displays the command output while the command is running.

You can interrupt the command by clicking on the **STOP** button.

You can run the following AIX commands on the processes you select in the process table:

- The **svmon** command
- The **renice** command
- The **kill** command
- The following **proctools** commands:
  - The **procfiles** command

- The **proctree** command
- The **procsig** command
- The **procstack** command
- The **procrun** command
- The **procmmap** command
- The **procflags** command
- The **proccred** command
- The **procldd** command

---

## Profiling tools

You can use profiling tools to identify which portions of the program are executed most frequently or where most of the time is spent.

Profiling tools are typically used after a basic tool, such as the **vmstat** or **iostat** commands, shows that a CPU bottleneck is causing a performance problem.

Before you begin locating hot spots in your program, you need a fully functional program and realistic data values.

## The timing commands

Use the timing commands for testing and debugging programs whose performance you are recording and trying to improve.

The output from the **time** command is in minutes and seconds, as follows:

```
real    0m26.72s
user    0m26.53s
sys     0m0.03s
```

The output from the **timex** command is in seconds, as follows:

```
real 26.70
user 26.55
sys  0.02
```

Comparing the user+sys CPU time to the real time will give you an idea if your application is CPU-bound or I/O-bound.

**Note:** Be careful when you do this on an SMP system. For more information, see [time](#) and [timex](#) (Cautions).

The **timex** command is also available through the SMIT command on the Analysis Tools menu, found under Performance and Resource Scheduling. The **-p** and **-s** options of the **timex** command enable data from accounting (**-p**) and the **sar** command (**-s**) to be accessed and reported. The **-o** option reports on blocks read or written.

## The prof command

The **prof** command displays a profile of CPU usage for each external symbol, or routine, of a specified program.

In detail, it displays the following:

- The percentage of execution time spent between the address of that symbol and the address of the next
- The number of times that function was called
- The average number of milliseconds per call

The **prof** command interprets the profile data collected by the **monitor()** subroutine for the object file (**a.out** by default), reads the symbol table in the object file, and correlates it with the profile file (**mon.out** by default) generated by the **monitor()** subroutine. A usage report is sent to the terminal, or can be redirected to a file.

To use the **prof** command, use the **-p** option to compile a source program in C, FORTRAN, or COBOL. This inserts a special profiling startup function into the object file that calls the **monitor()** subroutine to track function calls. When the program is executed, the **monitor()** subroutine creates a **mon.out** file to track execution time. Therefore, only programs that explicitly exit or return from the main program cause the **mon.out** file to be produced. Also, the **-p** flag causes the compiler to insert a call to the **mcount()** subroutine into the object code generated for each recompiled function of your program. While the program runs, each time a parent calls a child function, the child calls the **mcount()** subroutine to increment a distinct counter for that parent-child pair. This counts the number of calls to a function.

**Note:** You cannot use the **prof** command for profiling optimized code.

By default, the displayed report is sorted by decreasing percentage of CPU time. This is the same as when specifying the **-t** option.

The **-c** option sorts by decreasing number of calls and the **-n** option sorts alphabetically by symbol name.

If the **-s** option is used, a summary file **mon.sum** is produced. This is useful when more than one profile file is specified with the **-m** option (the **-m** option specifies files containing monitor data).

The **-z** option includes all symbols, even if there are zero calls and time associated.

Other options are available and explained in the **prof** command in the *Files Reference*.

The following example shows the first part of the **prof** command output for a modified version of the Whetstone benchmark (Double Precision) program.

```
# cc -o cwhet -p -lm cwhet.c
# cwhet > cwhet.out
# prof
Name           %Time    Seconds    Cumsecs  #Calls  msec/call
.main          32.6      17.63      17.63     1    17630.
.__mcount      28.2      15.25      32.88
.mod8          16.3      8.82       41.70  8990000    0.0010
.mod9          9.9       5.38       47.08  6160000    0.0009
.cos           2.9       1.57       48.65  1920000    0.0008
.exp           2.4       1.32       49.97  930000     0.0014
.log           2.4       1.31       51.28  930000     0.0014
.mod3          1.9       1.01       52.29  140000     0.0072
.sin           1.2       0.63       52.92  640000     0.0010
.sqrt          1.1       0.59       53.51
.atan          1.1       0.57       54.08  640000     0.0009
.pout          0.0       0.00       54.08    10         0.0
.exit          0.0       0.00       54.08    1         0.
.free         0.0       0.00       54.08    2         0.
.free_y       0.0       0.00       54.08    2         0.
```

In this example, we see many calls to the **mod8()** and **mod9()** routines. As a starting point, examine the source code to see why they are used so much. Another starting point could be to investigate why a routine requires so much time.

**Note:** If the program you want to monitor uses a **fork()** system call, be aware that the parent and the child create the same file (**mon.out**). To avoid this problem, change the current directory of the child process.

## The gprof command

The **gprof** command produces an execution profile of C, FORTRAN, or COBOL programs.

The statistics of called subroutines are included in the profile of the calling program. The **gprof** command is useful in identifying how a program consumes CPU resources. It is roughly a superset of the **prof** command, giving additional information and providing more visibility to active sections of code.

### Implementation of the gprof command

The source code must be compiled with the **-pg** option.

This action links in versions of library routines compiled for profiling and reads the symbol table in the named object file (**a.out** by default), correlating it with the call graph profile file (**gmon.out** by default). This means that the compiler inserts a call to the **mcount()** function into the object code generated for each recompiled function of your program. The **mcount()** function counts each time a parent calls a child function. Also, the **monitor()** function is enabled to estimate the time spent in each routine.

The **gprof** command generates two useful reports:

- The call-graph profile, which shows the routines, in descending order by CPU time, plus their descendants. The profile permits you to understand which parent routines called a particular routine most frequently and which child routines were called by a particular routine most frequently.
- The flat profile of CPU usage, which shows the usage by routine and number of calls, similar to the **prof** output.

Each report section begins with an explanatory part describing the output columns. You can suppress these pages by using the **-b** option.

Use **-s** for summaries and **-z** to display routines with zero usage.

Where the program is executed, statistics are collected in the **gmon.out** file. These statistics include the following:

- The names of the executable program and shared library objects that were loaded
- The virtual memory addresses assigned to each program segment
- The **mcount()** data for each parent-child
- The number of milliseconds accumulated for each program segment

Later, when the **gprof** command is issued, it reads the **a.out** and **gmon.out** files to generate the two reports. The call-graph profile is generated first, followed by the flat profile. It is best to redirect the **gprof** output to a file, because browsing the flat profile first might answer most of your usage questions.

The following example shows the profiling for the **cwhet** benchmark program. This example is also used in “The prof command” on page 245:

```
# cc -o cwhet -pg -lm cwhet.c
# cwhet > cwhet.out
# gprof cwhet > cwhet.gprof
```

### The call-graph profile:

The call-graph profile is the first part of the **cwhet.gprof** file.

The following is an example of the **cwhet.gprof** file:

granularity: each sample hit covers 4 byte(s) Time: 62.85 seconds

index	%time	self	descendants	called/total called+self called/total	parents name children	index
-------	-------	------	-------------	---	-----------------------------	-------

```

[1] 64.6 19.44 21.18 1/1      .__start [2]
      8.89  0.00 8990000/8990000  .mod8 [4]
      5.64  0.00 6160000/6160000  .mod9 [5]
      1.58  0.00 930000/930000    .exp [6]
      1.53  0.00 1920000/1920000  .cos [7]
      1.37  0.00 930000/930000    .log [8]
      1.02  0.00 140000/140000    .mod3 [10]
      0.63  0.00 640000/640000    .atan [12]
      0.52  0.00 640000/640000    .sin [14]
      0.00  0.00 10/10          .pout [27]

```

```

-----
[2] 64.6 0.00 40.62      <spontaneous>
      19.44 21.18 1/1      .__start [2]
      0.00  0.00 1/1      .main [1]
      0.00  0.00 1/1      .exit [37]
-----

```

Usually the call graph report begins with a description of each column of the report, but it has been deleted in this example. The column headings vary according to type of function (current, parent of current, or child of current function). The current function is indicated by an index in brackets at the beginning of the line. Functions are listed in decreasing order of CPU time used.

To read this report, look at the first index [1] in the left-hand column. The .main function is the current function. It was started by .\_\_start (the parent function is on top of the current function), and it, in turn, calls .mod8 and .mod9 (the child functions are beneath the current function). All the accumulated time of .main is propagated to .\_\_start. The self and descendents columns of the children of the current function add up to the descendents entry for the current function. The current function can have more than one parent. Execution time is allocated to the parent functions based on the number of times they are called.

### Flat profile:

The flat profile sample is the second part of the **cwhet.gprof** file.

The following is an example of the **cwhet.gprof** file:

granularity: each sample hit covers 4 byte(s) Total time: 62.85 seconds

% time	cumulative seconds	self seconds	calls	self ms/call	total ms/call	name
30.9	19.44	19.44	1	19440.00	40620.00	.main [1]
30.5	38.61	19.17				.__mcount [3]
14.1	47.50	8.89	8990000	0.00	0.00	.mod8 [4]
9.0	53.14	5.64	6160000	0.00	0.00	.mod9 [5]
2.5	54.72	1.58	930000	0.00	0.00	.exp [6]
2.4	56.25	1.53	1920000	0.00	0.00	.cos [7]
2.2	57.62	1.37	930000	0.00	0.00	.log [8]
2.0	58.88	1.26				.qincrement [9]
1.6	59.90	1.02	140000	0.01	0.01	.mod3 [10]
1.2	60.68	0.78				.__stack_pointer [11]
1.0	61.31	0.63	640000	0.00	0.00	.atan [12]
0.9	61.89	0.58				.qincrement1 [13]
0.8	62.41	0.52	640000	0.00	0.00	.sin [14]
0.7	62.85	0.44				.sqrt [15]
0.0	62.85	0.00	180	0.00	0.00	.fwrite [16]
0.0	62.85	0.00	180	0.00	0.00	.memchr [17]
0.0	62.85	0.00	90	0.00	0.00	.__fbsbuf [18]
0.0	62.85	0.00	90	0.00	0.00	._fbsbuf [19]

The flat profile is much less complex than the call-graph profile and very similar to the output of the **prof** command. The primary columns of interest are the **self** seconds and the **calls** columns. These reflect the CPU seconds spent in each function and the number of times each function was called. The next columns to look at are **self ms/call** (CPU time used by the body of the function itself) and **total ms/call** (time in the body of the function plus any descendent functions called).

Normally, the top functions on the list are candidates for optimization, but you should also consider how many calls are made to the function. Sometimes it can be easier to make slight improvements to a frequently called function than to make extensive changes to a piece of code that is called once.

A cross reference index is the last item produced and looks similar to the following:

Index by function name

[18] .__flsbuf	[37] .exit	[5] .mod9
[34] .__ioctl	[6] .exp	[43] .moncontrol
[20] .__mcount	[39] .expand_catname	[44] .monitor
[3] .__mcount	[32] .free	[22] .myecvt
[23] .__nl_langinfo_std	[33] .free_y	[28] .nl_langinfo
[11] .__stack_pointer	[16] .fwrite	[27] .pout
[24] .__doprnt	[40] .getenv	[29] .printf
[35] .__findbuf	[41] .ioctl	[9] .qincrement
[19] .__flsbuf	[42] .isatty	[13] .qincrement1
[36] .__wrtchk	[8] .log	[45] .saved_category_nam
[25] .__xflsbuf	[1] .main	[46] .setlocale
[26] .__xwrite	[17] .memchr	[14] .sin
[12] .atan	[21] .mf2x2	[31] .splay
[38] .catopen	[10] .mod3	[15] .sqrt
[7] .cos	[4] .mod8	[30] .write

**Note:** If the program you want to monitor uses a **fork()** system call, be aware that by default, the parent and the child create the same file, **gmon.out**. To avoid this problem, use the **GPROF** environment variable. You can also use the **GPROF** environment variable to profile multi-threaded applications.

## The tprof command

The typical program execution is a variable combination of application code, library subroutines, and kernel services. Frequently, programs that have not been tuned expend most of their CPU cycles in certain statements or subroutines.

You can determine which particular statements or subroutines to examine with the **tprof** command.

The **tprof** command is a versatile profiler that provides a detailed profile of CPU usage by every process ID and name. It further profiles at the application level, routine level, and even to the source statement level and provides both a global view and a detailed view. In addition, the **tprof** command can profile kernel extensions, stripped executable programs, and stripped libraries. It does subroutine-level profiling for most executable programs on which the **stripnm** command produces a symbols table. The **tprof** command can profile any program produced by any of the following compilers:

- C
- C++
- FORTRAN
- Java™

The **tprof** command only profiles CPU activity. It does not profile other system resources, such as memory or disks.

The **tprof** command can profile Java programs using Java Persistence API (JPA) (**-x java -Xrunjpa**) to collect Java Just-in-Time (JIT) source line numbers and instructions, if the following parameters are added to **-Xrunjpa**:

- **source=1**; if IBM Java Runtime Environment (JRE) 1.5.0 is installed, this parameter enables JIT source line collecting.
- **instructions=1**; enables JIT instructions collecting.

## Time-based profiling

Time-based profiling is the default profiling mode and it is triggered by the decremter interrupt, which occurs every 10 milliseconds.

With time-based profiling, the **tprof** command cannot determine the address of a routine when interrupts are disabled. While interrupts are disabled, all ticks are charged to the **unlock\_enable()** routines.

## Event-based profiling

Event-based profiling is triggered by any one of the software-based events or any Performance Monitor event that occurs on the processor.

The primary advantages of event-based profiling over time-based profiling are the following:

- The routine addresses are visible when interrupts are disabled.
- The ability to vary the profiling event
- The ability to vary the sampling frequency

With event-based profiling, ticks that occur while interrupts are disabled are charged to the proper routines. Also, you can select the profiling event and sampling frequency. The profiling event determines the trigger for the interrupt and the sampling frequency determines how often the interrupt occurs. After the specified number of occurrences of the profiling event, an interrupt is generated and the executing instruction is recorded.

The default type of profiling event is processor cycles. The following are various types of software-based events:

- Emulation interrupts (EMULATION)
- Alignment interrupts (ALIGNMENT)
- Instruction Segment Lookaside Buffer misses (ISLBMISS)
- Data Segment Lookaside Buffer misses (DSLBMIS)

The sampling frequency for the software-based events is specified in milliseconds and the supported range is 1 to 500 milliseconds. The default sampling frequency is 10 milliseconds.

The following command generates an interrupt every 5 milliseconds and retrieves the record for the last emulation interrupt:

```
# tprof -E EMULATION -f 5
```

The following command generates an interrupt every 100 milliseconds and records the contents of the Sampled Instruction Address Register, or SIAR:

```
# tprof -E -f 100
```

The following are other types of Performance Monitor events:

- Completed instructions
- Cache misses

For a list of all the Performance Monitor events that are supported on the processors of the system, use the **pmlist** command. The chosen Performance Monitor event must be taken in a group where we can also find the PM\_INST\_CMPL Performance Monitor event. The sampling frequency for these events is specified in the number of occurrences of the event. The supported range is 10,000 to MAXINT occurrences. The default sampling frequency is 10,000 occurrences.

The following command generates an interrupt after the processor completes 50,000 instructions:

```
# tprof -E PM_INST_CMPL -f 50000
```

Event-based profiling uses the SIAR, which contains the address of an instruction close to the executing instruction. For example, if the profiling event is PM\_FPU0\_FIN, which means the floating point unit 0 produces a result, the SIAR might not contain that floating point instruction but might contain another instruction close to it. This is more relevant for profiling based on Performance Monitor events. In fact for the proximity reason, on systems based on POWER4 and later, it is recommended that the Performance Monitor profiling event be one of the marked events. Marked events have the **PM\_MRK** prefix.

Certain combinations of profiling event, sampling frequency, and workload might cause interrupts to occur at such a rapid rate that the system spends most of its time in the interrupt handler. The **tprof** command detects this condition by keeping track of the number of completed instructions between two consecutive interrupts. When the **tprof** command detects five occurrences of the count falling below the acceptable limit, the trace collection stops. Reports are still generated and an error message is displayed. The default threshold is 1,000 instructions.

## Large page analysis

The **tprof -a** command collects profile trace from a representative application run and produces performance projections for mapping different portions of the application's data space to different page sizes.

Large Page Analysis uses the information in the trace to project translation buffer performance when mapping any of the following four application memory regions to a different page size:

- static application data (initialized and uninitialized data)
- application heap (dynamically allocated data)
- stack
- application text

The performance projections are provided for each of the page sizes supported by the operating system. The first performance projection is a baseline projection for mapping all four memory regions to the default 4 KB pages. Subsequent projections map one region at a time to a different page size. The statistics reported for each projection include: the page size, the number of pages needed to back all four regions, a translation miss score, and a cold translation miss score.

The summary section lists the processes profiled and the statistics reported including: number/percentage of memory reference, modeled memory reference, malloc calls, and free calls.

### How to interpret the results:

The translation miss score is an indicator of the translation miss rate and ranges from 0 (no translation misses) to 1 (every reference results in a translation miss).

The translation miss rate is defined as:

$$\text{Translation miss rate} = (\text{Number of translation misses}) / (\text{Number of translation buffer accesses})$$

The translation miss score differs from the actual translation miss rate because it is based on sampled references. Sampling has the effect of reducing the denominator (Number of translation buffer accesses) in the above equation faster than the numerator (Number of translation misses). As a result, the translation miss score tends to overestimate the actual translation miss rate at increasing sampling rates. Thus, the translation score should be interpreted as a relative measure for comparing the effectiveness of different projections rather than as a predictor of actual translation miss rates.

The translation miss score is directly affected by larger page sizes: growing the page size reduces the translation miss score. The performance projection report includes both a cold translation miss score (such

as compulsory misses) and a total translation miss score (such as compulsory and capacity misses). The cold translation miss score provides a useful lower bound; if growing the page size has reduced the translation miss score to the cold translation miss score, then all capacity translation misses have been eliminated and further increases in page size can only have negligible additional benefits.

The performance projection for a process would appear similar to the following:

Modeled region for the process ./workload [661980]

Region	Start	End	Size (KB)	%MemRef
=====	=====	=====	=====	=====
heap	0x1100059b0	0x1207b0b60	269996.43	74.45
data	0x110000710	0x11000598c	20.63	1.55
stack	0xffffffffced10	0xffffffffffe0	196.71	20.44
text	0x100000288	0x100053710	333.14	2.56

Performance projection for the process ./workload [661980]

Region	PageSize	# Pages	TMissScore	ColdTMissScore
=====	=====	=====	=====	=====
heap	4 KB	67500	0.92343 (100.0%)	0.09234 (100.0%)
heap	64 KB	4219	0.53615 ( 45.0%)	0.02744 ( 30.0%)
heap	16 MB	17	0.00010 ( 00.1%)	0.00002 ( 00.1%)
data	4 KB	6	0.53615 (100.0%)	0.02744 (100.0%)
data	64 KB	1	0.00053 ( 00.1%)	0.00009 ( 00.1%)
data	16 MB	1	0.00053 ( 00.1%)	0.00009 ( 00.1%)
stack	4 KB	50	0.53615 (100.0%)	0.02744 (100.0%)
stack	64 KB	4	0.05361 ( 10.0%)	0.00274 ( 10.0%)
stack	16 MB	1	0.00053 ( 00.1%)	0.00009 ( 00.1%)
text	4 KB	84	0.53615 (100.0%)	0.04744 (100.0%)
text	64 KB	6	0.05361 ( 10.0%)	0.00274 ( 10.0%)
text	16 MB	1	0.00053 ( 00.1%)	0.00009 ( 00.1%)

*Data profiling:*

The **tprof -b** command turns on basic data profiling and collects data access information.

The summary section reports access information across kernel data, library data, user global data, and stackheap sections for each process, as shown in the following example:

*Table 3. Data profiling of the tprof -b command*

Process	Freq	Total	Kernel	User	Shared	Other
tlbref	1	60.49	0.07	59.71	0.38	0.00
/usr/bin/dd	1	39.30	26.75	11.82	0.73	0.00
tprof	2	0.21	0.21	0.00	0.33	0.00
Total	20	100.00	27.03	71.53	1.44	0.00

Table 4. An example of the data profiling report for the /usr/bin/dd process.

Process	PID	TID	Total	Kernel	User	Shared	Other
tlbref	327688	757943	60.49	0/07	59.71	0.38	0.00
	Kernel:	0.04%					
	lib:	0.00%					
	u_global:	0.00%					
	stackheap:	u_global:	0.00%				
	unresolved:	99.42%					
tprof	3278000	792863	0.21	0.21	0.00	0.00	0.00
	kernel:	0.20%					
	lib:	0.00%					
	u_global:	0.00%					
	stackheap	0.00%					
	unresolved:	0.01%					
/usr/bin/dd	323768	974985	39.30	26.75	11.82	0.73	0.00
	kernel:	12.86%					
	lib:	0.00%					
	u_global:	7.80%					
	stackheap:	2.42%					
	unresolved:	2.18%					
Total			100.00	27.03	99.01	1.44	0.00

When used with the **-s**, **-u**, **-k** and **-e** flags, the **tprof** command's data profiling reports most-used data structures (exported data symbols) in shared library, binary, kernel and kernel extensions. The **-B** flag also reports the functions that use data structures.

The second table shown is an example of the data profiling report for the /usr/bin/dd process.. The example report shows that `__start` data structure is the most used data structure in the /usr/bin/dd process, based on the samples collected. The data structure is a list of functions (right aligned) that use the data structure, reported along with their share and source as shown in the following example:

Total % For /usr/bin/dd[323768] (/usr/bin/dd) = 11.69

Subroutine	%	Source
.noconv	11.29	/usr/bin/dd
.main	0.14	/usr/bin/dd
.read	0.07	glink.s
.setobuf	0.05	/usr/bin/dd
.rpipe	0.04	/usr/bin/dd
.flush	0.04	/usr/bin/dd
.write	0.04	glink.s
.wbuf	0.02	/usr/bin/dd
.rbuf	0.02	/usr/bin/dd

Data	%	Source
__start	7.80	/usr/bin/dd
.noconv	6.59	/usr/bin/dd
.main	0.14	/usr/bin/dd
.read	0.04	glink.s
.wbuf	0.02	/usr/bin/dd
.write	0.02	glink.s
.flush	0.102	/usr/bin/dd

## Implementation of the tprof command

The **tprof** command uses the system trace facility. Since you can only execute the trace facility one user at a time, you can only execute one **tprof** command at a time.

You can obtain the raw data for the **tprof** command through the trace facility. For more information about the trace facility, see Analyzing Performance with the Trace Facility in *Files Reference*.

When a program is profiled, the trace facility is activated and instructed to collect data from the trace hook with hook ID 234 that records the contents of the Instruction Address Register, or IAR, when a system-clock interrupt occurs (100 times a second per processor). Several other trace hooks are also activated to enable the **tprof** command to track process and dispatch activity. The trace records are not written to a disk file. They are written to a pipe that is read by a program that builds a table of the unique program addresses that have been encountered and the number of times each one occurred. When the workload being profiled is complete, the table of addresses and their occurrence counts are written to disk. The data-reduction component of the **tprof** command then correlates the instruction addresses that were encountered with the ranges of addresses occupied by the various programs and reports the distribution of address occurrences, or *ticks*, across the programs involved in the workload.

The distribution of ticks is roughly proportional to the CPU time spent in each program, which is 10 milliseconds per tick. After the high-use programs are identified, you can take action to restructure the hot spots or minimize their use.

### Example: tprof command

You can view the complete details of the **tprof** command in *Files Reference*.

The following example demonstrates how to collect a CPU tick profile of a program using the **tprof** command. The example was executed on a 4-way SMP system and since it is a fast-running system, the command completed in less than a second. To make this program run longer, the array size, or *Asize*, was changed to 4096 instead of 1024.

Upon running the following command, the **version1.prof** file is created in the current directory:

```
# tprof -z -u -p version1 -x version1
```

The **version1.prof** file reports how many CPU ticks for each of the programs that were running on the system while the **version1** program was running.

The following is an example of what the **version1.prof** file contains:

Process	Freq	Total	Kernel	User	Shared	Other
===== wait	4	5810	5810	0	0	0
./version1	1	1672	35	1637	0	0
/usr/bin/tprof	2	15	13	0	2	0
/etc/syncd	1	2	2	0	0	0
/usr/bin/sh	2	2	2	0	0	0
swapper	1	1	1	0	0	0
/usr/bin/trcstop	1	1	1	0	0	0
rmcd	1	1	1	0	0	0
===== Total	13	7504	5865	1637	2	0

Process	PID	TID	Total	Kernel	User	Shared	Other
===== wait	16392	16393	1874	1874	0	0	0
wait	12294	12295	1873	1873	0	0	0
wait	20490	20491	1860	1860	0	0	0
./version1	245974	606263	1672	35	1637	0	0
wait	8196	8197	203	203	0	0	0
/usr/bin/tprof	291002	643291	13	13	0	0	0
/usr/bin/tprof	274580	610467	2	0	0	2	0
/etc/syncd	73824	110691	2	2	0	0	0
/usr/bin/sh	245974	606263	1	1	0	0	0
/usr/bin/sh	245976	606265	1	1	0	0	0
/usr/bin/trcstop	245976	606263	1	1	0	0	0
swapper	0	3	1	1	0	0	0

```

      rcmd  155876  348337      1      1      0      0      0
=====  ===    ===    =====  =====  =====  =====
      Total                7504    5865    1637      2      0

```

Total Samples = 7504      Total Elapsed Time = 18.76s

Profile: ./version1

Total Ticks For All Processes (./version1) = 1637

```

      Subroutine  Ticks    %      Source  Address  Bytes
=====  =====  =====  =====  =====  =====
      .main      1637    21.82  version1.c    350    536

```

Profile: ./version1

Total Ticks For ./version1[245974] (./version1) = 1637

```

      Subroutine  Ticks    %      Source  Address  Bytes
=====  =====  =====  =====  =====  =====
      .main      1637    21.82  version1.c    350    536

```

The first section of the report summarizes the results by program, regardless of the process ID, or PID. It shows the number of different processes, or Freq, that ran each program at some point.

The second section of the report displays the number of ticks consumed by, or on behalf of, each process. In the example, the **version1** program used 1637 ticks itself and 35 ticks occurred in the kernel on behalf of the **version1** process.

The third section breaks down the user ticks associated with the executable program being profiled. It reports the number of ticks used by each function in the executable program and the percentage of the total run's CPU ticks (7504) that each function's ticks represent. Since the system's CPUs were mostly idle, most of the 7504 ticks are idle ticks.

To see what percentage of the busy time this program took, subtract the wait thread's CPU ticks, which are the idle CPU ticks, from the total and then divide the difference from the total number of ticks.

```

Total number of ticks / (Total - Idle CPU ticks) = % busy time of program
      1637 / (7504 - 5810) =
      1637 / 1694 = 0.97

```

So, the percentage of system busy ticks is 97%.

## The raso tunables

As the root user, you can tune the instruction threshold with the **tprof\_inst\_threshold** tunable of the **raso** command.

As the root user, you can tune the sampling frequency with the following **raso** tunables:

- **tprof\_cyc\_mult**
- **tprof\_evt\_mult**

For example, for events based on processor cycles, setting the **tprof\_cyc\_mult** tunable to 50 and specifying the **-f** flag as 100 is equivalent to specifying a sampling frequency of 100/50 milliseconds.

For other Performance Monitor events, setting the **tprof\_evt\_mult** tunable to 100 and specifying the **-f** flag as 20,000 is equivalent to specifying a sampling frequency of 20,000/100 occurrences.

## Manual offline processing with the tprof command

You can perform offline processing of trace files with the **tprof** command, but you must specify filenames with a *rootstring* name.

Also, there are certain suffixes required for the input files that the **tprof** command uses. For example, the trace binary file must end in *.trc*. Also, you need to collect the **gensyms** command output and put it in a file called the **rootstring.syms** file.

To insure the trace file contains sufficient information to be post-processed by **tprof**, the **trace** command line must include the **-M** and **-j tprof** flags.

If you name the *rootstring* file **trace1**, to collect a trace, you can use the **trace** command using all of the hooks or at least the following hooks:

```
# trace -af -M -T 1000000 -L 10000000 -o trace1.trc -j tprof
# workload
# trcoff
# gensyms > trace1.syms
# trcstop
# trcrpt -r trace1 -k -u -s -z
```

The example above creates a **trace1.prof** file, which gives you a CPU profile of the system while the **trace** command was running.

## X-Windows Performance Profiler (Xprofiler)

The X-Windows Performance Profiler (Xprofiler) tool helps you analyze your parallel or serial application's performance. It uses procedure-profiling information to construct a graphical display of the functions within your application.

X-Windows Performance Profiler (Xprofiler) provides quick access to the profiled data, which lets you identify the functions that are the most CPU-intensive. The graphical user interface (GUI) also lets you manipulate the display in order to focus on the application's critical areas.

The word *function* is used frequently throughout this chapter. Consider it to be synonymous with the terms *routine*, *subroutine*, and *procedure*.

### Xprofiler overview

Xprofiler lets you profile both serial and parallel applications. Serial applications generate a single profile data file, while a parallel application produces multiple profile data files. You can use Xprofiler to analyze the resulting profiling information.

Xprofiler provides a set of resource variables that let you customize some of the features of the Xprofiler window and reports.

### Requirements and limitations:

To use Xprofiler, your application must be compiled with the **-pg** flag.

**Note:** You can generate a new format of the thread-level profiling **gmon.out** files. Xprofiler does not support this new format, so you must set the **GPROF** environment variable to ensure that you produce the previous format of the **gmon.out** files. For more information, please see the **gprof** Command.

Like the **gprof** command, Xprofiler lets you analyze CPU (busy) usage only. It does not provide other kinds of information, such as CPU idle, I/O, or communication information.

If you compile your application on one processor, and then analyze it on another, you must first make sure that both processors have similar library configurations, at least for the system libraries used by the application. For example, if you run a High Performance Fortran application on a server, then try to analyze the profiled data on a workstation, the levels of High Performance Fortran run-time libraries must match and must be placed in a location on the workstation that Xprofiler recognizes. Otherwise, Xprofiler produces unpredictable results.

Because Xprofiler collects data by sampling, functions that run for a short amount of time might not show any CPU use.

Xprofiler does not give you information about the specific threads in a multi-threaded program. Xprofiler presents the data as a summary of the activities of all the threads.

#### **Related concepts:**

“Compiling applications to be profiled”

To use Xprofiler, you must compile and link your application with the **-pg** flag of the compiler command.

#### **Comparing Xprofiler and the gprof command:**

With Xprofiler, you can produce the same tabular reports that you might be accustomed to seeing with the **gprof** command. As with **gprof**, you can generate the Flat Profile, Call Graph Profile, and Function Index reports.

Unlike **gprof**, Xprofiler provides a GUI that you can use to profile your application. Xprofiler generates a graphical display of your application's performance, as opposed to a text-based report. Xprofiler also lets you profile your application at the source statement level.

From the Xprofiler GUI, you can use all of the same command line flags as **gprof**, as well as some additional flags that are unique to Xprofiler.

#### **Compiling applications to be profiled:**

To use Xprofiler, you must compile and link your application with the **-pg** flag of the compiler command.

You must use the **-pg** regardless of whether you are compiling a serial or parallel application. You can compile and link your application all at once, or perform the compile and link operations separately. The following is an example of how you would compile and link all at once:

```
cc -pg -o foo foo.c
```

The following is an example of how you would first compile your application and then link it. To compile, do the following:

```
cc -pg -c foo.c
```

To link, do the following:

```
cc -pg -o foo foo.o
```

Notice that when you compile and link separately, you must use the **-pg** flag with *both* the compile and link commands.

The **-pg** flag compiles and links the application so that when you run it, the CPU usage data is written to one or more output files. For a serial application, this output consists of only one file called **gmon.out**, by default. For parallel applications, the output is written into multiple files, one for each task that is running in the application. To prevent each output file from overwriting the others, the task ID is appended to each **gmon.out** file (for example: **gmon.out.10**).

**Note:** The **-pg** flag is not a combination of the **-p** and the **-g** compiling flags.

To get a complete picture of your parallel application's performance, you must indicate all of its **gmon.out** files when you load the application into Xprofiler. When you specify more than one **gmon.out** file, Xprofiler shows you the sum of the profile information contained in each file.

The Xprofiler GUI lets you view included functions. Your application must also be compiled with the **-g** flag in order for Xprofiler to display the included functions.

In addition to the **-pg** flag, the **-g** flag is also required for source-statement profiling.

**Related concepts:**

“Requirements and limitations” on page 256

To use Xprofiler, your application must be compiled with the **-pg** flag.

## **Xprofiler installation information**

This section contains Xprofiler system requirements, limitations, and information about installing Xprofiler. It also lists the files and directories that are created by installing Xprofiler.

### **Preinstallation information:**

Review the following requirements before you install Xprofiler.

The following are hardware and software requirements for Xprofiler:

#### **Software requirements:**

- X Window System
- X11.Dt.lib 4.2.1.0 or later, if you want to run Xprofiler in the Common Desktop Environment (CDE)

#### **Disk space requirements:**

- 6500 512-byte blocks in the **/usr** directory

#### *Limitations:*

Although it is not required to install Xprofiler on every node, it is advisable to install it on at least one node in each group of nodes that have the same software library levels.

If users plan to collect a **gmon.out** file on one processor and then use Xprofiler to analyze the data on another processor, they should be aware that some shared (system) libraries might not be the same on the two processors. This situation might result in different function-call tree displays for shared libraries.

### **Installing Xprofiler:**

There are two methods to install Xprofiler. One method is by using the **installp** command. The other is by using SMIT.

#### *Using the installp command:*

You can use the **installp** command to install Xprofiler.

To install Xprofiler, type:

```
installp -a -I -X -d device_name xprofiler
```

#### *Using SMIT:*

You can use SMIT to install Xprofiler.

To install Xprofiler using SMIT, do the following:

1. Insert the distribution media in the installation device (unless you are installing over a network).
2. Enter the following:  

```
smit install_latest
```

This command opens the SMIT panel for installing software.

3. Press **List**. A panel lists the available INPUT devices and directories for software.
4. Select the installation device or directory from the list of available INPUT devices. The original SMIT panel indicates your selection.
5. Press **Do**. The SMIT panel displays the default installation parameters.
6. Type:
 

```
xprofiler
```

in the **SOFTWARE to install** field and press **Enter**.

7. Once the installation is complete, press **F10** to exit SMIT.

### Directories and files created by Xprofiler:

Review the follow information about directories and files that are created when you install Xprofiler.

Installing Xprofiler creates the directories and files shown in the following table:

*Table 5. Xprofiler directories and files installed*

Directory or file	Description
/usr/lib/nls/msg/En_US/xprofiler.cat	Message catalog for Xprofiler
/usr/lib/nls/msg/en_US/xprofiler.cat	
/usr/lib/nls/msg/C/xprofiler.cat	
/usr/xprofiler/defaults/Xprofiler.ad	Defaults file for X-Windows and Motif resource variables
/usr/xprofiler/bin/.startup_script	Startup script for Xprofiler
/usr/xprofiler/bin/xprofiler	Xprofiler exec file
/usr/xprofiler/help/en_US/xprofiler.sdl	Online help
/usr/xprofiler/help/en_US/xprofiler_msg.sdl	
/usr/xprofiler/help/en_US/graphics	
/usr/xprofiler/README/xprofiler.README	Installation readme file
/usr/xprofiler/samples	Directory containing sample programs

The following symbolic link is made during the installation process of Xprofiler:

This link:	To:
/usr/lpp/X11/lib/X11/app-defaults/Xprofiler	/usr/xprofiler/defaults/Xprofiler.ad
/usr/bin/xprofiler	/usr/xprofiler/bin.startup_script

### Starting the Xprofiler GUI

To start Xprofiler, enter the **xprofiler** command on the command line.

You must also specify the binary executable file, one or more profile data files, and optionally, one or more flags, which you can do in one of two ways. You can either specify the files and flags on the command line along with the **xprofiler** command, or you can enter the **xprofiler** command alone, then specify the files and flags from within the GUI.

You will have more than one **gmon.out** file if you are profiling a parallel application, because a **gmon.out** file is created for each task in the application when it is run. If you are running a serial application, there might be times when you want to summarize the profiling results from multiple runs of the application. In these cases, you must specify each of the profile data files you want to profile with Xprofiler.

To start Xprofiler and specify the binary executable file, one or more profile data files, and one or more flags, type:

```
xprofiler a.out gmon.out... [flag...]
```

where: **a.out** is the binary executable file, **gmon.out...** is the name of your profile data file (or files), and *flag...* is one or more of the flags listed in the following section on Xprofiler command-line flags.

### Xprofiler command line flags:

You can specify the same command-line flags with the **xprofiler** command that you do with **gprof**, as well as one additional flag (**-disp\_max**), which is specific to Xprofiler.

The command line flags let you control the way Xprofiler displays the profiled output.

You can specify the flags in Table 6 from the command line or from the Xprofiler GUI (see “Specifying command line options (from the GUI)” on page 267 for more information).

Table 6. Xprofiler command-line flags

Use this flag:	To:	For example:
<b>-a</b>	Add alternative paths to search for source code and library files, or changes the current path search order. When using this flag, you can use the "at" symbol (@) to represent the default file path, in order to specify that other paths be searched before the default path.	To set an alternative file search path so that Xprofiler searches <b>pathA</b> , the default path, then <b>pathB</b> , type: <code>xprofiler -a pathA:@:pathB</code>
<b>-b</b>	Suppress the printing of the field descriptions for the <b>Flat Profile</b> , <b>Call Graph Profile</b> , and <b>Function Index</b> reports when they are written to a file with the <b>Save As</b> option of the <b>File</b> menu.	Type: <code>xprofiler -b a.out gmon.out</code>
<b>-c</b>	Load the specified configuration file. If this flag is used on the command line, the configuration file name specified with it will appear in the <b>Configuration File (-c)</b> : text field in <b>Load Files Dialog</b> window and in the <b>Selection</b> field of the <b>Load Configuration File Dialog</b> window. When both the <b>-c</b> and <b>-disp_max</b> flags are specified on the command line, the <b>-disp_max</b> flag is ignored, but the value that was specified with it will appear in the <b>Initial Display (-disp_max)</b> : field in the <b>Load Files Dialog</b> window the next time this window is opened.	To load the configuration file <b>myfile.cfg</b> , type: <code>xprofiler a.out gmon.out -c myfile.cfg</code>
<b>-disp_max</b>	Set the number of function boxes that Xprofiler initially displays in the function call tree. The value supplied with this flag can be any integer between 0 and 5000. Xprofiler displays the function boxes for the most CPU-intensive functions through the number you specify. For example, if you specify 50, Xprofiler displays the function boxes for the 50 functions in your program with the highest CPU usage. After this, you can change the number of function boxes that are displayed using the <b>Filter</b> menu options. This flag has no effect on the content of any of the Xprofiler reports.	To display the function boxes for the 50 most CPU-intensive functions in the function call tree, type: <code>xprofiler -disp_max 50 a.out gmon.out</code>
<b>-e</b>	Deemphasize the general appearance of the function box for the specified function in the function call tree, and limits the number of entries for this function in the <b>Call Graph Profile</b> report. This also applies to the specified function's descendants, as long as they have not been called by non-specified functions.  In the function call tree, the function box for the specified function is made unavailable. The box size and the content of the label remain the same. This also applies to descendant functions, as long as they have not been called by non-specified functions.  In the <b>Call Graph Profile</b> report, an entry for a specified function only appears where it is a child of another function, or as a parent of a function that also has at least one non-specified function as its parent. The information for this entry remains unchanged. Entries for descendants of the specified function do not appear unless they have been called by at least one non-specified function in the program.	To deemphasize the appearance of the function boxes for <b>foo</b> and <b>bar</b> and their qualifying descendants in the function call tree, and limit their entries in the <b>Call Graph Profile</b> report, type: <code>xprofiler -e foo -e bar a.out gmon.out</code>

Table 6. Xprofiler command-line flags (continued)

Use this flag:	To:	For example:
-E	<p>Change the general appearance and label information of the function box for the specified function in the function call tree. This flag also limits the number of entries for this function in the <b>Call Graph Profile</b> report, and changes the CPU data associated with them. These results also apply to the specified function's descendants, as long as they have not been called by non-specified functions in the program.</p> <p>In the function call tree, the function box for the specified function is made unavailable, and the box size and shape also changes so that it appears as a square of the smallest permitted size. In addition, the CPU time shown in the function box label, appears as <b>0</b>. The same applies to function boxes for descendant functions, as long as they have not been called by non-specified functions. This flag also causes the CPU time spent by the specified function to be deducted from the CPU total on the left in the label of the function box for each of the specified function's ancestors.</p> <p>In the <b>Call Graph Profile</b> report, an entry for the specified function only appears where it is a child of another function, or as a parent of a function that also has at least one non-specified function as its parent. When this is the case, the time in the <b>self</b> and <b>descendants</b> columns for this entry is set to <b>0</b>. In addition, the amount of time that was in the <b>descendants</b> column for the specified function is subtracted from the time listed under the <b>descendants</b> column for the profiled function. As a result, be aware that the value listed in the <b>% time</b> column for most profiled functions in this report will change.</p>	<p>To change the display and label information for <b>foo</b> and <b>bar</b>, as well as their qualifying descendants in the function call tree, and limit their entries and data in the <b>Call Graph Profile</b> report, type: <code>xprofiler -E foo -E bar a.out gmon.out</code></p>
-f	<p>Deemphasize the general appearance of all function boxes in the function call tree, <i>except</i> for that of the specified function and its descendants. In addition, the number of entries in the <b>Call Graph Profile</b> report for the non-specified functions and non-descendant functions is limited. The <b>-f</b> flag overrides the <b>-e</b> flag.</p> <p>In the function call tree, all function boxes <i>except</i> for that of the specified function and its descendants are made unavailable. The size of these boxes and the content of their labels remain the same. For the specified function and its descendants, the appearance of the function boxes and labels remain the same.</p> <p>In the <b>Call Graph Profile</b> report, an entry for a non-specified or non-descendant function only appears where it is a parent or child of a specified function or one of its descendants. All information for this entry remains the same.</p>	<p>To deemphasize the display of function boxes for all functions in the function call tree <i>except</i> for <b>foo</b>, <b>bar</b>, and their descendants, and limit their types of entries in the <b>Call Graph Profile</b> report, type: <code>xprofiler -f foo -f bar a.out gmon.out</code></p>
-F	<p>Change the general appearance and label information of all function boxes in the function call tree <i>except</i> for that of the specified function and its descendants. In addition, the number of entries in the <b>Call Graph Profile</b> report for the non-specified and non-descendant functions is limited, and the CPU data associated with them is changed. The <b>-F</b> flag overrides the <b>-E</b> flag.</p> <p>In the function call tree, the function box for the specified function are made unavailable, and its size and shape also changes so that it appears as a square of the smallest permitted size. In addition, the CPU time shown in the function box label, appears as <b>0</b>.</p> <p>In the <b>Call Graph Profile</b> report, an entry for a non-specified or non-descendant function only appears where it is a parent or child of a specified function or one of its descendants. When this is the case, the time in the <b>self</b> and <b>descendants</b> columns for this entry is set to <b>0</b>. As a result, be aware that the value listed in the <b>% time</b> column for most profiled functions in this report will change.</p>	<p>To change the display and label information of the function boxes for all functions <i>except</i> the functions <b>foo</b> and <b>bar</b> and their descendants, and limit their types of entries and data in the <b>Call Graph Profile</b> report, type: <code>xprofiler -F foo -F bar a.out gmon.out</code></p>

Table 6. Xprofiler command-line flags (continued)

Use this flag:	To:	For example:
<b>-h</b>   <b>-?</b>	Display the <b>xprofiler</b> command's usage statement.	<code>xprofiler -h</code>  Usage: <code>xprofiler [program] [-b] [-h] [-s] [-z] [-a path(s)] [-c file] [-L pathname] [[-e function]...] [[-E function]...] [[-f function]...] [[-F function]...] [-disp_max number_of_functions] [[gmon.out]...]</code>
<b>-L</b>	Specify an alternative path name for locating shared libraries. If you plan to specify multiple paths, use the <b>Set File Search Path</b> option of the <b>File</b> menu on the Xprofiler GUI. See "Setting the file search sequence" on page 270 for more information.	To specify <code>/lib/profiled/libc.a:shr.o</code> as an alternative path name for your shared libraries, type: <code>xprofiler -L /lib/profiled/libc.a:shr.o</code>
<b>-s</b>	Produce the <b>gmon.sum</b> profile data file (if multiple <b>gmon.out</b> files are specified when Xprofiler is started). The <b>gmon.sum</b> file represents the sum of the profile information in all the specified profile files. Note that if you specify a single <b>gmon.out</b> file, the <b>gmon.sum</b> file contains the same data as the <b>gmon.out</b> file.	To write the sum of the data from three profile data files, <b>gmon.out.1</b> , <b>gmon.out.2</b> , and <b>gmon.out.3</b> , into a file called <b>gmon.sum</b> , type: <code>xprofiler -s a.out gmon.out.1 gmon.out.2 gmon.out.3</code>
<b>-z</b>	Include functions that have both zero CPU usage and no call counts in the <b>Flat Profile</b> , <b>Call Graph Profile</b> , and <b>Function Index</b> reports. A function will not have a call count if the file that contains its definition was not compiled with the <b>-pg</b> flag, which is common with system library files.	To include all functions used by the application that have zero CPU usage and no call counts in the <b>Flat Profile</b> , <b>Call Graph Profile</b> , and <b>Function Index</b> reports, type: <code>xprofiler -z a.out gmon.out</code>

After you enter the **xprofiler** command, the Xprofiler main window appears and displays your application's data.

### Loading files from the Xprofiler GUI:

If you enter the **xprofiler** command on its own, you can then specify an executable file, one or more profile data file, and any flags, from within the Xprofiler GUI. You use the **Load File** option of the **File** menu to do this.

If you enter the **xprofiler -h** or **xprofiler -?** command, Xprofiler displays the usage statement for the command and then exits.

When you enter the **xprofiler** command alone, the Xprofiler main window appears. Because you did not load an executable file or specify a profile data file, the window will be empty, as shown below.




Figure 16. The Xprofiler main window.

From the Xprofiler GUI, select **File**, then **Load File** from the menu bar. The Load Files Dialog window will appear, as shown below.




Figure 17. The Load Files Dialog window

The Load Files Dialog window lets you specify your application's executable file and its corresponding profile data (**gmon.out**) files. When you load a file, you can also specify the various command-line options that let you control the way Xprofiler displays the profiled data.

To load the files for the application you want to profile, you must specify the following:

- the binary executable file

- one or more profile data files

Optionally, you can also specify one or more command-line flags.

*The binary executable file:*

You can specify the binary executable file from the **Binary Executable File:** area of the Load Files Dialog window.




Figure 18. The Binary Executable File dialog

Use the scroll bars of the **Directories** and **Files** selection boxes to locate the executable file you want to load. By default, all of the files in the directory from which you called Xprofiler appear in the **Files** selection box.

To make locating your binary executable files easier, the **Binary Executable File:** area includes a **Filter** button. Filtering lets you limit the files that are displayed in the **Files** selection box to those of a specific directory or of a specific type. For information about filtering, see “Filtering what you see” on page 278.

Profile data files:

You can specify one or more profile data files from the **gmon.out Profile Data File(s)** area of the Load Files Dialog window.




Figure 19. The *gmon.out* Profile Data File area

When you start Xprofiler using the **xprofiler** command, you are not required to indicate the name of the profile data file. If you do not specify a profile data file, Xprofiler searches your directory for the presence of a file named **gmon.out** and, if found, places it in the **Selection** field of the **gmon.out Profile Data File(s)** area, as the default. Xprofiler then uses this file as input, even if it is not related to the binary executable file you specify. Because this will cause Xprofiler to display incorrect data, it is important that you enter the correct file into this field. If the profile data file you want to use is named something other than what appears in the **Selection** field, you must replace it with the correct file name.

Use the scroll bars of the **Directories** and **Files** selection boxes to locate one or more of the profile data (**gmon.out**) files you want to specify. The file you use does not have to be named **gmon.out**, and you can specify more than one profile data file.

To make locating your output files easier, the **gmon.out Profile Data File(s)** area includes a **Filter** button. Filtering lets you limit the files that are displayed in the **Files** selection box to those in a specific directory or of a specific type. For information about filtering, see “Filtering what you see” on page 278.

Specifying command line options (from the GUI):

Specify command line flags from the **Command Line Options** area of the Load Files Dialog window.




Figure 20. The Command Line Options area

You can specify one or more flags as follows:

Table 7. Xprofiler GUI command-line flags

Use this flag:	To:	For example:
-a (field)	Add alternative paths to search for source code and library files, or changes the current path search order. After clicking the <b>OK</b> button, any modifications to this field are also made to the <b>Enter Alt File Search Paths:</b> field of the Alt File Search Path Dialog window. If both the Load Files Dialog window and the Alt File Search Path Dialog window are opened at the same time, when you make path changes in the Alt File Search Path Dialog window and click <b>OK</b> , these changes are also made to the Load Files Dialog window. Also, when both of these windows are open at the same time, clicking the <b>OK</b> or <b>Cancel</b> buttons in the Load Files Dialog window causes both windows to close. If you want to restore the <b>Alt File Search Path(s) (-a):</b> field to the same state as when the Load Files Dialog window was opened, click the <b>Reset</b> button.  You can use the “at” symbol (@) with this flag to represent the default file path, in order to specify that other paths be searched before the default path.	To set an alternative file search path so that Xprofiler searches <b>pathA</b> , the default path, then <b>pathB</b> , type <b>pathA:@:pathB</b> in the <b>Alt File Search Path(s) (-a)</b> field.
-b (button)	Suppress the printing of the field descriptions for the <b>Flat Profile</b> , <b>Call Graph Profile</b> , and <b>Function Index</b> reports when they are written to a file with the <b>Save As</b> option of the <b>File</b> menu.	To suppress printing of the field descriptions for the <b>Flat Profile</b> , <b>Call Graph Profile</b> , and <b>Function Index</b> reports in the saved file, set the <b>-b</b> button to the pressed-in position.

Table 7. Xprofiler GUI command-line flags (continued)

Use this flag:	To:	For example:
-c (field)	<p>Load the specified configuration file. If the -c option was used on the command line, or a configuration file had been previously loaded with the Load Files Dialog window or the Load Configuration File Dialog window, the name of the most recently loaded file will appear in the <b>Configuration File (-c):</b> text field in the Load Files Dialog window, as well as the <b>Selection</b> field of Load Files Dialog window. If the Load Files Dialog window and the Load Files Dialog window are open at the same time, when you specify a configuration file in the Load Configuration File Dialog window and then click the <b>OK</b> button, the name of the specified file also appears in the Load Files Dialog window. Also, when both of these windows are open at the same time, clicking the <b>OK</b> or <b>Cancel</b> button in the Load Files Dialog window causes both windows to close. When entries are made to both the <b>Configuration File (-c):</b> and <b>Initial Display (-disp_max):</b> fields in the Load Files Dialog window, the value in the <b>Initial Display (-disp_max):</b> field is ignored, but is retained the next time this window is opened. If you want to retrieve the file name that was in the <b>Configuration File (-c):</b> field when the Load Files Dialog window was opened, click the <b>Reset</b> button.</p>	<p>To load the configuration file <b>myfile.cfg</b>, type <b>myfile.cfg</b> in the <b>Configuration File (-c)</b> field.</p>
-disp_max (field)	<p>Set the number of function boxes that Xprofiler initially displays in the function call tree. The value supplied with this flag can be any integer between 0 and 5000. Xprofiler displays the function boxes for the most CPU-intensive functions through the number you specify. For example, if you specify 50, Xprofiler displays the function boxes for the 50 functions in your program with the highest CPU usage. After this, you can change the number of function boxes that are displayed using the <b>Filter</b> menu options. This flag has no effect on the content of any of the Xprofiler reports.</p>	<p>To display the function boxes for the 50 most CPU-intensive functions in the function call tree, type 50 in the <b>Init Display (-disp_max)</b> field.</p>
-e (field)	<p>Deemphasize the general appearance of the function box for the specified function in the function call tree, and limits the number of entries for this function in the <b>Call Graph Profile</b> report. This also applies to the specified function's descendants, as long as they have not been called by non-specified functions.</p> <p>In the function call tree, the function box for the specified function is made unavailable. The box size and the content of the label remain the same. This also applies to descendant functions, as long as they have not been called by non-specified functions.</p> <p>In the <b>Call Graph Profile</b> report, an entry for a specified function only appears where it is a child of another function, or as a parent of a function that also has at least one non-specified function as its parent. The information for this entry remains unchanged. Entries for descendants of the specified function do not appear unless they have been called by at least one non-specified function in the program.</p>	<p>To deemphasize the appearance of the function boxes for <b>foo</b> and <b>bar</b> and their qualifying descendants in the function call tree, and limit their entries in the <b>Call Graph Profile</b> report, type <b>foo</b> and <b>bar</b> in the <b>Exclude Routines (-e)</b> field.</p> <p>Multiple functions are separated by a space.</p>

Table 7. Xprofiler GUI command-line flags (continued)

Use this flag:	To:	For example:
<p>-E (field)</p>	<p>Change the general appearance and label information of the function box for the specified function in the function call tree. This flag also limits the number of entries for this function in the <b>Call Graph Profile</b> report, and changes the CPU data associated with them. These results also apply to the specified function's descendants, as long as they have not been called by non-specified functions in the program.</p> <p>In the function call tree, the function box for the specified function appears greyed out, and the box size and shape also changes so that it appears as a square of the smallest permitted size. In addition, the CPU time shown in the function box label, appears as 0. The same applies to function boxes for descendant functions, as long as they have not been called by non-specified functions. This flag also causes the CPU time spent by the specified function to be deducted from the CPU total on the left in the label of the function box for each of the specified function's ancestors.</p> <p>In the <b>Call Graph Profile</b> report, an entry for the specified function only appears where it is a child of another function, or as a parent of a function that also has at least one non-specified function as its parent. When this is the case, the time in the self and descendants columns for this entry is set to 0. In addition, the amount of time that was in the descendants column for the specified function is subtracted from the time listed under the descendants column for the profiled function. As a result, be aware that the value listed in the % time column for most profiled functions in this report will change.</p>	<p>To change the display and label information for <b>foo</b> and <b>bar</b> and their qualifying descendants in the function call tree, and limit their entries and data in the <b>Call Graph Profile</b> report, type foo bar in the <b>Exclude Routines (-E)</b> field.</p> <p>Multiple functions are separated by a space.</p>
<p>-f (field)</p>	<p>Deemphasize the general appearance of all function boxes in the function call tree, <i>except</i> for that of the specified function and its descendants. In addition, the number of entries in the <b>Call Graph Profile</b> report for the non-specified functions and non-descendant functions is limited. The <b>-f</b> flag overrides the <b>-e</b> flag.</p> <p>In the function call tree, all function boxes <i>except</i> for that of the specified function and its descendants are made unavailable. The size of these boxes and the content of their labels remain the same. For the specified function and its descendants, the appearance of the function boxes and labels remain the same.</p> <p>In the <b>Call Graph Profile</b> report, an entry for a non-specified or non-descendant function only appears where it is a parent or child of a specified function or one of its descendants. All information for this entry remains the same.</p>	<p>To deemphasize the display of function boxes for all functions in the function call tree <i>except</i> for <b>foo</b> and <b>bar</b> and their descendants, and limit their types of entries in the <b>Call Graph Profile</b> report, type foo bar in the <b>Include Routines (-f)</b> field.</p> <p>Multiple functions are separated by a space.</p>

Table 7. Xprofiler GUI command-line flags (continued)

Use this flag:	To:	For example:
-F (field)	<p>Change the general appearance and label information of all function boxes in the function call tree <i>except</i> for that of the specified function and its descendants. In addition, the number of entries in the <b>Call Graph Profile</b> report for the non-specified and non-descendant functions is limited, and the CPU data associated with them is changed. The <b>-F</b> flag overrides the <b>-E</b> flag.</p> <p>In the function call tree, the function box for the specified function is made unavailable, and its size and shape also changes so that it appears as a square of the smallest permitted size. In addition, the CPU time shown in the function box label, appears as 0.</p> <p>In the <b>Call Graph Profile</b> report, an entry for a non-specified or non-descendant function only appears where it is a parent or child of a specified function or one of its descendants. When this is the case, the time in the self and descendants columns for this entry is set to 0. As a result, be aware that the value listed in the % time column for most profiled functions in this report will change.</p>	<p>To change the display and label information of the function boxes for all functions <i>except</i> the functions <b>foo</b> and <b>bar</b> and their descendants, and limit their types of entries and data in the <b>Call Graph Profile</b> report, type <b>foo bar</b> in the <b>Include Routines (-F)</b> field.</p> <p>Multiple functions are separated by a space.</p>
-L (field)	<p>Set the alternative path name for locating shared objects. If you plan to specify multiple paths, use the <b>Set File Search Path</b> option of the <b>File</b> menu on the Xprofiler GUI. See "Setting the file search sequence" for information.</p>	<p>To specify <b>/lib/profiled/libc.a:shr.o</b> as an alternative path name for your shared libraries, type <b>/lib/profiled/libc.a:shr.o</b> in this field.</p>
-s (button)	<p>Produces the <b>gmon.sum</b> profile data file, if multiple <b>gmon.out</b> files are specified when Xprofiler is started. The <b>gmon.sum</b> file represents the sum of the profile information in all the specified profile files. Note that if you specify a single <b>gmon.out</b> file, the <b>gmon.sum</b> file contains the same data as the <b>gmon.out</b> file.</p>	<p>To write the sum of the data from three profile data files, <b>gmon.out.1</b>, <b>gmon.out.2</b>, and <b>gmon.out.3</b>, into a file called <b>gmon.sum</b>, set the <b>-s</b> button to the pressed-in position.</p>
-z (button)	<p>Includes functions that have both zero CPU usage and no call counts in the <b>Flat Profile</b>, <b>Call Graph Profile</b>, and <b>Function Index</b> reports. A function will not have a call count if the file that contains its definition was not compiled with the <b>-pg</b> flag, which is common with system library files.</p>	<p>To include all functions used by the application that have zero CPU usage and no call counts in the <b>Flat Profile</b>, <b>Call Graph Profile</b>, and <b>Function Index</b> reports, set the <b>-z</b> button to the pressed-in position.</p>

After you have specified the binary executable file, one or more profile data files, and any command-line flags you want to use, click the **OK** button to save the changes and close the window. Xprofiler loads your application and displays its performance data.

### Setting the file search sequence:

You can specify where you want Xprofiler to look for your library files and source code files by using the **Set File Search Paths** option of the **File** menu.

By default, Xprofiler searches the default paths first and then any alternative paths you specify.

#### Default paths:

For library files, Xprofiler uses the paths recorded in the specified **gmon.out** files.

If you use the **-L** flag, the path you specify with it will be used instead of those in the **gmon.out** files.

**Note:** The **-L** flag enables only one path to be specified, and you can use this flag only once.

For source code files, the paths recorded in the specified **a.out** file are used.

#### *Alternative paths:*

You specify the alternative paths with the **Set File Search Paths** option of the **File** menu.

For library files, if everything else failed, the search will be extended to the path (or paths) specified by the LIBPATH environment variable associated with the executable file.

To specify alternative paths, do the following:

1. Select the **File** menu, and then the **Set File Search Paths** option. The Alt File Search Path Dialog window appears.
2. Enter the name of the path in the **Enter Alt File Search Path(s)** text field. You can specify more than one path by separating each path name with a colon (:) or a space.

#### **Note:**

- a. You can use the “at” symbol (@) with this option to represent the default file path, in order to specify that other paths be searched before the default path. For example, to set the alternative file search paths so that Xprofiler searches **pathA**, the default path, then **pathB**, type **pathA:@:pathB** in the **Alt File Search Path(s) (-a)** field.
  - b. If @ is used in the alternative search path, the two buttons in the Alt File Search Path Dialog window will be unavailable, and will have no effect on the search order.
3. Click the **OK** button. The paths you specified in the text field become the alternative paths.

#### *Changing the search sequence:*

You can change the order of the search sequence for library files and source code files using the **Set File Search Paths** option of the **File** menu.

To change the search sequence, complete the following steps.

1. Select the **File** menu, and then the **Set File Search Paths** option. The Alt File Search Path Dialog window appears.
2. To indicate that the file search should use alternative paths first, click the **Check alternative path(s) first** button.
3. Click **OK**. This changes the search sequence to the following:
  - a. Alternative paths
  - b. Default paths
  - c. Paths specified in LIBPATH (library files only)

To return the search sequence back to its default order, repeat steps 1 through 3, but in step 2, click the **Check default path(s) first** button. When the action is confirmed (by clicking **OK**), the search sequence will start with the default paths again.

If a file is found in one of the alternative paths or a path in LIBPATH, this path now becomes the default path for this file throughout the current Xprofiler session (until you exit this Xprofiler session or load a new set of data).

## **Understanding the Xprofiler display**

The primary difference between Xprofiler and the **gprof** command is that Xprofiler gives you a graphical picture of your application's CPU consumption in addition to textual data.

Xprofiler displays your profiled program in a single main window. It uses several types of graphical images to represent the relevant parts of your program. Functions appear as solid green boxes (called

function boxes), and the calls between them appear as blue arrows (called *call arcs*). The function boxes and call arcs that belong to each library within your application appear within a fenced-in area called a *cluster box*.

### Xprofiler main window:

The Xprofiler main window contains a graphical representation of the functions and calls within your application, as well as their interrelationships. The window provides six menus, including one for online help.

When an application has been loaded, the Xprofiler main window looks similar to the following:




Figure 21. The Xprofiler main window with application loaded

In the main window, Xprofiler displays the *function call tree*. The function call tree displays the function boxes, call arcs, and cluster boxes that represent the functions within your application.

**Note:** When Xprofiler first opens, by default, the function boxes for your application will be *clustered* by library. A cluster box appears around each library, and the function boxes and arcs within the cluster box are reduced in size. To see more detail, you must uncluster the functions. To do this, select the **File** menu and then the **Uncluster Functions** option.

*Xprofiler's main menus:*

The following are part of Xprofiler's main menu.

*The file menu:*

The File menu lets you specify the executable (**a.out**) files and profile data (**gmon.out**) files that Xprofiler will use. It also lets you control how your files are accessed and saved.

*The view menu:*

The View menu lets you focus on specific portions of the function call tree in order to get a better view of the application's critical areas.

*The filter menu:*

The Filter menu lets you add, remove, and change specific parts of the function call tree. By controlling what Xprofiler displays, you can focus on the objects that are most important to you.

*The report menu:*

The report menu provides several types of profiled data in a textual and tabular format.

In addition to presenting the profiled data, the options of the Report menu let you do the following:

- Display textual data
- Save it to a file
- View the corresponding source code
- Locate the corresponding function box or call arc in the function call tree

*The utility menu:*

The Utility menu contains one option, **Locate Function By Name**, which lets you highlight a particular function in the function call tree.

*Xprofiler's hidden menus:*

*The function menu:*

The Function menu lets you perform a number of operations for any of the functions shown in the function call tree.

You can access statistical data, look at source code, and control which functions are displayed.

The Function menu is not visible from the Xprofiler window. You access it by right-clicking on the function box of the function in which you are interested. By doing this, you open the Function menu, and select this function as well. Then, when you select actions from the Function menu, the actions are applied to this function.

### *The arc menu:*

The Arc menu lets you locate the caller and callee functions for a particular *call arc*. A call arc is the representation of a call between two functions within the function call tree.

The Arc menu is not visible from the Xprofiler window. You access it by right-clicking on the call arc in which you are interested. By doing this, you open the Arc menu, and select that call arc as well. Then, when you perform actions with the Arc menu, they are applied to that call arc.

### *The cluster node menu:*

The cluster node menu lets you control the way your libraries are displayed by Xprofiler.

To access the Cluster Node menu, the function boxes in the function call tree must first be clustered by library. For information about clustering and unclustering the function boxes of your application, see “Clustering libraries” on page 283. When the function call tree is clustered, all the function boxes within each library appear within a *cluster box*.

The Cluster Node menu is not visible from the Xprofiler window. You access it by right-clicking on the edge of the cluster box in which you are interested. By doing this, you open the Cluster Node menu, and select that cluster as well. Then, when you perform actions with the Cluster Node menu, they are applied to the functions within that library cluster.

### *The display status field:*

The display status field is at the bottom of the Xprofiler window.

The display status field provides the following information:

- Name of your application
- Number of **gmon.out** files used in this session
- Total amount of CPU used by the application
- Number of functions and calls in your application, and how many of these are currently displayed

### *How functions are represented:*

Functions are represented by solid green boxes in the function call tree.

The size and shape of each function box indicates its CPU usage. The height of each function box represents the amount of CPU time it spent on executing itself. The width of each function box represents the amount of CPU time it spent executing itself, plus its descendant functions.

This type of representation is known as *summary mode*. In summary mode, the size and shape of each function box is determined by the total CPU time of multiple **gmon.out** files used on that function alone, and the total time used by the function and its descendant functions. A function box that is wide and flat represents a function that uses a relatively small amount of CPU on itself (it spends most of its time on its descendants). The function box for a function that spends most of its time executing only itself will be roughly square-shaped.

Functions can also be represented in *average mode*. In average mode, the size and shape of each function box is determined by the average CPU time used on that function alone, among all loaded **gmon.out** files, and the standard deviation of CPU time for that function among all loaded **gmon.out** files. The height of each function node represents the average CPU time, among all the input **gmon.out** files, used on the function itself. The width of each node represents the standard deviation of CPU time, among the **gmon.out** files, used on the function itself. The average mode representation is available only when more

than one **gmon.out** file is entered. For more information about summary mode and average mode, see “Controlling the representation of the function call tree” on page 277.

Under each function box in the function call tree is a label that contains the name of the function and related CPU usage data. For information about the function box labels, see “Obtaining basic data” on page 288.

The following figure shows the function boxes for two functions, **sub1** and **printf**, as they would appear in the Xprofiler display.




Figure 22. Function boxes and arcs in the Xprofiler display

Each function box has its own menu. To access it, place your mouse cursor over the function box of the function you are interested in and press the right mouse button. Each function also has an information box that lets you get basic performance numbers quickly. To access the information box, place your mouse cursor over the function box of the function you are interested in and press the left mouse button.

*How calls between functions are depicted:*

The calls made between each of the functions in the function call tree are represented by blue arrows extending between their corresponding function boxes.

These lines are called *call arcs*. Each call arc appears as a solid blue line between two functions. The arrowhead indicates the direction of the call; the function represented by the function box it points to is the one that receives the call. The function making the call is known as the *caller*, while the function receiving the call is known as the *callee*.

Each call arc includes a numeric label that indicates how many calls were exchanged between the two corresponding functions.

Each call arc has its own menu that lets you locate the function boxes for its caller and callee functions. To access it, place your mouse cursor over the call arc for the call in which you are interested, and press the right mouse button. Each call arc also has an information box that shows you the number of times the caller function called the callee function. To access the information box, place your mouse cursor over the call arc for the call in which you are interested, and press the left mouse button.

*How library clusters are represented:*

Xprofiler lets you collect the function boxes and call arcs that belong to each of your shared libraries into *cluster boxes*.

Because there will be a box around each library, the individual function boxes and call arcs will be difficult to see. If you want to see more detail, you must uncluster the function boxes. To do this, select the Filter menu and then the **Uncluster Functions** option.

When viewing function boxes within a cluster box, note that the size of each function box is relative to those of the other functions within the same library cluster. On the other hand, when all the libraries are unclustered, the size of each function box is relative to all the functions in the application (as shown in the function call tree).

Each library cluster has its own menu that lets you manipulate the cluster box. To access it, place your mouse cursor over the edge of the cluster box you are interested in, and press the right mouse button. Each cluster also has an information box that shows you the name of the library and the total CPU usage (in seconds) consumed by the functions within it. To access the information box, place your mouse cursor over the edge of the cluster box you are interested in and press the left mouse button.

## Controlling how the display is updated

The **Utility** menu of the Overview Window lets you choose the mode in which the display is updated.

The default is the **Immediate Update** option, which causes the display to show you the items in the highlight area as you are moving it around. The **Delayed Update** option, on the other hand, causes the display to be updated only when you have moved the highlight area over the area in which you are interested, and released the mouse button. The **Immediate Update** option applies only to what you see when you move the highlight area; it has no effect on the resizing of items in highlight area, which is always delayed.

## Other viewing options

Xprofiler lets you change the way it displays the function call tree, based on your personal preferences.

### Controlling the graphic style of the function call tree:

You can choose between two-dimensional and three-dimensional function boxes in the function call tree.

The default style is two-dimensional. To change to three-dimensional, select the **View** menu, and then the **3-D Image** option. The function boxes in the function call tree now appear in three-dimensional format.

## Controlling the orientation of the function call tree:

You can choose to have Xprofiler display the function call tree in either top-to-bottom or left-to-right format.

The default is top-to-bottom. To see the function call tree displayed in left-to-right format, select the **View** menu, and then the **Layout: Left→Right** option. The function call tree now displays in left-to-right format, as shown below.




Figure 23. Left-to-right format

## Controlling the representation of the function call tree:

You can choose to have Xprofiler represent the function call tree in either *summary mode* or *average mode*.

When you select the **Summary Mode** option of the View menu, the size and shape of each function box is determined by the total CPU time of multiple **gmon.out** files used on that function alone, and the total time used by the function and its descendant functions. The height of each function node represents the total CPU time used on the function itself. The width of each node represents the total CPU time used on

the function and its descendant functions. When the display is in summary mode, the **Summary Mode** option is unavailable and the **Average Mode** option is activated.

When you select the **Average Mode** option of the View menu, the size and shape of each function box is determined by the average CPU time used on that function alone, among all loaded **gmon.out** files, and the standard deviation of CPU time for that function among all loaded **gmon.out** files. The height of each function node represents the average CPU time, among all the input **gmon.out** files, used on the function itself. The width of each node represents the standard deviation of CPU time, among the **gmon.out** files, used on the function itself.

The purpose of average mode is to reveal workload balancing problems when an application is involved with multiple **gmon.out** files. In general, a function node with large standard deviation has a wide width, and a node with small standard deviation has a slim width.

Both summary mode and average mode affect only the appearance of the function call tree and the labels associated with it. All the performance data in Xprofiler reports and code displays are always summary data. If only one **gmon.out** file is specified, **Summary Mode** and **Average Mode** will be unavailable, and the display is always in **Summary Mode**.

## Filtering what you see

When Xprofiler first opens, the entire function call tree appears in the main window.

This includes the function boxes and call arcs that belong to your executable file as well as the shared libraries that it uses. You can simplify what you see in the main window, and there are several ways to do this.

**Note:** Filtering options of the Filter menu let you change the appearance only of the function call tree. The performance data contained in the reports (through the Reports menu) is not affected.

### Restoring the status of the function call tree:

Xprofiler enables you to undo operations that involve adding or removing nodes and arcs from the function call tree.

When you undo an operation, you reverse the effect of any operation which adds or removes function boxes or call arcs to the function call tree. When you select the **Undo** option, the function call tree is returned to its appearance just prior to the performance of the add or remove operation. To undo an operation, select the **Filter** menu, and then the **Undo** option. The function call tree is returned to its appearance just prior to the performance of the add or remove operation.

Whenever you invoke the **Undo** option, the function call tree loses its zoom focus and zooms all the way out to reveal the entire function call tree in the main display. When you start Xprofiler, the **Undo** option is unavailable. It is activated only after an add or remove operation involving the function call tree takes place. After you undo an operation, the option is made unavailable again until the next add or remove operation takes place.

The options that activate the **Undo** option include the following:

- In the main **File** menu:
  - Load Configuration
- In the main **Filter** menu:
  - Show Entire Call Tree
  - Hide All Library Calls
  - Add Library Calls
  - Filter by Function Names
  - Filter by CPU Time
  - Filter by Call Counts

- In the **Function** menu:
  - Immediate Parents
  - All Paths To
  - Immediate Children
  - All Paths From
  - All Functions on The Cycle
  - Show This Function Only
  - Hide This Function
  - Hide Descendant Functions
  - Hide This & Descendant Functions

If a dialog such as the Load Configuration Dialog or the Filter by CPU Time Dialog is invoked and then canceled immediately, the status of the **Undo** option is not affected. After the option is available, it stays that way until you invoke it, or a new set of files is loaded into Xprofiler through the Load Files Dialog window.

### Displaying the entire function call tree:

When you first open Xprofiler, by default, all the function boxes and call arcs of your executable and its shared libraries appear in the main window.

After that, you can choose to filter out specific items from the window. However, there might be times when you want to see the entire function call tree again, without having to reload your application. To do this, select the **Filter** menu, and then the **Show Entire Call Tree** option. Xprofiler erases whatever is currently displayed in the main window and replaces it with the entire function call tree.

### Excluding and including specific objects:

There are a number of ways that Xprofiler lets you control the items that display in the main window. You will want to include or exclude certain objects so that you can more easily focus on the things that are of most interest to you.

#### *Filtering shared library functions:*

In most cases, your application will call functions that are within shared libraries.

By default, these shared libraries display in the Xprofiler window along with your executable file. As a result, the window can get crowded and obscure the items that you most need to see. If this is the case, you can filter the shared libraries from the display. To do this, select the **Filter** menu, and then the **Remove All Library Calls** option.

The shared library function boxes disappear from the function call tree, leaving only the function boxes of your executable file visible.

If you removed the library calls from the display, you might want to restore them. To do this, select the **File** menu and then the **Add Library Calls** option.

The function boxes again appear with the function call tree. Note, however, that all of the shared library calls that were in the initial function call tree might not be added back. This is because the **Add Library Calls** option only adds back in the function boxes for the library functions that were called by functions that are currently displayed in the Xprofiler window.

To add only specific function boxes back into the display, do the following:

1. Select the **Filter** menu, and then the **Filter by Function Names** option. The Filter By Function Names dialog window appears.

2. From the Filter By Function Names Dialog window, click the **add these functions to graph** button, and then type the name of the function you want to add in the **Enter function name** field. If you enter more than one function name, you must separate them with a blank space between each function name string.

If there are multiple functions in your program that include the string you enter in their names, the filter applies to each one. For example, if you specified **sub** and **print**, and your program also included functions named **sub1**, **psub1**, and **printf**. The **sub**, **sub1**, **psub1**, **print**, and **printf** functions would all be added to the graph.

3. Click **OK**. One or more function boxes appears in the Xprofiler display with the function call tree.

*Filtering by function characteristics:*

Review the following steps to filter functions based on specific characteristics.

The Filter menu of Xprofiler offers the following options that enable you to add or subtract function boxes from the main window, based on specific characteristics:

- Filter by Function Names
- Filter by CPU Time
- Filter by Call Counts

Each option uses a different window to let you specify the criteria by which you want to include or exclude function boxes from the window.

To filter by function names, do the following:

1. Select the **Filter** menu and then the **Filter by Function Names** option. The following Filter By Function Names Dialog window appears:




Figure 24. The Filter By Function Names Dialog window

The Filter By Function Names Dialog window includes the following options:

- add these functions to graph
  - remove these functions from the graph
  - display only these functions
2. From the Filter By Function Names Dialog window, select the option, and then type the name of the function (or functions) to which you want it applied in the **Enter function name** field. For example, if

you want to remove the function box for a function called **printf** from the main window, click the **remove this function from the graph** button, and type **printf** in the **Enter function name** field.

You can enter more than one function name in this field. If there are multiple functions in your program that include the string you enter in their names, the filter will apply to each one. For example, if you specified **sub** and **print**, and your program also included functions named **sub1**, **psub1**, and **printf**, the option you chose would be applied to the **sub**, **sub1**, **psub1**, **print**, and **printf** functions.

3. Click **OK**. The contents of the function call tree now reflect the filtering options you specified.

To filter by CPU time, do the following:

1. Select the **Filter** menu and then the **Filter by CPU Time** option. The following Filter By CPU Time Dialog window appears:

The Filter By CPU Time Dialog window includes the following options:




Figure 25. The Filter By CPU Time Dialog window

- show functions consuming the most CPU time
  - show functions consuming the least CPU time
2. Select the option you want (**show functions consuming the most CPU time** is the default).
  3. Select the number of functions to which you want it applied (1 is the default). You can move the slider in the **Functions** bar until the desired number appears, or you can enter the number in the **Slider Value** field. The slider and **Slider Value** field are synchronized so when the slider is updated, the text field value is updated also. If you enter a value in the text field, the slider is updated to that value when you click **Apply** or **OK**.  
For example, to display the function boxes for the 10 functions in your application that consumed the most CPU, you would select the **show functions consuming the most CPU** button, and specify 10 with the slider or enter the value 10 in the text field.
  4. Click **Apply** to show the changes to the function call tree without closing the dialog. Click **OK** to show the changes and close the dialog.

To filter by call counts, do the following:

1. Select the **Filter** menu and then the **Filter by Call Counts** option. The Filter By Call Counts Dialog window appears.




Figure 26. The Filter By Call Counts Dialog window

The **Filter By Call Counts Dialog** window includes the following options:

- show arcs with the most call counts
  - show arcs with the least call counts
2. Select the option you want (**show arcs with the most call counts** is the default).
  3. Select the number of call arcs to which you want it applied (1 is the default). If you enter a value in the text field, the slider is updated to that value when you click **Apply** or **OK**.

For example, to display the 10 call arcs in your application that represented the least number of calls, you would select the **show arcs with the least call counts** button, and specify 10 with the slider or enter the value 10 in the text field.

4. Click **Apply** to show the changes to the function call tree without closing the dialog. Click **OK** to show the changes and close the dialog.

*Including and excluding parent and child functions:*

You must understand how parent and child behavior functions behave, and are able to improve their performance, than you can figure out how to analyzing the functions that consume less CPU.

When tuning the performance of your application, you will want to know which functions consumed the most CPU time, and then you will need to ask several questions in order to understand their behavior:

- Where did each function spend most of the CPU time?
- What other functions called this function? Were the calls made directly or indirectly?
- What other functions did this function call? Were the calls made directly or indirectly?

When your application is large, the function call tree will also be large. As a result, the functions that are the most CPU-intensive might be difficult to see in the function call tree. To avoid this situation, use the **Filter by CPU** option of the Filter menu, which lets you display only the function boxes for the functions that consume the most CPU time. After you have done this, the Function menu for each function lets you

add the parent and descendant function boxes to the function call tree. By doing this, you create a smaller, simpler function call tree that displays the function boxes associated with the most CPU-intensive area of the application.

A *child* function is one that is directly called by the function of interest. To see only the function boxes for the function of interest and its child functions, do the following:

1. Place your mouse cursor over the function box in which you are interested, and press the right mouse button. The Function menu appears.
2. From the Function menu, select the **Immediate Children** option, and then the **Show Child Functions Only** option.

Xprofiler erases the current display and replaces it with only the function boxes for the function you chose, as well as its child functions.

A *parent* function is one that directly calls the function of interest. To see only the function box for the function of interest and its parent functions, do the following:

1. Place your mouse cursor over the function box in which you are interested, and press the right mouse button. The Function menu appears.
2. From the Function menu, select the **Immediate Parents** option, and then the **Show Parent Functions Only** option.

Xprofiler erases the current display and replaces it with only the function boxes for the function you chose, as well as its parent functions.

You might want to view the function boxes for both the parent and child functions of the function in which you are interested, without erasing the rest of the function call tree. This is especially true if you chose to display the function boxes for two or more of the most CPU-intensive functions with the **Filter by CPU** option of the Filter menu (you suspect that more than one function is consuming too much CPU). Do the following:

1. Place your mouse cursor over the function box in which you are interested, and press the right mouse button. The Function menu appears.
2. From the Function menu, select the **Immediate Parents** option, and then the **Add Parent Functions to Tree** option.
3. Place your mouse cursor over the same function box and press the right mouse button. The Function menu appears.
4. From the Function menu, select the **Immediate Children** option, and then the **Add Child Functions to Tree** option.

Xprofiler leaves the current display as it is, but now adds the child function boxes in addition to the parents.

## Clustering libraries

When you first open the Xprofiler window, by default, the function boxes of your executable file, and the libraries associated with it, are clustered.

Because Xprofiler shrinks the call tree of each library when it places it in a cluster, you must uncluster the function boxes if you want to look closely at a specific function box label.

You can see much more detail for each function, when your display is in the unclustered or *expanded* state, than when it is in the clustered or *collapsed* state. Depending on what you want to do, you must cluster or uncluster (collapse or expand) the display.

The Xprofiler window can be visually crowded, especially if your application calls functions that are within shared libraries; function boxes representing your executable functions as well as the functions of the shared libraries are displayed. As a result, you might want to organize what you see in the Xprofiler

window so you can focus on the areas that are most important to you. You can do this by collecting all the function boxes of each library into a single area, known as a library *cluster*.

The following figure shows the `hello_world` application with its function boxes unclustered.




Figure 27. The Xprofiler window with function boxes unclustered

### Clustering functions:

If the functions within your application are unclustered, you can use an option of the **Filter** menu to cluster them. To do this, select the **Filter** menu and then the **Cluster Functions by Library** option.

The libraries within your application appear within their respective cluster boxes.

After you cluster the functions in your application you can further reduce the size (also referred to as *collapse*) of each cluster box by doing the following:

1. Place your mouse cursor over the edge of the cluster box and press the right mouse button. The Cluster Node menu appears.

2. Select the **Collapse Cluster Node** option. The cluster box and its contents now appear as a small solid green box. In the following figure, the `/lib/profiled/libc.a:shr.o` library is collapsed.




Figure 28. The Xprofiler window with one library cluster box collapsed

To return the cluster box to its original condition (*expand* it), do the following:

1. Place your mouse cursor over the collapsed cluster box and press the right mouse button. The **Cluster Node** menu appears.
2. Select the **Expand Cluster Node** option. The cluster box and its contents appear again.

#### Unclustering functions:

If the functions within your application are clustered, you can use an option of the **Filter** menu to uncluster them. To do this, select the **Filter** menu, and then the **Uncluster Functions** option.

The cluster boxes disappear and the functions boxes of each library expand to fill the Xprofiler window.

If your functions have been clustered, you can remove one or more (but not all) cluster boxes. For example, if you want to uncluster only the functions of your executable file, but keep its shared libraries within their cluster boxes, you would do the following:

1. Place your mouse cursor over the edge of the cluster box that contains the executable and press the right mouse button. The **Cluster Node** menu appears.
2. Select the **Remove Cluster Box** option. The cluster box is removed and the function boxes and call arcs that represent the executable functions, now appear in full detail. The function boxes and call arcs of the shared libraries remain within their cluster boxes, which now appear smaller to make room for the unclustered executable function boxes. The following figure shows the `hello_world` executable file with its cluster box removed. Its shared library remains within its cluster box.




Figure 29. The Xprofiler window with one library cluster box removed

### Locating specific objects in the function call tree

If you are interested in one or more specific functions in a complex program, you might need help locating their corresponding function boxes in the function call tree.

If you want to locate a single function, and you know its name, you can use the **Locate Function By Name** option of the **Utility** menu. To locate a function by name, do the following:

1. Select the **Utility** menu, and then the **Locate Function By Name** option. The **Search By Function Name Dialog** window appears.
2. Type the name of the function you want to locate in the **Enter Function Name** field. The function name you type here must be a continuous string (it cannot include blanks).
3. Click **OK** or **Apply**. The corresponding function box is highlighted (its color changes to red) in the function call tree and Xprofiler zooms in on its location.

To display the function call tree in full detail again, go to the **View** menu and use the **Overview** option.

You might want to see only the function boxes for the functions that you are concerned with, in addition to other specific functions that are related to it. For example, if you want to see all the functions that directly called the function in which you are interested, it might not be easy to separate these function boxes when you view the entire call tree. You would want to display them, as well as the function of interest, alone.

Each function has its own menu. Through the Function menu, you can choose to see the following for the function you are interested in:

- Parent functions (functions that directly call the function of interest)
- Child functions (functions that are directly called by the function of interest)
- Ancestor functions (functions that can call, directly or indirectly, the function of interest)
- Descendant functions (functions that can be called, directly or indirectly, by the function of interest)
- Functions that belong to the same cycle

When you use these options, Xprofiler erases the current display and replaces it with only the function boxes for the function of interest and all the functions of the type you specified.

#### **Locating and displaying parent functions:**

A *parent* is any function that directly calls the function in which you are interested.

To locate the parent function boxes of the function in which you are interested:

1. Click the function box of interest with the right mouse button. The Function menu appears.
2. From the Function menu, select **Immediate Parents** then **Show Parent Functions Only**. Xprofiler redraws the display to show you only the function boxes for the function of interest and its parent functions.

#### **Locating and displaying child functions:**

A *child* is any function that is directly called by the function in which you are interested.

To locate the child functions boxes for the function in which you are interested:

1. Click the function box of interest with the right mouse button. The Function menu appears.
2. From the Function menu, select **Immediate Children** then **Show Child Functions Only**. Xprofiler redraws the display to show you only the function boxes for the function of interest and its child functions.

#### **Locating and displaying ancestor functions:**

An *ancestor* is any function that can call, directly or indirectly, the function in which you are interested.

To locate the ancestor functions:

1. Click the function box of interest with the right mouse button. The Function menu appears.

2. From the Function menu, select **All Paths To** then **Show Ancestor Functions Only**. Xprofiler redraws the display to show you only the function boxes for the function of interest and its ancestor functions.

#### **Locating and displaying descendant functions:**

A *descendant* is any function that can be called, directly or indirectly, by the function in which you are interested.

To locate the descendant functions (all the functions that the function of interest can reach, directly or indirectly):

1. Click the function box of interest with the right mouse button. The Function menu appears.
2. From the Function menu, select **All Paths From** then **Show Descendant Functions Only**. Xprofiler redraws the display to show you only the function boxes for the function of interest and its descendant functions.

#### **Locating and displaying functions on a cycle:**

Review the following steps to located and display function on a cycle.

To locate the functions that are on the same cycle as the function, complete the following steps:

1. Click the function box of interest with the right mouse button. The Function menu appears.
2. From the Function menu, select **All Functions on the Cycle** then **Show Cycle Functions Only**. Xprofiler redraws the display to show you only the function of interest and all the other functions on its cycle.

### **Obtaining performance data for your application**

With Xprofiler, you can get performance data for your application on a number of levels, and in a number of ways.

You can easily view data pertaining to a single function, or you can use the reports provided to get information on your application as a whole.


#### **Obtaining basic data:**

Xprofiler makes it easy to get data on specific items in the function call tree.

After you located the item that you are interested, you can get the data by using a number of ways. If you cannot locate a function in the function call tree, see Locate a function section.

*Basic function data:*

Review each function box in the function call tree is a label that contains basic performance data.



*Figure 30. An example of a function box label*

The label contains the name of the function, its associated cycle, if any, and its index. In the preceding figure, the name of the function is **sub1**. It is associated with cycle 1, and its index is 5. Also, depending on whether the function call tree is viewed in summary mode or average mode, the label will contain different information.

If the function call tree is viewed in summary mode, the label will contain the following information:

- The total amount of CPU time (in seconds) this function spent on itself plus the amount of CPU time it spent on its descendants (the number on the left of the *x*).
- The amount of CPU time (in seconds) this function spent only on itself (the number on the right of the *x*).

If the function call tree is viewed in average mode, the label will contain the following information:

- The average CPU time (in seconds), among all the input **gmon.out** files, used on the function itself
- The standard deviation of CPU time (in seconds), among all the input **gmon.out** files, used on the function itself


For more information about summary mode and average mode, see “Controlling the representation of the function call tree” on page 277.

Because labels are not always visible in the Xprofiler window when it is fully zoomed out, you might need to zoom in on it in order to see the labels. For information about how to do this, see “Information boxes” on page 290.

*Basic call data:*

Call arc labels appear over each call arc. The label indicates the number of calls that were made between the two functions (from caller to callee).

For example:



*Figure 31. An example of a call arc label*

To see a call arc label, you can zoom in on it. For information about how to do this, see “Information boxes.”

*Basic cluster data:*

Cluster box labels indicate the name of the library that is represented by that cluster. If it is a shared library, the label shows its full path name.

*Information boxes:*

For each function box, call arc, and cluster box, a corresponding information box gives you the same basic data that appears on the label.

This is useful when the Xprofiler display is fully zoomed out and the labels are not visible. To access the information box, click on the function box, call arc, or cluster box (place the mouse pointer over the edge of the box) with the left mouse button. The information box appears.

For a function, the information box contains the following:

- The name of the function, its associated cycle, if any, and its index.
- The amount of CPU used by this function. There are two values supplied in this field. The first is the amount of CPU time spent on this function plus the time spent on its descendants. The second value represents the amount of CPU time this function spent only on itself.
- The number of times this function was called (by itself or any other function in the application).

For a call, the information box contains the following:

- The caller and callee functions (their names) and their corresponding indexes
- The number of times the caller function called the callee

For a cluster, the information box contains the following:

- The name of the library
- The total CPU usage (in seconds) consumed by the functions within it

*Function menu statistics report option:*

You can get performance statistics for a single function through the **Statistics Report** option of the **Function** menu. This option lets you see data on the CPU usage and call counts of the selected function.

If you are using more than one **gmon.out** file, the **Statistics Report** option breaks down the statistics for each **gmon.out** file you use.

When you select the **Statistics Report** menu option, the Function Level Statistics Report window appears.




Figure 32. The Function Level Statistics Report window

The Function Level Statistics Report window provides the following information:

*Function name:*

The name of the function you selected.

*Summary Data:*

The total amount of CPU used by this function. If you used multiple **gmon.out** files, the value shown here represents their sum.

The **CPU Usage** field indicates:

- The amount of CPU time used by this function. There are two values supplied in this field. The first is the amount of CPU time spent on this function plus the time spent on its descendants. The second value represents the amount of CPU time this function spent only on itself.

The **Call Counts** field indicates:

- The number of times this function called itself, plus the number of times it was called by other functions.

*Statistics data:*

The CPU usage and calls made to or by this function, broken down for each **gmon.out** file.

The **CPU Usage** field indicates:

- **Average**

The average CPU time used by the data in each **gmon.out** file.

- **Std Dev**

Standard deviation. A value that represents the difference in CPU usage samplings, per function, from one **gmon.out** file to another. The smaller the standard deviation, the more balanced the workload.

- **Maximum**

Of all the **gmon.out** files, the maximum amount of CPU time used. The corresponding **gmon.out** file appears to the right.

- **Minimum**

Of all the **gmon.out** files, the minimum amount of CPU time used. The corresponding **gmon.out** file appears to the right.

The **Call Counts** field indicates:

- **Average**

The average number of calls made to this function or by this function, for each **gmon.out** file.

- **Std Dev**

Standard deviation. A value that represents the difference in call count sampling, per function, from one **gmon.out** file to another. A small standard deviation value in this field means that the function was almost always called the same number of times in each **gmon.out** file.

- **Maximum**

The maximum number of calls made to this function or by this function in a single **gmon.out** file. The corresponding **gmon.out** file appears to the right.

- **Minimum**

The minimum number of calls made to this function or by this function in a single **gmon.out** file. The corresponding **gmon.out** file appears to the right.

### Getting detailed data from reports:

Xprofiler provides performance data in textual and tabular format. This data is provided in various tables called *reports*.

Similar to the **gprof** command, Xprofiler generates the **Flat Profile**, **Call Graph Profile**, and **Function Index** reports, as well as two additional reports.

You can access the Xprofiler reports from the **Report** menu. The **Report** menu displays the following reports:

- Flat Profile
- Call Graph Profile
- Function Index
- Function Call Summary
- Library Statistics

Each report window includes a File menu. Under the File menu is the **Save As** option, which lets you save the report to a file. For information about using the **Save File Dialog** window to save a report to a file, see “Saving the call graph profile, function index, and flat profile reports to a file” on page 301.

**Note:** If you select the **Save As** option from the **Flat Profile**, **Function Index**, or **Function Call Summary** report window, you must either complete the save operation or cancel it before you can select any other option from the menus of these reports. You can, however, use the other Xprofiler menus before completing the save operation or canceling it, with the exception of the **Load Files** option of the **File** menu, which remains unavailable.

Each of the Xprofiler reports are explained as follows.

*Flat profile report:*

When you select the **Flat Profile** menu option, the Flat Profile window appears.

The Flat Profile report shows you the total execution times and call counts for each function (including shared library calls) within your application. The entries for the functions that use the greatest percentage of the total CPU usage appear at the top of the list, while the remaining functions appear in descending order, based on the amount of time used.

Unless you specified the **-z** flag, the **Flat Profile** report does not include functions that have no CPU usage and no call counts. The data presented in the **Flat Profile** window is the same data that is generated with the **gprof** command.

The Flat Profile report looks similar to the following:

The screenshot shows a window titled "Flat Profile: total CPU time = 0.11 seconds". The window contains a table with the following columns: File, Code Display, Utility, %time, cumulative seconds, self seconds, calls, self ns/call, total ns/call, and name. The data is sorted by %time in descending order.

File	Code Display	Utility	%time	cumulative seconds	self seconds	calls	self ns/call	total ns/call	name
			54.5	0.06	0.06	2	30.00	30.00	.sub2 <cycle 1> [2] hello_world.c
			27.3	0.09	0.03	2	15.00	15.00	.sub1 <cycle 1> [5] hello_world.c
			9.1	0.10	0.01	1	10.00	100.00	.main [3] hello_world.c
			9.1	0.11	0.01				__mcount [6] .....
			0.0	0.11	0.00	11	0.00	0.00	__doprint [67] .....
			0.0	0.11	0.00	11	0.00	0.00	__xflzbuf [68] .....
			0.0	0.11	0.00	11	0.00	0.00	__xwrite [69] .....
			0.0	0.11	0.00	11	0.00	0.00	.fwrite [70] .....
			0.0	0.11	0.00	11	0.00	0.00	.memcpy [71] .....
			0.0	0.11	0.00	11	0.00	0.00	.printf [72] .....
			0.0	0.11	0.00	11	0.00	0.00	.write [73] .....
			0.0	0.11	0.00	3	0.00	0.00	.splay [74] .....
			0.0	0.11	0.00	2	0.00	0.00	.free [75] .....
			0.0	0.11	0.00	2	0.00	0.00	.free_y [76] .....
			0.0	0.11	0.00	1	0.00	0.00	__ioctl [77] .....
			0.0	0.11	0.00	1	0.00	0.00	__findbuf [78] .....
			0.0	0.11	0.00	1	0.00	0.00	__wrtchk [79] .....
			0.0	0.11	0.00	1	0.00	0.00	.catopen [80] .....
			0.0	0.11	0.00	1	0.00	0.00	.exit [81] .....
			0.0	0.11	0.00	1	0.00	0.00	.expand_catname [82] .....

Search Engine: (regular expressions supported)

Figure 33. The Flat Profile report

### *Flat profile window fields:*

This topic provides detailed information about the **Flat Profile** fields.

The **Flat Profile** window contains the following fields:

- **%time**  
The percentage of the program's total CPU usage that is consumed by this function.
- **cumulative seconds**  
A running sum of the number of seconds used by this function and those listed above it.
- **self seconds**  
The number of seconds used by this function alone. Xprofiler uses the **self seconds** values to sort the functions of the **Flat Profile** report.
- **calls**  
The number of times this function was called (if this function is profiled). Otherwise, it is blank.
- **self ms/call**  
The average number of milliseconds spent in this function per call (if this function is profiled). Otherwise, it is blank.
- **total ms/call**  
The average number of milliseconds spent in this function and its descendants per call (if this function is profiled). Otherwise, it is blank.
- **name**  
The name of the function. The *index* appears in brackets (I) to the right of the function name. The index serves as the function's identifier within Xprofiler. It also appears below the corresponding function in the function call tree.

### *Call graph profile report:*

The Call Graph Profile menu option lets you view the functions of your application, sorted by the percentage of total CPU usage that each function, and its descendants, consumed. When you select this option, the Call Graph Profile window appears.

Unless you specified the **-z** flag, the **Call Graph Profile** report does not include functions whose CPU usage is 0 (zero) and have no call counts. The data presented in the **Call Graph Profile** window is the same data that is generated with the **gprof** command.

The Call Graph Profile report looks similar to the following:




Figure 34. The Call Graph Profile report

Call graph profile window fields:

The following information provides detailed information about the **Call Graph Profile** fields.

The **Call Graph Profile** window contains the following fields:

- **index**  
The index of the function in the **Call Graph Profile**. Each function in the **Call Graph Profile** has an associated index number which serves as the function's identifier. The same index also appears with each function box label in the function call tree, as well as other Xprofiler reports.
- **%time**  
The percentage of the program's total CPU usage that was consumed by this function and its descendants.
- **self**  
The number of seconds this function spends within itself.
- **descendants**  
The number of seconds spent in the descendants of this function, on behalf of this function.
- **called/total, called+self, called/total**  
The heading of this column refers to the different kinds of calls that take place within your program. The values in this field correspond to the functions listed in the **name, index, parents, children** field to its right. Depending on whether the function is a parent, a child, or the function of interest (the function with the index listed in the **index** field of this row), this value might represent the number of times that:
  - a parent called the function of interest
  - the function of interest called itself, recursively
  - the function of interest called a child

In the following figure, **sub2** is the function of interest, **sub1** and **main** are its parents, and **printf** and **sub1** are its children.

called/total called+self called/total	parents name children	index
-----		
1	.sub1 <cycle 1>	[5]
1/2	.main	[3]
2	.sub2 <cycle 1>	[2]
4/11	.printf	[72]
1	.sub1 <cycle 1>	[5]

Figure 35. The called/total, call/self, called/total field

- **called/total**  
For a parent function, the number of calls made to the function of interest, as well as the total number of calls it made to all functions.
- **called+self**  
The number of times the function of interest called itself, recursively.
- **name, index, parents, children**  
The layout of the heading of this column indicates the information that is provided. To the left is the name of the function, and to its right is the function's index number. Appearing above the function are its parents, and below are its children.

parents name children	index
.sub1 <cycle 1>	[5]
.main	[3]
.sub2 <cycle 1>	[2]
.printf	[72]
.sub1 <cycle 1>	[5]

Figure 36. The name/index/parents/children field

- **name**  
The name of the function, with an indication of its membership in a cycle, if any. The function of interest appears to the left, while its parent and child functions are indented above and below it.
- **index**  
The index of the function in the **Call Graph Profile**. This number corresponds to the index that appears in the *index* column of the **Call Graph Profile** and the on the function box labels in the function call tree.

- **parents**

The parents of the function. A *parent* is any function that directly calls the function in which you are interested.

If any portion of your application was not compiled with the **-pg** flag, Xprofiler cannot identify the parents for the functions within those portions. As a result, these parents will be listed as *spontaneous* in the **Call Graph Profile** report.

- **children**

The children of the function. A *child* is any function that is directly called by the function in which you are interested.

*Function index report:*

The Function Index menu option lets you view a list of the function names included in the function call tree.

When you select this option, the Function Index window appears and displays the function names in alphabetical order. To the left of each function name is its *index*, enclosed in brackets ([]). The index is the function's identifier, which is assigned by Xprofiler. An index also appears on the label of each corresponding function box in the function call tree, as well as on other reports.

Unless you specified the **-z** flag, the Function Index report does not include functions that have no CPU usage and no call counts.

Like the **Flat Profile** menu option, the **Function Index** menu option includes a **Code Display** menu, so you can view source code or disassembler code. See “Looking at your code” on page 303 for more information.

The **Function Index** report looks similar to the following:




Figure 37. The Function Index report

*Function call summary report:*

The Function Call Summary menu option lets you display all the functions in your application that call other functions. They appear as caller-callee pairs (call arcs, in the function call tree), and are sorted by the number of calls in descending order.

When you select this option, the Function Call Summary window appears.

The **Function Call Summary** report looks similar to the following:

Function Call Summary		
File	Utility	Help
%total	calls	function
10.78%	11	calls from .printf [72] to ._doprint [67]
10.78%	11	calls from ._doprint [67] to .fwrite [70]
10.78%	11	calls from ._xflsbuf [68] to ._xwrite [69]
10.78%	11	calls from ._xwrite [69] to .write [73]
10.78%	11	calls from .fwrite [70] to .memchr [71]
10.78%	11	calls from .fwrite [70] to ._xflsbuf [68]
3.92%	4	calls from .sub2 <cycle 1> [2] to .printf [72]
3.92%	4	calls from .sub1 <cycle 1> [5] to .printf [72]
2.94%	3	calls from .free_y [76] to .splay [74]
2.94%	3	calls from .main [3] to .printf [72]
1.96%	2	calls from .free [75] to .free_y [76]
0.98%	1	calls from .ioctl [84] to ._ioctl [77]
0.98%	1	calls from .setlocale [89] to .saved_category_name [88]
0.98%	1	calls from .monitor [87] to .catopen [80]
0.98%	1	calls from .monstr [1465] to .free [75]
0.98%	1	calls from .monstartup [1463] to .free [75]
0.98%	1	calls from .monitor [87] to .moncontrol [86]
0.98%	1	calls from .expand_catname [82] to .getenv [83]
0.98%	1	calls from .expand_catname [82] to .setlocale [89]
0.98%	1	calls from .isatty [85] to .ioctl [84]
0.98%	1	calls from .catopen [80] to .expand_catname [82]

Search Engine: (regular expressions supported)

Figure 38. The Function Call Summary report

Function call summary window fields:

This topic provides detailed information about the Function Call Summary fields.

The Function Call Summary window contains the following fields:

- **%total**  
The percentage of the total number of calls generated by this caller-callee pair
- **calls**  
The number of calls attributed to this caller-callee pair
- **function**  
The name of the caller function and callee function

Library statistics report:

The Library Statistics menu option lets you display the CPU time consumed and call counts of each library within your application. When you select this option, the Library Statistics window appears.

The **Library Statistics** report looks similar to the following:

The screenshot shows a window titled "Library Statistics" with a menu bar containing "File" and "Help". The main area contains a table with the following data:

total seconds	%total time	total calls	%total calls	%calls out of	%calls into	%calls within	load unit
0.10	90.91	5	4.90	11.76	0.00	4.90	hello_world
0.01	9.09	97	95.10	0.00	11.76	83.33	/lib/profiled/libc.a : shr.o
0.00	0.00	NA	--	0.00	--	--	/lib/profiled/libc.a : meth.o

At the bottom of the window, there is a search engine field with the text "Search Engine: (regular expressions supported)".

Figure 39. The Library Statistics report

Library statistics window fields:

This topic provides detailed information about the **Library Statistics** fields.

The **Library Statistics** window contains the following fields:

- **total seconds**  
The total CPU usage of the library, in seconds
- **%total time**  
The percentage of the total CPU usage that was consumed by this library
- **total calls**  
The total number of calls that this library generated
- **%total calls**  
The percentage of the total calls that this library generated
- **%calls out of**  
The percentage of the total number of calls made from this library to other libraries
- **%calls into**  
The percentage of the total number of calls made from other libraries into this library
- **%calls within**  
The percentage of the total number of calls made between the functions within this library
- **load unit**  
The library's full path name

*Saving reports to a file:*

Xprofiler lets you save any of the reports you generate with the **Report** menu to a file.

You can do this using the **File** and **Report** menus of the Xprofiler GUI.

*Saving a single report:*

To save a single report, go to the **Report** menu on the Xprofiler main window and select the report you want to save.

Each report window includes a **File** menu. Select the **File** menu and then the **Save As** option to save the report. A **Save** dialog window appears, which is named according to the report from which you selected the **Save As** option. For example, if you chose **Save As** from the **Flat Profile** window, the save window is named **Save Flat Profile Dialog**.

*Saving the call graph profile, function index, and flat profile reports to a file:*

You can save the **Call Graph Profile**, **Function Index**, and **Flat Profile** reports to a single file through the **File** menu of the Xprofiler main window.

The information you generate here is identical to the output of the **gprof** command. From the **File** menu, select the **Save As** option. The **Save File Dialog** window appears.

To save the reports, do the following:

1. Specify the file into which the profiled data should be placed. You can specify either an existing file or a new one. To specify an existing file, use the scroll bars of the **Directories** and **Files** selection boxes to locate the file. To make locating your files easier, you can also use the **Filter** button (see “Filtering what you see” on page 278 for more information). To specify a new file, type its name in the **Selection** field.
2. Click **OK**. A file that contains the profiled data appears in the directory you specified, under the name you gave it.

**Note:** After you select the **Save As** option from the **File** menu and the Save Profile Reports window opens, you must either complete the save operation or cancel it before you can select any other option from the menus of its parent window. For example, if you select the **Save As** option from the **Flat Profile** report and the Save File Dialog window appears, you cannot use any other option of the **Flat Profile** report window.

The **File Selection** field of the Save File Dialog window follows Motif standards.

*Saving summarized data from multiple profile data files:*

If you are profiling a parallel program, you can specify more than one profile data (**gmon.out**) file when you start Xprofiler.

The **Save gmon.sum As** option of the **File** menu lets you save a summary of the data in each of these files to a single file.

The Xprofiler **Save gmon.sum As** option produces the same result as the **xprofiler -s** command and the **gprof -s** command. If you run Xprofiler later, you can use the file you create here as input with the **-s** flag. In this way, you can accumulate summary data over several runs of your application.

To create a summary file, do the following:

1. Select the **File** menu, and then the **Save gmon.sum As** option. The **Save gmon.sum Dialog** window appears.
2. Specify the file into which the summarized, profiled data should be placed. By default, Xprofiler puts the data into a file called **gmon.sum**. To specify a new file, type its name in the selection field. To specify an existing file, use the scroll bars of the **Directories** and **Files** selection boxes to locate the file you want. To make locating your files easier, you can also use the **Filter** button (see “Filtering what you see” on page 278 for information).
3. Click **OK**. A file that contains the summary data appears in the directory you specified, under the name you specified.

*Saving a configuration file:*

The **Save Configuration** menu option lets you save the names of the functions that are displayed currently to a file.

Later, in the same Xprofiler session or in a different session, you can read this configuration file in using the **Load Configuration** option. For more information, see “Loading a configuration file”.

To save a configuration file, do the following:

1. Select the **File** menu, and then the select **Save Configuration**. The **Save Configuration File Dialog** window displays with the *program.cgf* file as the default value in the Selection field, where *program* is the name of the input in the a.out file. You can use the default file name, enter a file name in the Selection field, or select a file from the file list.
2. Specify a file name in the **Selection** field and click **OK**. A configuration file is created that contains the name of the program and the names of the functions that are displayed currently.
3. Specify an existing file name in the **Selection** field and click **OK**. An Overwrite File Dialog window appears so that you can check the file before overwriting it.

If you selected the **Forced File Overwriting** option in the Runtime Options Dialog window, the Overwrite File Dialog window does not open and the specified file is overwritten without warning.

*Loading a configuration file:*

The **Load Configuration** menu option lets you read in a configuration file that you saved.

See “Saving a configuration file” for more information. The **Load Configuration** option automatically reconstructs the function call tree according to the function names recorded in the configuration file.

To load a configuration file, do the following:

1. Select the File menu, and then the **Load Configuration** option. The **Load Configuration File Dialog** window opens. If configuration files were loaded previously during the current Xprofiler session, the name of the file that was most recently loaded will appear in the **Selection** field of this dialog. You can also load the file with the **-c** flag. For more information, see “Specifying command line options (from the GUI)” on page 267.
2. Select a configuration file from the dialog’s **Files** list or specify a file name in the **Selection** field and click **OK**. The function call tree is redrawn to show only those function boxes for functions that are listed in the configuration file and are called within the program that is currently represented in the display. All corresponding call arcs are also drawn.  
If the **a.out** name, that is, the program name in the configuration file, is different from the **a.out** name in the current display, a confirmation dialog asks you whether you still want to load the file.
3. If after loading a configuration file, you want to return the function call tree to its previous state, select the **Filter** menu, and then the **Undo** option.

## Looking at your code:

Xprofiler provides several ways for you to view your code. You can view the source code or the disassembler code for your application, for each function. This also applies to any included function code that your application might use.

To view source or included function code, use the Source Code window. To view disassembler code, use the Disassembler Code window. You can access these windows through the Report menu of the Xprofiler GUI or the Function menu of the function you are interested in.

### *Viewing the source code:*

Both the Function menu and Report menu permits you to access the Source Code window, from which you can view your code.

To access the Source Code window through the Function menu, complete the following steps:

1. Click the function box you are interested in with the right mouse button. The **Function** menu appears.
2. From the **Function** menu, select the **Show Source Code** option.

To access the **Source Code** window through the Report menu, complete the following steps:

1. Select the Report menu, and then the **Flat Profile** option. The **Flat Profile** window appears.
2. From the **Flat Profile** window, select the function you would like to view by clicking the entry in the window. The entry is highlighted to show that it is selected.
3. Select the **Code Display** menu, and then the **Show Source Code** option.

### *Using the source code window:*

The **Source Code** window shows you the source code file for the function you specified from the **Flat Profile** window or the **Function** menu.

The **Source Code** window looks similar to the following:




Figure 40. The Source Code window

The **Source Code** window contains information in the following fields:

- **line**  
The source code line number.
- **no. ticks per line**  
Each tick represents .01 seconds of CPU time used. The value in this field represents the number of ticks used by the corresponding line of code. For example, if the number 3 appeared in this field, for a source statement, this source statement would have used .03 seconds of CPU time. The CPU usage data only appears in this field if you used the **-g** flag when you compiled your application. Otherwise, this field is blank.
- **source code**  
The application's source code.

The **Source Code** window contains the following menus:

- **File**  
The **Save As** option lets you save the annotated source code to a file. When you select this option, the **Save File Dialog** window appears. For more information about using the **Save File Dialog** window, see "Saving the call graph profile, function index, and flat profile reports to a file" on page 301.  
To close the **Source Code** window, select **Close**.
- **Utility**  
This menu contains the **Show Included Functions** option.

For C++ users, the **Show Included Functions** option lets you view the source code of included function files that are included by the application's source code.

If a selected function does not have an included function file associated with it or does not have the function file information available because the **-g** flag was not used for compiling, the **Utility** menu will be unavailable. The availability of the **Utility** menu indicates whether there is any included function-file information associated with the selected function.

When you select the **Show Included Functions** option, the **Included Functions Dialog** window appears, which lists all of the included function files. Specify a file by either clicking on one of the entries in the list with the left mouse button, or by typing the file name in the **Selection** field. Then click **OK** or **Apply**. After you select a file from the **Included Functions Dialog** window, the **Included Function File** window appears, displaying the source code for the file that you specified.

*Viewing the disassembler code:*

Both the **Function** menu and **Report** menu permit you to access the Disassembler Code window, from which you can view your code.

To access the **Disassembler Code** window through the **Function** menu, complete the following steps:

1. Click the function you are interested in with the right mouse button. The **Function** menu appears.
2. From the **Function** menu, select the **Show Disassembler Code** option.

To access the Disassembler Code window through the **Report** menu, complete the following steps:

1. Select the **Report** menu, and then the **Flat Profile** option. The **Flat Profile** window appears.
2. From the **Flat Profile** window, select the function you want to view by clicking the entry in the window. The entry is highlighted to show that it is selected.
3. Select the **Code Display** menu, and then the **Show Disassembler Code** option.

*Using the disassembler code window:*

The Disassembler Code window shows you only the disassembler code for the function you specified from the Flat Profile window.

The **Disassembler Code** window looks similar to the following:




Figure 41. The Disassembler Code window

The Disassembler Code window contains information in the following fields:

- **address**  
The address of each instruction in the function you selected (from either the **Flat Profile** window or the function call tree).
- **no. ticks per instr.**  
Each tick represents .01 seconds of CPU time used. The value in this field represents the number of ticks used by the corresponding instruction. For instance, if the number 3 appeared in this field, this instruction would have used .03 seconds of CPU time.
- **instruction**  
The execution instruction.
- **assembler code**  
The execution instruction's corresponding assembler code.
- **source code**  
The line in your application's source code that corresponds to the execution instruction and assembler code. In order for information to appear in this field, you must have compiled your application with the **-g** flag.

The **Search Engine** field at the bottom of the **Disassembler Code** window lets you search for a specific string in your disassembler code.

The **Disassembler Code** window contains one menu:

- **File**

Select **Save As** to save the annotated disassembler code to a file. When you select this option, the **Save File Dialog** window appears. For information on using the **Save File Dialog** window, see “Saving the call graph profile, function index, and flat profile reports to a file” on page 301.

To close the **Disassembler Code** window, select **Close**.

### Saving screen images of profiled data

The **File** menu of the Xprofiler GUI includes an option called **Screen Dump** that lets you capture an image of the Xprofiler main window.

This option is useful if you want to save a copy of the graphical display to refer to later. You can either save the image as a file in PostScript format, or send it directly to a printer.

To capture a window image, do the following:

1. Select **File** and then **Screen Dump**. The **Screen Dump** menu opens.
2. From the **Screen Dump** menu, select **Set Option**. The Screen Dump Options Dialog window appears.



Figure 42. The Screen Dump Options Dialog window

3. Make the appropriate selections in the fields of the **Screen Dump Options Dialog** window, as follows:
  - **Output To:**

This option lets you specify whether you want to save the captured image as a PostScript file or send it directly to a printer.

If you would like to save the image to a file, select the **File** button. This file, by default, is named **Xprofiler.screenDump.ps.0**, and is displayed in the **Default File Name** field of this dialog window. When you select the **File** button, the text in the **Print Command** field greys out.

To send the image directly to a printer, select the **Printer** button. The image is sent to the printer you specify in the **Print Command** field of this dialog window. When you specify the **Print** option, a file of the image is not saved. Also, selecting this option causes the text in the **Default File Name** field is made unavailable.

- **PostScript Output:**

This option lets you specify whether you want to capture the image in shades of grey or in color.

If you want to capture the image in shades of grey, select the **GreyShades** button. You must also select the number of shades you want the image to include with the **Number of Grey Shades** option, as discussed below.

If you want to capture the image in color, select the **Color** button.

- **Number of Grey Shades**

This option lets you specify the number of grey shades that the captured image will include. Select either the 2, 4, or 16 buttons, depending on the number of shades you want to use. Typically, the more shades you use, the longer it will take to print the image.

- **Delay Before Grab**

This option lets you specify how much of a delay will occur between activating the capturing mechanism and when the image is actually captured. By default, the delay is set to one second, but you might need time to arrange the window the way you want it. Setting the delay to a longer interval gives you some extra time to do this. You set the delay with the slider bar of this field. The number above the slider indicates the time interval in seconds. You can set the delay to a maximum of thirty seconds.

- **Enable Landscape** (button)

This option lets you specify that you want the output to be in landscape format (the default is portrait). To select landscape format, select the **Enable Landscape** button.

- **Annotate Output** (button)

This option lets you specify that you would like information about how the file was created to be included in the PostScript image file. By default, this information is not included. To include this information, select the **Annotate Output** button.

- **Default File Name** (field)

If you chose to put your output in a file, this field lets you specify the file name. The default file name is **Xprofiler.screenDump.ps.0**. If you want to change to a different file name, type it over the one that appears in this field.

If you specify the output file name with an integer suffix (that is, the file name ends with *xxx.nn*, where *nn* is a non-negative integer), the suffix automatically increases by one every time a new output file is written in the same Xprofiler session.

- **Print Command** (field)

If you chose to send the captured image directly to a printer, this field lets you specify the print command. The default print command is **qprt -B ga -c -Pps**. If you want to use a different command, type the new command over the one that appears in this field.

4. Click **OK**. The **Screen Dump Options Dialog** window closes.

After you have set your screen dump options, you need to select the window, or portion of a window, you want to capture. From the **Screen Dump** menu, select the **Select Target Window** option. A cursor that looks like a person's hand appears after the number of seconds you specified. To cancel the capture, click the right mouse button. The hand-shaped cursor will revert to normal and the operation will be terminated.

To capture the entire Xprofiler window, place the cursor in the window and then click the left mouse button.

To capture a portion of the Xprofiler window, do the following:

1. Place the cursor in the upper left corner of the area you want to capture.
2. Press and hold the middle mouse button and drag the cursor diagonally downward, until the area you want to capture is within the rubberband box.
3. Release the middle mouse button to set the location of the rubberband box.
4. Press the left mouse button to capture the image.

If you chose to save the image as a file, the file is stored in the directory that you specified. If you chose to print the image, the image is sent to the printer you specified.

## Customizing Xprofiler resources

You can customize certain features of an X Window System. For example, you can customize its colors, fonts, and orientation. This section lists each of the resource variables you can set for Xprofiler.

You can customize resources by assigning a value to a resource name in a standard X Window System format. Several resource files are searched according to the following X Window System convention:

```
/usr/lib/X11/$LANG/app-defaults/Xprofiler
/usr/lib/X11/app-defaults/Xprofiler
$XAPPLRESDIR/Xprofiler
$HOME/.Xdefaults
```

Options in the **.Xdefaults** file take precedence over entries in the preceding files. This permits you to have certain specifications apply to all users in the **app-defaults** file, as well as user-specific preferences set for each user in their **\$HOME/.Xdefaults** file.

You customize a resource by setting a value to a *resource variable* associated with that feature. You store these *resource settings* in a file called **.Xdefaults** in your home directory. You can create this file on a server, and so customize a resource for all users. Individual users might also want to customize resources. The resource settings are essentially your personal preferences for how the X Window System should look.

For example, consider the following resource variables for a hypothetical X Window System tool:

```
TOOL*MainWindow.foreground:
TOOL*MainWindow.background:
```

In this example, suppose the resource variable *TOOL\*MainWindow.foreground* controls the color of text on the tool's main window. The resource variable *TOOL\*MainWindow.background* controls the background color of this same window. If you wanted the tool's main window to have red lettering on a white background, you would insert these lines into the **.Xdefaults** file:

```
TOOL*MainWindow.foreground:   red
TOOL*MainWindow.background:  white
```

Customizable resources and instructions for their use for Xprofiler are defined in **/usr/lib/X11/app-defaults/Xprofiler** file, as well as **/usr/lpp/ppe.xprofiler/defaults/Xprofiler.ad** file. This file contains a set of X Window System resources for defining graphical user interfaces based on the following criteria:

- Window geometry
- Window title
- Push button and label text
- Color maps
- Text font (in both textual reports and the graphical display)

## Xprofiler resource variables:

You can use the following resource variables to control the appearance and behavior of Xprofiler. The values listed in this section are the defaults; you can change these values to suit your preferences.

### *Controlling fonts:*

Review the following information to learn how to control Xprofiler fonts.

To specify the font for the labels that appear with function boxes, call arcs, and cluster boxes:

Use this resource variable:	Specify this default, or a value of your choice:
*narc*font	fixed

To specify the font used in textual reports:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*fontList	rom10

### *Controlling the appearance of the Xprofiler main window:*

You can control the size, foreground, background, and number of function boxes, for the Xprofiler main window.

To specify the size of the main window:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*mainW.height	700
Xprofiler*mainW.width	900

To specify the foreground and background colors of the main window:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*foreground	black
Xprofiler*background	light grey

To specify the number of function boxes that are displayed when you first open the Xprofiler main window:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*InitialDisplayGraph	5000

You can use the **-disp\_max** flag to override this value.

To specify the colors of the function boxes and call arcs of the function call tree:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*defaultNodeColor	forest green
Xprofiler*defaultArcColor	royal blue

To specify the color in which a specified function box or call arc is highlighted:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*HighlightNode	red
Xprofiler*HighlightArc	red

To specify the color in which de-emphasized function boxes appear:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*SuppressNode	grey

Function boxes are de-emphasized with the **-e**, **-E**, **-f**, and **-F** flags.

*Controlling variables related to the file menu:*

You can control the size of the Load Files Dialog window, alternative search paths for locating source or library files, and the file search sequence for the Xprofiler File menu.

To specify the size of the Load Files Dialog window, use the following:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*loadFile.height	785
Xprofiler*loadFile.width	725

The **Load Files Dialog** window is called by the **Load Files** option of the **File** menu.

To specify whether a confirmation dialog box should appear whenever a file will be overwritten:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*OverwriteOK	False

The value True would be equivalent to selecting the **Set Options** option from the File menu, and then selecting the **Forced File Overwriting** option from the Runtime Options Dialog window.

To specify the alternative search paths for locating source or library files:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*fileSearchPath	.(refers to the current working directory)

The value you specify for the search path is equivalent to the search path you would designate from the Alt File Search Path Dialog window. To get to this window, choose the **Set File Search Paths** option from the File menu.

To specify the file search sequence (whether the default or alternative path is searched first):

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*fileSearchDefault	True

The value True is equivalent to selecting the **Set File Search Paths** from the File menu, and then the **Check default path(s) first** option from the Alt File Search Path Dialog window.

*Controlling variables related to the screen dump option:*

You can control the where you want the screen dump placed, the color of the screen dump, and how long to wait before capturing the screen dump for the Xprofiler Screen Dump window.

To specify whether a screen dump will be sent to a printer or placed in a file:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*PrintToFile	True

The value True is equivalent to selecting the **File** button in the **Output To** field of the Screen Dump Options Dialog window. You access the Screen Dump Options Dialog window by selecting **Screen Dump** and then **Set Option** from the File menu.

To specify whether the PostScript screen dump will be created in color or in shades of grey:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*ColorPscript	False

The value False is equivalent to selecting the **GreyShades** button in the **PostScript Output** area of the Screen Dump Options Dialog window. You access the Screen Dump Options Dialog window by selecting **Screen Dump** and then **Set Option** from the File menu.

To specify the number of grey shades that the PostScript screen dump will include (if you selected **GreyShades** in the **PostScript Output** area):

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*GreyShades	16

The value 16 is equivalent to selecting the **16** button in the **Number of Grey Shades** field of the Screen Dump Options Dialog window. You access the Screen Dump Options Dialog window by selecting **Screen Dump** and then **Set Option** from the File menu.

To specify the number of seconds that Xprofiler waits before capturing a screen image:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*GrabDelay	1

The value 1 is the default for the **Delay Before Grab** option of the Screen Dump Options Dialog window, but you can specify a longer interval by entering a value here. You access the Screen Dump Options Dialog window by selecting **Screen Dump** and then **Set Option** from the File menu.

To set the maximum number of seconds that can be specified with the slider of the **Delay Before Grab** option:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*grabDelayScale.maximum	30

The value 30 is the maximum for the **Delay Before Grab** option of the Screen Dump Options Dialog window. This means that users cannot set the slider scale to a value greater than 30. You access the Screen Dump Options Dialog window by selecting **Screen Dump** and then **Set Option** from the File menu.

To specify whether the screen dump is created in landscape or portrait format:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*Landscape	False

The value True is the default for the **Enable Landscape** option of the Screen Dump Options Dialog window. You access the Screen Dump Options Dialog window by selecting **Screen Dump** and then **Set Option** from the File menu.

To specify whether you would like information about how the image was created to be added to the PostScript screen dump:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*Annotate	False

The value False is the default for the **Annotate Output** option of the Screen Dump Options Dialog window. You access the Screen Dump Options Dialog window by selecting **Screen Dump** and then **Set Option** from the File menu.

To specify the directory that will store the screen dump file (if you selected **File** in the **Output To** field):

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*PrintFileName	/tmp/Xprofiler_screenDump.ps.0

The value you specify is equivalent to the file name you would designate in the **File Name** field of the Screen Dump Dialog window. You access the Screen Dump Options Dialog window by selecting **Screen Dump** and then **Set Option** from the File menu.

To specify the printer destination of the screen dump (if you selected **Printer** in the **Output To** field):

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*PrintCommand	qprt -B ga -c -Pps

The value qprt -B ga -c -Pps is the default print command, but you can supply a different one.

*Controlling variables related to the view menu:*

You can control the size of the window and the highlighted area for the window for the Xprofiler View menu.

To specify the size of the **Overview** window:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*overviewMain.height	300
Xprofiler*overviewMain.width	300

To specify the color of the highlight area of the **Overview** window:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*overviewGraph*defaultHighlightColor	sky blue

To specify whether the function call tree is updated as the highlight area is moved (immediate) or only when it is stopped and the mouse button released (delayed):

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*TrackImmed	True

The value True is equivalent to selecting the **Immediate Update** option from the Utility menu of the Overview window. You access the Overview window by selecting the **Overview** option from the View menu.

To specify whether the function boxes in the function call tree appear in two-dimensional or three-dimensional format:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*Shape2D	True

The value True is equivalent to selecting the **2-D Image** option from the View menu.

To specify whether the function call tree appears in top-to-bottom or left-to-right format:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*LayoutTopDown	True

The value True is equivalent to selecting the **Layout: Top and Bottom** option from the View menu.

*Controlling variables related to the filter menu:*

You can control whether the function boxes of the function call tree are clustered or unclustered and whether the call arcs of the function call tree are collapsed or expanded for the Xprofiler Filter menu.

To specify whether the function boxes of the function call tree are clustered or unclustered when the Xprofiler main window is first opened:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*ClusterNode	True

The value True is equivalent to selecting the **Cluster Functions by Library** option from the Filter menu.

To specify whether the call arcs of the function call tree are collapsed or expanded when the Xprofiler main window is first opened:

Use this resource variable:	Specify this default, or a value of your choice:
Xprofiler*ClusterArc	True

The value True is equivalent to selecting the **Collapse Library Arcs** option from the Filter menu.

---

## The svmon command

The **svmon** command provides a more in-depth analysis of memory usage.

The **svmon** command captures a snapshot of the current state of memory; however, it is not a true snapshot because it runs at the user level with interrupts enabled.

If an interval is indicated by the the **-i** flag statistics will be displayed until the command is killed or until the number of intervals which is specified with the **-i** flag, is reached.

You can generate the following different reports to analyze the memory consumption of your machine:

- command report (-C)
- detailed report (-D)
- global report (-G)
- process report (-P)
- segment report (-S)
- user report (-U)
- workload management Class report (-W)
- workload management tier report (-T)
- XML report (-X)

For more information on the **svmon** command, see *Files Reference*.

## Security

Any user of the machine can run the **svmon** command. It uses two different mechanisms to allow two different views for a non-root user.

The following will create the views:

- When **RBAC** authorization is used, the user will have the same view as the root user if their role is defined with **aix.system.stat** authorization.
- When **RBAC** is not used or when the user does not have the **aix.system.stat** authorization, the user's reports are limited to its environment or processes.

You can view the complete details of the **RBAC** in *Files Reference*.

## The svmon configuration file

A configuration file named **.svmonrc**, containing a list of **svmon -O** option, can be defined to overwrite the default values of these options. This file must be defined in the home directory of the user running **svmon** command.

At start time, the **svmon** command does the following:

- Initializes the default values for each **-O** option.
- Reads the **.svmonrc** file and overwrites the default **-O** option values with these new users default values.
- Reads the command flag defined by the user.

For example, the following **.svmonrc** file sets **svmon** to generate the default report format before the **-O** option were introduced:

```
# cat .svmonrc
summary=basic
segment=category
pgsz=on
```

### Note:

- When an option is not recognized in the file, it is ignored.

- When an option is defined more than once, only the last value will be used.

## Summary report metrics

The command report (-C option), global report (-G option), process report (-P option), user report (-U option), and workload management class report (-W option) include the same set type of summary metrics.

The following are the summary metrics:

- The **-O summary=basic** option used alone produces compact reports for the command report (-C), the process report (-P), the user report (-U), and the workload management class report (-W).
- The **-O summary=longreal** option used alone produces a compact report of the global report (-G).

In a system with Active Memory™ Expansion enabled, two new summary report metrics are available for global report (-G option).

- The **-O summary=ame option** used alone produces detailed memory compression information for the global report (-G).
- The **-O summary=longame** option used alone produces a compact report of memory compression information for the global report (-G).

## Basic summary report metrics

This is the *compatibility* mode with the previous versions of **svmon** command (before the **-O** option was introduced). This format uses 80 columns.

In these summaries, the following columns are always displayed:

Item	Descriptor
Inuse	Number of frames containing pages (expressed in <unit>) used by the report entities.
Pin	Number of frames containing pinned pages (expressed in <unit>) used by the report entities.
Pin	Number of pages (expressed in <unit>) allocated in the paging space by the report entities.
Virtual	Number of pages (expressed in <unit>) allocated in the virtual space by the report entities.

## Report formatting options

Review the report formatting options for the **svmon** command.

The svmon configuration file can generate two types of reports for the **-G**, **-P**, **-U**, **-C**, and **-W** option:

- **Compact report**, which is a one-line-per-entity report.
- **Long report**, which uses several lines per entity.

For the **-G** option, you can switch from the standard report to the compact report with the option **-O summary=longreal**. For the **-P**, **-U**, **-C** and **-W** options, a compact report is reported when the option **-O summary=basic** is set and the option **-O segment=off** is set (default value).

The following **-O** options can be used in both compact or long reports:

- **-O format=[80,160,nolimit]**: This option sets the width of the report. The default width of most reports is 80 characters. But, some reports need 160 characters, in which case this option is implicitly set. You can always specify to display the reports with more columns, to eliminate truncated strings.
- **-O timestamp=[on | off]**: When this flag is set to **on**, a timestamp, recorded when the svmon command begins retrieving data, is displayed at the beginning of the report. Because the data collection can take some time, you can use the **-O timestamp=on** with the **-i** flag to specify timestamp intervals. The time specified with the **-i** flag is the interval between the end of one **svmon** command iteration and the start of the next one.

**Example:**

In this example, the command line specifies to run `svmon` 3 times every 5 seconds. The timestamp and command line are set with the `.svmonrc` file.

- **-O commandline=[on|off]**: when set to on, this option adds the command line you use to produce the report in the report header.

```
# svmon -G -i 5 3
Command line : svmon -G -i 5 3
.svmonrc: -0 timestamp=on,commandline=on
Unit: page                                     Timestamp: 11:23:02
-----
      size      inuse      free      pin      virtual  available
memory    262144    227471    34673    140246    223696    53801
pg space  131072      39091
-----
      work      pers      clnt      other
pin        113676         0         0     10186
in use    189693         0     29586
Unit: page                                     Timestamp: 11:23:07
-----
      size      inuse      free      pin      virtual  available
memory    262144    227473    34671    140243    223697    53800
pg space  131072      39091
-----
      work      pers      clnt      other
pin        113673         0         0     10186
in use    189694         0     29587
Unit: page                                     Timestamp: 11:23:12
-----
      size      inuse      free      pin      virtual  available
memory    262144    227475    34670    140244    223699    53799
pg space  131072      39091
-----
      work      pers      clnt      other
pin        113674         0         0     10186
in use    189696         0     29587
```

### Example:

```
# svmon -G -O commandline=on
Command line : svmon -G -O commandline=on
Unit: page
-----
      size      inuse      free      pin      virtual  available
memory    262144    227312    34832    140242    223536    53961
pg space  131072      39091
-----
      work      pers      clnt      other
pin        113672         0         0     10186
in use    189533         0     29587
```

- **-O unit=[auto,page,KB,MB,GB]**: this option is set to **page** by default. In this case, the reported metrics for each segment are in the segment page size:
  - s are 4 KB pages
  - m are 64 KB pages
  - L are 16 MB pages
  - S are 16 GB pages

When **auto**, **KB**, **MB**, or **GB** are used, only the 3 most significant digits are displayed. You should be careful when interpreting the results with a unit other than **page**. When the **auto** setting is selected, the abbreviated units are specified immediately after each metric (K for kilobytes, M for megabytes, or G for gigabytes).

## Examples:

This is the same report using different **unit** options:

```
# svmon -G -O unit=page
```

```
Unit: page
```

```
=====
      size      inuse      free      pin      virtual  available
memory    1048576    220617    827959    113371    194382    819969
pg space   131072      1280

      work      pers      clnt      other
pin        78124        0         0        35247
in use    194382        0       26235
```

```
# svmon -G -O unit=GB
```

```
Unit: GB
```

```
=====
      size      inuse      free      pin      virtual  available
memory     4.00      0.84      3.16      0.43      0.74      3.13
pg space   0.50        0

      work      pers      clnt      other
pin        0.30        0         0        0.13
in use    0.74        0       0.10
```

```
# svmon -G -O unit=auto
```

```
Unit: auto
```

```
=====
      size      inuse      free      pin      virtual  available
memory    4.00G    860.78M    3.16G    442.86M    758.29M    3.13G
pg space  512.00M    5.00M

      work      pers      clnt      other
pin       305.17M    0K         0K       137.68M
in use   758.29M    0K       102.49M
```

## Segment details and -O options

Review the segment details and -O options for the **svmon** command.

Segment details can be added to the user, command, process, and class reports after the summary when the **-O segment=on** or **-O segment=category** option is set to:

- **-O segment=on**, the list of segments is displayed for each entity.
- **-O segment=category**, the segments are grouped into the following three categories for each entity:
  - **system**: used by the system
  - **exclusive**: used only by one entity, except for shared memory (shm) segments
  - **shared**: used by two or more entities, except for shared memory (shm) segments

The following table contains the description of the items that the svmon reports for segment information.

*Table 8. Description table*

Segment type	Segment usage	Description
persistent	log files	IO space mapping
persistent	files and directories	device name : inode number
persistent	large files	large file device name : inode number
mapping	files mapping	mapped to sid source sid no longer mapped
working	data areas of processes and shared memory segments	dependent on the role of the segment based on the VSID and ESID

Table 8. Description table (continued)

Segment type	Segment usage	Description
client	NFS and CD-ROM files	dependent on the role of the segment based on the VSID and ESID
client	JFS2 files	device name: inode number
rmapping	I/O space mapping	dependent on the role of the segment based on the VSID and ESID

When **-O segment=on** or **-O segment=category** is set, additional details can be added:

- **-O range=on**: each segment is followed by the ranges, within the segment, where pages have been allocated.

**Example:**

```
# svmon -P 1 -O range=on
Unit: page
```

```
-----
      Pid Command          Inuse   Pin   Pgsp Virtual
      1  init              16874  8052    0   16858

      Vsid   Esid Type Description          PSize Inuse Pin Pgsp Virtual
      0      0 work kernel segment          m    576 503  0    576
                Addr Range: 0..3945
      d802d   d work shared library text          m    467  0  0    467
                Addr Range: 0..562
      1001    2 work process private              s    98  4  0    98
                Addr Range: 0..179 : 65309..65535
      1c101d   f work shared library data          s    72  0  0    72
                Addr Range: 0..545
      1a101b   1 clnt code,/dev/hd2:531           s    11  0  -    -
                Addr Range: 0..10
      21023    - clnt /dev/hd4:1236              s     5  0  -    -
                Addr Range: 0..4
```

- **-O pidlist=on** and **-O pidlist=number**: adds either the list of PIDs of processes or the number of processes using this segment. It also adds either the user name or the command name corresponding to each PID. When the **-@** flag is added, the WPAR name is also added.

**Example:**

```
# svmon -C yes -O pidlist=on
Unit: page
```

```
-----
      Command          Inuse   Pin   Pgsp Virtual
      yes              16893  8112    0   16892

      Vsid   Esid Type Description          PSize Inuse Pin Pgsp Virtual
      0      0 work kernel segment          m    579 506  0    579
                System segment
      d802d   d work shared library text          m    468  0  0    468
                Shared library text segment
      111750   2 work process private              s    18  4  0    18
                pid(s)=348386
      e174f   2 work process private              s    18  4  0    18
                pid(s)=340154
      131752   2 work process private              s    18  4  0    18
                pid(s)=389352
      1c171d   2 work process private              s    18  4  0    18
                pid(s)=360640
      81749    f work shared library data          s    17  0  0    17
                pid(s)=340154
      71726    f work shared library data          s    17  0  0    17
                pid(s)=360640
      101751   f work shared library data          s    17  0  0    17
                pid(s)=348386
```

```

121753      f work shared library data      s   17   0   0   17
            pid(s)=389352
a172b      1 clnt code,/dev/hd2:338      s    1   0   -   -
            pid(s)=389352, 360640, 348386, 340154

```

```

# svmon -C yes -O pidlist=number
Unit: page

```

```

=====
Command          Inuse      Pin      Pgps  Virtual
yes              16893     8112      0     16892

  Vsid   Esid Type Description          PSize  Inuse  Pin Pgps Virtual
    0     0 work kernel segment      m    579  506  0    579
          System segment
d802d    d work shared library text  m    468   0   0    468
          Shared library text segment
111750   2 work process private     s    18   4   0    18
          pid number=1
e174f    2 work process private     s    18   4   0    18
          pid number=1
131752   2 work process private     s    18   4   0    18
          pid number=1
1c171d   2 work process private     s    18   4   0    18
          pid number=1
81749    f work shared library data  s    17   0   0    17
          pid number=1
71726    f work shared library data  s    17   0   0    17
          pid number=1
101751   f work shared library data  s    17   0   0    17
          pid number=1
121753   f work shared library data  s    17   0   0    17
          pid number=1
a172b    1 clnt code,/dev/hd2:338   s     1   0   -    -
          pid number=4

```

- **-O filename=on:** Each persistent segment's complete, corresponding file name is shown. Note that because files can be deeply nested, running the **svmon** command with this flag, or with the **-S** and **-i** flags, can take significantly more time.

**Example:**

```

# svmon -P 266414 -O filename=on,format=nolimit
Unit: page

```

```

=====
Pid Command      Inuse      Pin      Pgps  Virtual
266414 IBM.ServiceRMD 17227     8116      0     17174

  Vsid   Esid Type Description          PSize  Inuse  Pin Pgps Virtual
    0     0 work kernel segment      m    579  506  0    579
d802d    d work shared library text  m    468   0   0    468
31322    2 work process private     s    202   4   0    202
171316   f work shared library data  s    167   0   0    167
1e133f   - work                      s     52  16   0    52
11320    1 clnt code,/dev/hd2:9929   s     51   0   -    -
          /opt/rsct/bin/IBM.ServiceRMD
b134a    - clnt /dev/hd9var:368          s     1   0   -    -
          /var/ct/3394394444/registry/local_tree/IBM.ServiceEvent,Class
a134b    - clnt /dev/hd9var:372          s     1   0   -    -
          /var/ct/3394394444/registry/local_tree/IBM.ServiceEvent,Resources
1341     4 work shared memory segment s     1   0   0     1
121333   3 mmap maps 2 source(s)     s     0   0   -    -
131312   - clnt /dev/hd9var:360          s     0   0   -    -
          /var/ct/IBM.ServiceRM.stderr
111310   - clnt /dev/hd9var:418          s     0   0   -    -
          /var/ct/3394394444/lck/mc/RMIBM.ServiceRM

```

- **-O mapping=on:** adds information about the source segment and the mapping segment when a segment is used to map another segment. If this option is used, source segments not belonging to the

process address space are listed in the report and marked with an asterisk (\*). Note that they are also taken into account in the process-level summary's number calculations.

**Example:**

```
# svmon -P 266414 -O mapping=off
Unit: page
```

```
-----
  Pid Command      Inuse   Pin   Pgps Virtual
 266414 IBM.ServiceRM 17227  8116    0   17174
```

```
# svmon -P 266414 -O mapping=on
Unit: page
```

```
-----
  Pid Command      Inuse   Pin   Pgps Virtual
 266414 IBM.ServiceRM 17231  8116    0   17174
```

```
# svmon -P 266414 -O mapping=on,segment=on
Unit: page
```

```
-----
  Pid Command      Inuse   Pin   Pgps Virtual
 266414 IBM.ServiceRM 17231  8116    0   17174
```

```
-----
  Vsid  Esid Type Description          PSize Inuse Pin Pgps Virtual
 0      0 work kernel segment          m    579 506  0    579
d802d  d work shared library text    m    468  0    0    468
31322  2 work process private        s    202  4    0    202
171316 f work shared library data    s    167  0    0    167
1e133f - work                          s    52  16    0    52
11320  1 clnt code,/dev/hd2:9929     s    51  0    -    -
191338 * - clnt /dev/hd9var:363        s     3  0    -    -
131332 * - clnt /dev/hd9var:361        s     1  0    -    -
b134a  - clnt /dev/hd9var:368        s     1  0    -    -
a134b  - clnt /dev/hd9var:372        s     1  0    -    -
1341   4 work shared memory segment  s     1  0    0    1
131312 - clnt /dev/hd9var:360        s     0  0    -    -
121333 3 mmap maps 2 source(s)       s     0  0    -    -
      source(s)=131332, 191338
111310 - clnt /dev/hd9var:418        s     0  0    -    -
```

In these examples, the mapping option adds or removes the mapping source segments which are not in the address space of the process number 266414. There is a difference of four pages (three pages from segment 191338, and one page from segment 131332) in the Inuse consumption between **-O mapping=off** and **-O mapping=on**.

- **-O sortseg=[inuse | pin | pgsp | virtual]**: by default,, all segments are sorted in decreasing order of real memory usage (the Inuse metric) for each entity (user, process, command, segment). Sorting options for the report include the following:
  - Inuse: real memory used
  - Pin: pinned memory used
  - Pgps: paging space memory used
  - Virtual: virtual memory used

**Examples:**

```
# svmon -P 1 -O unit=KB,segment=on
Unit: KB
```

```
-----
  Pid Command      Inuse   Pin   Pgps Virtual
 1 init            67752  32400    0   67688
```

```
-----
  Vsid  Esid Type Description          PSize Inuse Pin Pgps Virtual
 0      0 work kernel segment          m  37056 32384  0  37056
d802d  d work shared library text    m  29952  0    0  29952
1001   2 work process private        s   392  16    0   392
1c101d f work shared library data    s   288  0    0   288
```

```

1a101b      1 clnt code,/dev/hd2:531      s    44    0    -    -
21023      - clnt /dev/hd4:1236                s    20    0    -    -

```

```

# svmon -P 1 -O unit=KB,segment=on,sortseg=pin
Unit: KB

```

```

-----
  Pid Command      Inuse    Pin    Pgps Virtual
    1  init          67752   32400     0   67688

  Vsid   Esid Type Description      PSize Inuse  Pin Pgps Virtual
    0     0 work kernel segment      m  37056 32384 0  37056
  1001   2 work process private      s   392  16  0   392
21023   - clnt /dev/hd4:1236          s    20   0  -    -
d802d   d work shared library text      m  29952  0  0  29952
1a101b  1 clnt code,/dev/hd2:531      s    44   0  -    -
1c101d  f work shared library data      s   288   0  0   288

```

- **-O mpss=[on | off]**: breaks down the metrics for multiple page size segments, by page size.

#### Examples:

```

# svmon -P 1 -O segment=on,mpss=on
Unit: page

```

```

-----
  Pid Command      Inuse    Pin    Pgps Virtual
    1  init          14557   5492     0   14541

  Vsid   Esid Type Description      PSize Inuse  Pin Pgps Virtual
  502d   d work shared library text      m   502   0  0   502
  2002   0 work kernel segment          m   396  343 0   396
10001   2 work process private          s   100   4  0   100
                                     m    0   0  0    0
  8019   f work shared library data      s    73   0  0   73
                                     m    0   0  0    0
  6017   1 clnt code,/dev/hd2:532      s    11   0  -    -
e01f    - clnt /dev/hd4:893            s     5   0  -    -

```

**sm** pages are separated into **s** and **m** pages. The metrics reported are in the unit of the page size: **s** pages are 4 KB and **m** pages are 64 KB.

- **-O shmid=[on | off]**: displays shared memory IDs associated with shared memory segments. This option does not work you run it in inside a WPAR.

#### Examples:

```

# svmon -P 221326 -O commandline=on,segment=on,shmid=on,filterprop=notempty
Command line : svmon -P 221326 -O commandline=on,segment=on,shmid=on,filterprop=notempty

```

```

Unit: page

```

```

-----
  Pid Command      Inuse    Pin    Pgps Virtual
221326  java          20619   6326   9612  27584

  Vsid   Esid Type Description      PSize Inuse  Pin Pgps Virtual
  502d   d work text or shared-lib code seg m   585   0  1   585
    0     0 work kernel segment          m   443  393 4   444
14345   3 work working storage          sm  2877  0 7865 9064
15364   e work shared memory segment      sm  1082  0 1473 1641
                                     shmid:3
1b36a   f work working storage          sm   105   0 106  238
17386   - work                          s   100  34  64  146
1a38b   2 work process private          sm     7   4  24   31

```

## Additional -O options

Review the additional -O options for the **svmon** command.

The following additional options are:

- **-O process=on**: adds, for a given entity, the memory statistics of the processes belonging to the entity (user name or command name). If you specify the **-@** flag, each process report is followed by a line that shows the WPAR name. This option is only valid for the User and the Command reports.

All reports containing two or more entities can be filtered and/or sorted with the following options:

- **-O sortentity=[inuse | ...]**: specifies the summary metric used to sort the entities (process, user, and so on) when several entities are printed in a report.

The list of metrics permitted in the report depend on the type of summary (**-O** summary option) chosen. Any of the metrics used in a summary can be used as a sort key.

**Examples:**

```
# svmon -P -t 5 -O summary=off -O segment=off -O sortentity=pin
Command line : svmon -P -t 5 -O summary=off -O segment=off -O sortentity=pin
Unit: page
```

```
-----
```

Pid	Command	Inuse	Pin	Pgsp	Virtual
127044	dog	9443	8194	0	9443
0	swapper	9360	8176	0	9360
8196	wait	9360	8176	0	9360
53274	wait	9360	8176	0	9360
237700	rpc.lockd	9580	8171	0	9580

- **-O filtercat=[off | exclusive | kernel | shared | unused | unattached]**: this option filters the output by segment category. You can specify more than one filter at a time.

**Note:** Use the **unattached** filter value with the **-S** report because unattached segments cannot be owned by a process or command.

**Examples:**

```
# svmon -P 1 -O unit=KB,segment=on,sortseg=pin,filtercat=off
Unit: KB
```

```
-----
```

Pid	Command	Inuse	Pin	Pgsp	Virtual
1	init	58684	28348	0	58616

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
0	0	work	kernel segment	s	30948	28332	0	30948
6902f	2	work	process private	s	396	16	0	396
6c10d	d	work	shared library text	s	26996	0	0	26996
a9017	f	work	shared library data	s	276	0	0	276
b9015	1	clnt	code,/dev/hd2:531	s	44	0	-	-
f101c	-	clnt	/dev/hd4:824	s	24	0	-	-

```
# svmon -P 1 -O unit=KB,segment=on,sortseg=pin,filtercat=shared
Unit: KB
```

```
-----
```

Pid	Command	Inuse	Pin	Pgsp	Virtual
1	init	58684	28348	0	58616

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
6c10d	d	work	shared library text	s	26996	0	0	26996
a9017	f	work	shared library data	s	276	0	0	276

- **-O filtertype=[off | working | persistent | client]**: this option allows you to filter on the **Type** column of the segment details. You can specify more than one filter at a time.

**Examples:**

```
# svmon -P 495618 -O segment=on,filtertype=client
Unit=page
```

```
-----
```

Pid	Command	Inuse	Pin	Pgsp	Virtual
495618	IBM.AuditRMD	308	0	0	0

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
1619f7	-	clnt	/dev/fs1v07:417	s	253	0	-	-
31382	1	clnt	code,/dev/hd2:9803	s	36	0	-	-
1319f2	-	clnt	/dev/fs1v07:400	s	16	0	-	-
1a19db	-	clnt	/dev/fs1v07:399	s	1	0	-	-
a19cb	-	clnt	/dev/fs1v07:397	s	1	0	-	-
919c8	-	clnt	/dev/fs1v07:398	s	1	0	-	-
519c4	-	clnt	/dev/fs1v07:358	s	0	0	-	-
1f19de	-	clnt	/dev/fs1v07:325	s	0	0	-	-

Only the **client** segments for process number 495618 are displayed. Note that the summary only reports the sum of the metrics displayed in the entity details. This means that the summary numbers shown here do not represent the complete memory consumption for this process, only its consumption using client segments.

• **-O filterprop=[off | notempty | data | text]:**

This option allows filtering on the segment property:

- **Data:** Computational segments consisting of the pages belonging to working-storage segments or program text (executable files) segments.
- **Text:** Non-computational segments of *File memory* (or file pages), which are the remaining pages. These pages are usually from permanent data files in persistent storage.
- **Notempty:** Segments where the Inuse value is not 0.

You can specify more than one property at a time.

**Examples:**

```
# svmon -C yes -O segment=category,filterprop=notempty
```

Unit: page

```
=====
```

Command	Inuse	Pin	Pgsp	Virtual
yes	16256	6300	80	16271

```
.....
```

SYSTEM segments	Inuse	Pin	Pgsp	Virtual
	7088	6288	64	7104

```
.....
```

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
0	0	work	kernel segment	m	443	393	4	444

```
.....
```

EXCLUSIVE segments	Inuse	Pin	Pgsp	Virtual
	112	12	0	111

```
.....
```

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
851d	2	work	process private	sm	19	4	0	19
e6fb	2	work	process private	sm	19	4	0	19
1940f	2	work	process private	sm	19	4	0	19
1017	f	work	shared library data	sm	18	0	0	18
6f73	f	work	shared library data	sm	18	0	0	18
4a71	f	work	shared library data	sm	18	0	0	18
24626	1	clnt	code,/dev/hd2:338	s	1	0	-	-

```
.....
```

SHARED segments	Inuse	Pin	Pgsp	Virtual
	9056	0	16	9056

```
.....
```

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
502d	d	work	shared library text	m	566	0	1	566

```
# svmon -C yes -O segment=category,filterprop=text
```

Unit: page

```
=====
```

Command	Inuse	Pin	Pgsp	Virtual
---------	-------	-----	------	---------

```

yes                                1      0      0      0

.....
EXCLUSIVE segments                Inuse   Pin    Pgps  Virtual
                                  1      0      0      0

  Vsid   Esid Type Description          PSize  Inuse   Pin Pgps  Virtual
  24626   1 clnt code,/dev/hd2:338      s      1      0   -    -

```

```
# svmon -C yes -0 segment=category,filterprop=data
```

```
Unit: page
```

```

=====
Command                Inuse   Pin    Pgps  Virtual
yes                    16255  6300   80    16271

```

```

.....
SYSTEM segments        Inuse   Pin    Pgps  Virtual
                        7088   6288   64    7104

```

```

  Vsid   Esid Type Description          PSize  Inuse   Pin Pgps  Virtual
  0       0 work kernel segment            m     443   393   4    444

```

```

.....
EXCLUSIVE segments    Inuse   Pin    Pgps  Virtual
                        111    12     0     111

```

```

  Vsid   Esid Type Description          PSize  Inuse   Pin Pgps  Virtual
  e6fb   2 work process private            sm    19     4   0    19
  851d   2 work process private            sm    19     4   0    19
  1940f  2 work process private            sm    19     4   0    19
  4a71   f work shared library data         sm    18     0   0    18
  1017   f work shared library data         sm    18     0   0    18
  6f73   f work shared library data         sm    18     0   0    18

```

```

.....
SHARED segments       Inuse   Pin    Pgps  Virtual
                        9056   0      16    9056

```

```

  Vsid   Esid Type Description          PSize  Inuse   Pin Pgps  Virtual
  502d   d work shared library text         m     566   0    1    566

```

- **-O filterpgsz=[off | s | m | L | S]**: this option filters the segment based on their page size. Multiple page size segments can be selected using multiple code letters in the form <min\_size><max\_size>: **-O filterpgsz="sm s"** filters the small page segments and the multiple page size segments with small and medium pages.

For the **-P** report however, the behavior is slightly different. Indeed, the report contains all the processes having at least one page of the size specified with the **-O filterpgsz** option, and for these processes, svmon displays all their segments (whatever their page size).

#### Examples:

```
# svmon -P -0 segment=on,filterpgsz=L
```

```
Unit: page
```

```

-----
  Pid Command                Inuse   Pin    Pgps  Virtual
  270450 ptxtst_shm_a1          21674  17136   0    21658

  Vsid   Esid Type Description          PSize  Inuse   Pin Pgps  Virtual
  10002   0 work kernel segment            m     607   556   0    607
  1b9b35  70000000 work default shmat/mmap      L      2     2   0     2
  28005   9fffffff work shared library      s    1767   0   0    1767
  188030  90000000 work shared library text       m     110   0   0    110
  1010a2  90020014 work shared library      s     114   0   0    114
  209b43  f0000002 work process private          m      5     3   0     5
  3c107a  9fffffff clnt USLA text,/dev/hd2:2774 s     13     0   -     -
  7000e   9ffffffe work shared library      s     11     0   0     11

```

```

 21b06 9001000a work shared library data      s    11    0    0    11
241b4a 80020014 work  USLA heap                          s     5    0    0     5
281b52 8fffffff work  private load data                       s     4    0    0     4
131a24          10 clnt text data BSS heap,
/dev/hd2:2745
2a1b56          11 work  text data BSS heap                       s     1    0    0     1
159a29 ffffffff work  application stack                          s     1    0    0     1

```

```

-----
  Pid Command      Inuse   Pin    Pgsz  Virtual
266262 ptxtst_shm_a1   17578  13040     0   17562

  Vsid   Esid Type Description          PSize  Inuse  Pin Pgsz Virtual
 10002   0 work kernel segment      m    607  556  0    607
119ba1 70000000 work default shmat/mmap   L     1    1    0     1
 28005  9fffffff work shared library      s   1767    0    0   1767
188030 90000000 work shared library text m    110    0    0   110
1010a2 90020014 work shared library      s    114    0    0   114
3e19fe f0000002 work process private   m     5    3    0     5
3c107a 9fffffff clnt USLA text,/dev/hd2:2774 s    13    0    -     -
 7000e 9fffffff work shared library      s    11    0    0    11
 c1a1a 9001000a work shared library data s    11    0    0    11
2a9a57 80020014 work  USLA heap                          s     5    0    0     5
149b2b 8fffffff work  private load data                       s     4    0    0     4
131a24          10 clnt text data BSS heap,
/dev/hd2:2745
1f9b3d ffffffff work  application stack                          s     1    0    0     1
2b1b54          11 work  text data BSS heap                       s     1    0    0     1
      Addr Range: 0..3012

```

In this example, all processes running large pages are reported. For these processes, all segments are displayed whatever their page size.

```
# svmon -U root -O filterpgsz=L,segment=on
```

Unit: page

```

=====
User              Inuse   Pin    Pgsz  Virtual
root              12288  12288     0   12288

  Vsid   Esid Type Description          PSize  Inuse  Pin Pgsz Virtual
1b9b35 70000000 work default shmat/mmap   L     2    2    0     2
119ba1 70000000 work default shmat/mmap   L     1    1    0     1

```

```
# svmon -C ptxtst_shm_alt_pgsz -O filterpgsz=L,segment=on
```

Unit: page

```

=====
Command          Inuse   Pin    Pgsz  Virtual
ptxtst_shm_alt_pgsz
12288  12288     0   12288

  Vsid   Esid Type Description          PSize  Inuse  Pin Pgsz Virtual
1b9b35 70000000 work default shmat/mmap   L     2    2    0     2
119ba1 70000000 work default shmat/mmap   L     1    1    0     1

```

The previous two examples illustrate the difference of behavior with *-P*. In these examples, for the given entity, only the pages of the given size are kept in the report.

## Reports details

Review the output for the **svmon** command reports.

To display compact report of memory expansion information (in a system with Active Memory Expansion enabled), enter:

```
# svmon -G -O summary=longame
```

Unit: page

---

Active Memory Expansion								
Size	Inuse	Free	DXMSz	UCMinuse	CMInuse	TMSz	TMFr	CPSz
262144	152625	43055	67640	98217	54408	131072	6787	26068

CPFr	txf	cxf	CR
3888	2.00	1.48	2.45

## Global report

To print the Global report, specify the **-G** flag. The Global report displays a system-wide detailed real memory view of the machine. This report contains various summaries, only the memory and inuse summaries are always displayed.

When the **-O summary** option is not used, or when it is set to **-O summary=basic**, the column headings used in global reports summaries are:

### memory

Specifies statistics describing the use of memory, including:

**size** Number of frames (size of real memory)

**Tip:** This does not include the free frames that have been made unusable by the memory sizing tool, the `rmss` command.

**inuse** Number of frames containing pages

**Tip:** On a system where a reserved pool is defined (such as the 16 MB page pool), this value includes the frames reserved for any of these reserved pools, even if they are not used.

**free** Number of frames free in all memory pools. There may be more memory available depending on the file cache (see: available)

**pin** Number of frames containing pinned pages

**Tip:** On a system where a reserved pool is defined (such as the 16 MB page pool), this value includes the frames reserved for any of these reserved pools.

### virtual

Number of pages allocated in the system virtual space

### available

Amount of memory available for computational data. This metric is calculated based on the size of the file cache and the amount of free memory.

**stolen** Displayed only when `rmss` runs on the machine. Number of frames stolen by `rmss` and marked unusable by the VMM

### mmode

Indicates the memory mode the system is running.

Following are the current possible values for `mmode`.

**Ded** Neither Active Memory Sharing nor Active Memory Expansion is enabled.

**Shar** Only Active Memory Sharing is enabled, Expansion is not enabled.

#### Ded-E

Active Memory Sharing is not enabled but Expansion is enabled.

**Shar-E** Both Active Memory Sharing & Active Memory Expansion are enabled.

**ucomprsd**

This gives a breakdown of expanded memory statistics in the uncompressed pool, including: **inuse** Number of uncompressed pages that are in use.

**comprsd**

This gives a breakdown of expanded memory statistics in the compressed pool, including: **inuse** Number of compressed pages in the compressed pool.

**pg space**

Specifies statistics describing the use of paging space.

**size** Size of paging space

**inuse** Number of paging space pages used

**ucomprsd**

This gives a breakdown of expanded memory statistics of working pages in the uncompressed pool, including: **inuse** Number of compressed pages in the compressed pool.

**comprsd**

This gives a breakdown of expanded memory statistics of working pages in the compressed pool, including: **inuse** Number of compressed pages in the compressed pool.

**Pin** Specifies statistics on the subset of real memory containing pinned pages, including:

**work** Number of frames containing working segment in use pages

**pers** Number of frames containing persistent segment in use pages

**clnt** Number of frames containing client segment in use pages

**other** Number of frames containing all memory pages that do not use segment control blocks. Examples for these memory pages are physical to virtual page tables (PVT), physical to virtual page lists (PVLIST), and kernel special purpose (KSP) region.

**in use** Specifies statistics on the subset of real memory in use, including:

**work** Number of frames containing working segment in use pages

**pers** Number of frames containing persistent segment in use pages

**clnt** Number of frames containing client segment in use pages

**ucomprsd**

This gives a breakdown of expanded memory statistics of working pages in the uncompressed pool, including: **inuse** Number of uncompressed pages in the compressed pool.

**comprsd**

This gives a breakdown of expanded memory statistics of working pages in the compressed pool, including: **inuse** Number of compressed pages in the compressed pool.

**PageSize**

Displayed only if alternative page sizes (non-4KB) are available on the system and the option **-O pgsz=on** is set. It displays separate sets of statistics for each of the page sizes available on the system.

**PageSize**

Page size for the following statistics

**PoolSize**

Number of pages in the pool for a page size using reserved pools (such as the 16 MB page pool)

**inuse** Number of pages of this size that are used

**pgsp** Number of pages of this size that are allocated in the paging space

- pin** Number of pinned pages of this size
- virtual** Number of pages of this size that are allocated in the system virtual space
- ucomprsd** Number of pages of this size that are in uncompressed form.

**Domain affinity**

Displays statistics per affinity domain. This is activated by the **-O affinity=on** option.

- total** Total memory in this affinity domain.
- used** Total memory used in this affinity domain.
- free** Total remaining free memory in this affinity domain
- lcpus** List of logical cpus in this affinity domain.

**Note:** The **ucomprsd** and **comprsd** metrics are available only in systems with Active Memory Expansion enabled. **-O summary=ame** option is needed to show these expanded memory statistics.

When the **-O summary=ame** option is used in a system with Active Memory Expansion enabled, the following memory information (true memory snapshot) is displayed in the global report summary at the end of the regular report.

**True Memory**

True memory size.

**ucomprsd**

Displays detailed information about the uncompressed pool, including

- CurSz** Current size of the uncompressed pool.
- %Cur** Percentage of true memory used by the uncompressed pool
- TgtSz** Target size of the uncompressed pool needed to achieve the target memory expansion factor.
- % Tgt** Percentage of true memory that will be used by the uncompressed pool when the target memory expansion factor is achieved.

**comprsd**

Displays detailed information about the compressed pool, including:

- CurSz** Current size of the compressed pool
- %Cur** Percentage of true memory used by the compressed pool.
- TgtSz** Target size of the compressed pool needed to achieve the target memory expansion factor.
- % Tgt** Percentage of true memory that will be used by the compressed pool when the target memory expansion factor is achieved
- % Max** Percentage of true memory that will be used by the compressed pool when the compressed pool achieves maximum size.

**CRatio**

Compression ratio

**AME** Displays the following information

- txf** Target Memory Expansion Factor
- cx** Current Memory Expansion Factor

**dx**f     Deficit factor to reach the target expansion factor

**dx**m     Deficit memory to reach the target expansion

**Note:** The above true memory section of expanded memory statistics can be turned off using the option **-O tmem=off**.

When the **-O summary=longreal** option is set with **-G**, the compact report header contains the following metrics:

**Size**     Number of frames (size of real memory)

**Tip:** This includes any free frames that have been made unusable by the memory sizing tool, the **rmss** command.

**Inuse**     Number of frames containing pages

**Tip:** On a system where a reserved pool is defined (such as the 16 MB page pool), this value includes the frames reserved for any of these reserved pools.

**Free**     Number of frames free in all memory pools. There may be more memory available depending on the file cache (see: available)

**Pin**     Number of frames containing pinned pages

**Tip:** On a system where a reserved pool is defined (such as the 16 MB page pool), this value includes the frames reserved for any of these reserved pools.

**Virtual**

Number of pages allocated in the system virtual space

**Available**

Amount of memory available for computational data. This metric is calculated based on the size of the file cache and the amount of free memory.

**Pgsp**     Number of pages allocated in the paging space

When **-G** is used in conjunction with **-@** the following additional column is displayed:

**WPAR**     WPAR name

**Note:**

- If you specify the **-@** flag without a list, the flag has no effect except when the **-O summary** option is used, then the WPAR name is added in the last column.  
If a list is provided after the **-@** flag, the **svmon** command report includes one section per WPAR listed. If **ALL** is specified, a system-wide and a global section will also be present. Any metric not available on a per WPAR basis is either replaced by the corresponding global value (in the case of **-@ WparList**) or by a "-" (in the case of **-@ ALL**).
- Global values are displayed instead of a per WPAR metrics. They are flagged by the presence of a **@** in the report.
- Some of the metrics are only available on a per WPAR basis if the **WLM** is used to restrict the WPAR memory usage.

When the **-O summary=longame** option is set with **-G**, the compact report header contains the following Active Memory Expansion metrics

**Size**     Expanded memory size

**Inuse**     Number of pages in use (expanded form).

**Free**     Size of freelist (expanded form).

**DXMSz**

Deficit memory to reach the target memory expansion

**UCMInuse**

Number of uncompressed pages in use.

**CMInuse**

Number of compressed pages in the compressed pool.

**TMSz** True memory size

**TMFr** True number of free page frames

**CPSz** Size of Compressed pool.

**CPFr** Size of Uncompressed pool.

**txf** Target Memory Expansion Factor

**cx** Current Memory Expansion Factor

**CR** Compression Ratio.

**Examples**

- To display the default svmon report, with automatic unit selection, enter:

```
# svmon -O summary=basic,unit=auto,pgsz=on
or
```

```
# svmon -G -O unit=auto,pgsz=on
```

```
Unit: auto
```

```
-----
memory      size      inuse      free      pin      virtual  available
pg space    512.00M  13.4M
```

```
pin         work      pers      clnt      other
in use      2.65G    0K        124.55M  924.95M
```

```
PageSize  PoolSize  inuse      pgsp      pin      virtual
s  4 KB    -         2.41G    13.4M    1.34G    2.29G
m  64 KB   -         376.81M  0K       241.81M  376.81M
L  16 MB   5         0K       0K       80.0M    0K
```

The memory size of the system is 31GB. This size is split into the in-used frames for 2.85 GB and into the free frames for 28.1 GB. 1.65 GB are pinned in memory, 2.65 GB are allocated in the system virtual space and 27.3 GB are available to be used as computational data by new processes.

The inuse and pin values include the pages reserved for the 16 MB page memory pool (80 MB).

The size of the paging space is 512 MB, where 13.4 MB are used.

The pinned frames (1.65 GB) is composed of working segment pinned pages (688.57 MB) and 924.95 MB of other pin pages (can be used by the kernel for example), not counting the memory not used but pinned by the 16 MB page pool.

The number of frames containing pages (2.85 GB) is composed of working segment pages (2.65 GB) and client segment pages (124.55 MB), not counting the memory that is only reserved but counted inuse from the 16 MB pool.

Then statistics are displayed for each page size available on the system. For instance, the 16 MB page pool is composed of 5 pages of 16 MB. None of these are used, none are in the paging space (since they are all pinned), all of these are pinned, and none are in the system's virtual space.

- To also display the affinity domain information, enter:

```
# svmon -G -O unit=MB,pgsz=on,affinity=on
```

```
Unit: MB
```

```
-----
      size      inuse      free      pin      virtual  available
memory  31744.00  3055.36  28688.64  1838.84  2859.78  27911.33
pg space  512.00      14.7

      work      pers      clnt      other
pin      833.90      0         0         924.95
in use   2859.78      0        163.59

PageSize PoolSize      inuse      pgsp      pin      virtual
s  4 KB      -      1628.93    14.7    1291.47  1465.34
m  64 KB     -      1346.44      0      467.38  1346.44
L  16 MB     5       48.0        0      80.0    48.0

Domain affinity      free      used      total      lcpus
      0      14131.05  1475.13  15606.18    0 1 2 3
      1      14589.65  1538.35  16128.00    4 5 6 7
```

In this example taken on a dedicated LPAR partition, we added the domain affinity metrics. The 31744 MB of memory are split into 2 memory affinity domain:

- The domain 0 contains 15606.18 MB of memory with 1475.13 MB used, and 14131.05 MB free.
- The domain 1 contains 16128 MB of memory with 1538.35 MB used and 14589.65 MB free.

- To display detailed affinity domain information, enter:

```
# svmon -G -O unit=MB,pgsz=on,affinity=detail
```

```
Unit: MB
```

```
-----
      size      inuse      free      pin      virtual  available
memory  31744.00  3055.70  28688.30  1838.91  2860.11  27910.99
pg space  512.00      14.7

      work      pers      clnt      other
pin      833.96      0         0         924.95
in use   2860.11      0        163.58

PageSize PoolSize      inuse      pgsp      pin      virtual
s  4 KB      -      1629.26    14.7    1291.47  1465.68
  Domain affinity      used
    0      129735
    1      44909
m  64 KB     -      1346.44      0      467.44  1346.44
  Domain affinity      used
    0      12432
    1      8512
L  16 MB     5       48.0        0      80.0    48.0
  Domain affinity      used
    0      4096
    1      8192

Domain affinity      free      used      total      lcpus
      0      14131.05  1475.13  15606.18    0 1 2 3
      1      14589.65  1538.35  16128.00    4 5 6 7
```

In this example, we can see that the breakdown by affinity domain is also shown in the per-page size report. This option takes some time to execute.

- On a shared partition, attempting to display affinity domain information, results in:

```
# svmon -G -O unit=MB,pgsz=on,affinity=on
```

```
Unit: MB
```

```
-----
      size      inuse      free      pin      virtual  available
memory  4096.00    811.59   3284.41   421.71   715.08   3248.66
```

```

pg space      512.00      6.23

           work      pers      clnt      other
pin          284.02      0         0         137.68
in use      715.08      0         96.5

PageSize  PoolSize      inuse      pgsp      pin      virtual
s   4 KB      -      506.78      6.23      288.77      410.27
m   64 KB      -      304.81      0         132.94      304.81

```

```

Domain affinity      free      used      total      lcpus
*** not supported in shared pools ***

```

Memory affinity domains only have meaning for dedicated partitions.

- To display the one line global report, enter:

```

# svmon -O summary=longreal
Unit: page

```

```

-----
Memory
-----
      Size      Inuse      Free      Pin      Virtual Available      Pgspace
262144  187219  74925  82515  149067  101251  131072

```

The metrics reported here are identical to the metrics in the basic format. There is a memory size of 262144 frames with 187219 frames inuse and 74925 remaining frames. 149067 pages are allocated in the virtual memory and 101251 frames are available.

- To display global memory statistics in MB units at interval, enter:

```

# svmon -G -O unit=MB,summary=shortreal -i 60 5
Unit: MB

```

```

-----
      Size      Inuse      Free      Pin      Virtual Available      Pgspace
1024.00  709.69  314.31  320.89  590.74  387.95  512.00
1024.00  711.55  312.39  320.94  592.60  386.02  512.00
1024.00  749.10  274.89  322.89  630.15  348.53  512.00
1024.00  728.08  295.93  324.57  609.11  369.57  512.00
1024.00  716.79  307.21  325.66  597.50  381.16  512.00

```

This example shows how to monitor the whole system by taking a memory snapshot every 60 seconds for 5 minutes.

- To display detailed memory expansion information (in a system with Active Memory Expansion enabled), enter:

```

# svmon -G -O summary=ame
Unit: page

```

```

-----
      size      inuse      free      pin      virtual available      mmode
memory  262144  152619  43061  73733  154779  41340  Ded-E
ucomprsd -      98216      -
comprsd -      54403      -
pg space 131072  1212

```

```

           work      pers      clnt      other
pin       66195      0         0         7538
in use   147831      0        4788
ucomprsd 93428
comprsd  54403

```

```

-----
True Memory: 131072

```

```

CurSz      %Cur      TgtSz      %Tgt      MaxSz      %Max      CRatio
ucomprsd   105004      80.11      37450      28.57      -         -
comprsd    26068      19.89      93622      71.43      45308     34.57     2.45

```

	txf	cxf	dx	dxm
AME	2.00	1.48	0.52	67641

- To display memory expansion information with true memory snapshot turned-off (in a system with Active Memory Expansion enabled), enter:

```
# svmon -G -O summary=ame,tmem=off
```

Unit: page

```
-----
memory      size      inuse      free      pin      virtual  available  mmode
ucmprsd     -         98216     -         73733    154779    41340     Ded-E
comprsd     -         54403     -         -        -        -        -
pg space    131072    1212      -         -        -        -        -

pin         work      pers      clnt      other
in use     147831    0         4788     7538
ucmprsd    93428
comprsd    54403
```

## User report

The User report displays the memory usage statistics for all specified login name or when no argument is specified for all users.

To print the user report, specify the **-U** flag. This report contains all the columns detailed in the **common summary metrics** as well as its own defined here:

**User** Indicates the user name

If processes owned by this user use pages of a size other than the base 4 KB page size, and the **-O pgsz=on** option is set, these statistics are followed by breakdown statistics for each page size. The metrics reported in this per-page size summary are reported in the page size unit by default.

### Note:

- If you specify the **-@** flag without an argument, these statistics will be followed by the users assignments to WPARs. This information is shown with an additional WPAR column displaying the WPAR name where the user was found.
- If you specify the **-O activeusers=on** option, users which do not use memory (Inuse memory is 0 page) are not shown in the report.

## Examples

1. To display per user memory consumption statistics, enter:

```
# svmon -U
```

Unit: page

```
-----
User          Inuse      Pin      Pgps  Virtual
root          56007     16070    0     54032
daemon       14864     7093     0     14848
guest        14705     7087     0     14632
bin           0         0        0         0
sys           0         0        0         0
adm           0         0        0         0
uucp         0         0        0         0
nobody       0         0        0         0
```

This command gives a summary of all the users using memory on the system. This report uses the default sorting key: the Inuse column. Since no **-O** option was specified, the default unit (page) is used. Each page is 4 KB.

The Inuse column, which is the total number of pages in real memory from segments that are used by all the processes of the *root* user, shows 56007 pages. The Pin column, which is the total number of pages pinned from segments that are used by all the processes of the *root* user, shows 16070 pages. The Pgsz column, which is the total number of paging-space pages that are used by all the processes of the *root* user, shows 0 pages. The Virtual column (total number of pages in the process virtual space) shows 54032 pages for the *root* user.

- To display per WPAR per active user memory consumption statistics, enter:

```
# svmon -U -O summary=basic,activeusers=on -@ ALL
Unit: auto

#####
##### WPAR : Global
#####
=====
User          Inuse      Pin       Pgsz  Virtual
root         155.49M   49.0M     0K    149.99M
daemon       69.0M     34.8M     0K     68.9M

#####
##### WPAR : wp0
#####
=====
User          Inuse      Pin       Pgsz  Virtual
root         100.20M   35.4M     0K     96.4M

#####
##### WPAR : wp1
#####
=====
User          Inuse      Pin       Pgsz  Virtual
root         100.20M   35.4M     0K     96.4M

#####
##### WPAR : wp2
#####
=====
User          Inuse      Pin       Pgsz  Virtual
root         100.14M   35.4M     0K     96.3M
```

In this case, we run in each WPAR context and we want some details about every users in all the WPARS running on the system. Since there are users that are not active, we want to keep only the active user by adding the **-O activeusers=on** option on the command line. Each WPAR has a root user, which in this example consumes the same amount of memory since each one runs the exact same list of processes. The root user of the Global WPAR uses more memory since more processes are running in the Global than in a WPAR.

## Command report

The Command report displays the memory usage statistics for the specified command names. To print the command report, specify the **-C** flag.

This report contains all the columns detailed in the common summary metrics as well as its own defined here:

### Command

Indicates the command name.

If processes running this command use pages of size other than the base 4KB page size, and the **-O pgsz=on** option is set, these statistics are followed by breakdown statistics for each page size. The metrics reported in this per-page size summary are reported in the page size unit by default.

### Examples:

1. To display memory statistics about the `yes` command, with breakdown by process and categorized detailed statistics by segment, enter:

```
# svmon -C yes -O summary=basic,pidlist=on,segment=category,process=on
Unit: page
=====
Command                               Inuse    Pin    Pgps  Virtual
yes                                     14405   5492    0    14404
-----
  Pid Command                          Inuse    Pin    Pgps  Virtual
  217132 yes                            14405   5492    0    14404
  397448 yes                            14405   5492    0    14404
  372980 yes                            14405   5492    0    14404
-----
SYSTEM segments                        Inuse    Pin    Pgps  Virtual
                                         6336   5488    0    6336
-----
  Vsid   Esid Type Description                PSize  Inuse  Pin Pgps Virtual
  2002   0  work kernel segment                    m     396  343  0    396
-----
EXCLUSIVE segments                    Inuse    Pin    Pgps  Virtual
                                         37      4      0     36
-----
  Vsid   Esid Type Description                PSize  Inuse  Pin Pgps Virtual
  711    2  work process private                    sm     19   4  0    19
  126a3  f  work shared library data                sm     17   0  0    17
  1b70a  1  clnt code,/dev/hd2:338                  s      1   0  -    -
-----
SHARED segments                       Inuse    Pin    Pgps  Virtual
                                         8032    0      0    8032
-----
  Vsid   Esid Type Description                PSize  Inuse  Pin Pgps Virtual
  502d   d  work shared library text                m     502   0  0    502
         Shared library text segment
```

In this example, we are looking at the `yes` command. The report is divided in several sub-reports. The summary line for the command displays the `Inuse` memory, the `Pin` pages in memory, the paging space and virtual pages used by the command. The `-O process=on` option adds the process section, where we have the list of the processes for this command.

2. To display memory statistics about the `yes` command, with breakdown by process and statistics by segment including file names, enter:

```
# svmon -C yes -O summary=basic,segment=on,pidlist=on,filename=on
Unit: page
=====
Command                               Inuse    Pin    Pgps  Virtual
yes                                     14405   5492    0    14404
-----
  Vsid   Esid Type Description                PSize  Inuse  Pin Pgps Virtual
  502d   d  work shared library text                m     502   0  0    502
         Shared library text segment
  2002   0  work kernel segment                    m     396  343  0    396
         System segment
  13722  2  work process private                    sm     19   4  0    19
         pid(s)=397566
  1a72b  f  work shared library data                sm     17   0  0    17
         pid(s)=397566
  1b70a  1  clnt code,/dev/hd2:338                  s      1   0  -    -
         /usr/bin/yes
         pid(s)=397566, 295038, 217212
```

This report displays for each segment its list of pids when the segment is in a process address space. It also displays the filename of all client and persistent segments.

- To display memory statistics about the *init* command, with breakdown by process, enter:

```
# svmon -@ -C init -O cmdline=on,segment=off,process=on
# svmon -@ -C init -O cmdline=on,segment=off,process=on
Command line : svmon -@ -C init -O cmdline=on,segment=off,process=on
Unit: page
=====
Command                               Inuse    Pin    Pgps  Virtual
init                                   18484    8900    0     18469
-----
  Pid Command                          Inuse    Pin    Pgps  Virtual
  1  init                               18494    8900    0     18477
    WPAR=Global
159976  init                             18484    8900    0     18469
    WPAR=wp1
233722  init                             18484    8900    0     18469
    WPAR=wp2
180562  init                             18484    8900    0     18469
    WPAR=wp0
-----
```

In a WPAR context, the **-@** flag combined with the **-O process=on** flag, adds WPAR information in the report. This example shows which *init* process belongs to which WPAR.

## Process report

The process report displays the memory usage statistics for all or the specified process names. To print the process report, specify the **-P** flag.

This report contains all the columns detailed in the **common summary metrics** as well as its own defined here:

**Pid** Indicates the process ID.

**Command**  
Indicates the command the process is running.

If processes use pages of size other than the base 4KB page size, and the **-O pgsz=on** option is set, these statistics are followed by breakdown statistics for each page size. The metrics reported in this per-page size summary are reported in the page size unit by default.

After process information is displayed, **svmon** displays information about all the segments that the process used. Information about segments are described in the paragraph **Segment Report**.

### Note:

- If you specify the **-@** flag, the **svmon** command displays two additional lines that show the virtual pid and the WPAR name of the process. If the virtual pid is not valid, a dash sign (-) is displayed.
- The **-O affinity** flag supported by the **-P** option, gives details on domain affinity for the process when set to **on** and for each of the segments when set to **detail**. Note that the Memory affinity information is not available for the shared partitions.

### Examples:

- To display the top 10 list of processes in terms of real memory usage in KB unit, enter:

```
# svmon -P -O unit=KB,summary=basic,sortentity=inuse -t 10
Unit: KB
-----
  Pid Command                          Inuse    Pin    Pgps  Virtual
344254  java                               119792    22104    0     102336
-----
```

209034	xmwl	68612	21968	0	68256
262298	IBM.CSMAgentR	60852	22032	0	60172
270482	rmcd	60844	21996	0	60172
336038	IBM.ServiceRM	59588	22032	0	59344
225432	IBM.DRMd	59408	22040	0	59284
204900	sendmail	59240	21968	0	58532
266378	rpc.statd	59000	21980	0	58936
168062	snmpdv3ne	58700	21968	0	58508
131200	errdemon	58496	21968	0	58108

This example gives the top 10 processes consuming the most real memory. The report is sorted by the inuse count, 119792 KB for the **java** process, 68612 KB for the **xmwl** daemon and so on. The other metrics are: KB pinned in memory, KB of paging space and virtual memory.

- To display information about all the non empty segments of a process, enter:

```
# svmon -P 221326 -O commandline=on,segment=on,filterprop=notempty
Command line : svmon -P 221326 -O commandline=on,segment=on,filterprop=notempty
Unit: page
```

Pid	Command	Inuse	Pin	Pgsp	Virtual
221326	java	20619	6326	9612	27584

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
502d	d	work	text or shared-lib code seg	m	585	0	1	585
0	0	work	kernel segment	m	443	393	4	444
14345	3	work	working storage	sm	2877	0	7865	9064
15364	e	work	shared memory segment	sm	1082	0	1473	1641
1b36a	f	work	working storage	sm	105	0	106	238
17386	-	work		s	100	34	64	146
1a38b	2	work	process private	sm	7	4	24	31

The detailed section displays information about each non empty segment used by process 221326. This includes the *virtual*, *Vsid*, and effective, *Esid*, segment identifiers. The type of the segment is also displayed along with its description that consists of a textual description of the segment, including the volume name and i-node of the file for persistent segments.

The report also details the size of the pages the segment is backed by (Psize column), where **s** denotes 4 KB pages and **L** denotes 16 MB pages, and **sm** a multi size page (small and medium page in this case) the number of pages in memory (Inuse column), the number of pinned pages (Pin column), the number of pages used in the paging space (Pgsp column), and the number of virtual pages (Virtual column).

- To display information about all the non empty segments used by a process, including the corresponding shared memory ids and affinity domain data, enter:

```
# svmon -P 221326 -O commandline=on,segment=on,affinity=on,shmid=on,filterprop=notempty
Command line : svmon -P 221326 -O commandline=on,segment=on,affinity=on,shmid=on,filterprop=notempty
Unit: page
```

Pid	Command	Inuse	Pin	Pgsp	Virtual
221326	java	20619	6326	9612	27584
			Domain affinity	Npages	
			0	29345	
			1	11356	

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
502d	d	work	text or shared-lib code seg	m	585	0	1	585
			Domain affinity	Nbpages				
			0	4800				
			1	4560				
0	0	work	kernel segment	m	443	393	4	444
			Domain affinity	Nbpages				
			0	5744				

14345	3	work working storage	1	1344	sm	2877	0	7865	9064
		Domain affinity		Nbpages					
			0	1518					
			1	1359					
15364	e	work shared memory segment			sm	1082	0	1473	1641
		shmId:3							
		Domain affinity		Nbpages					
1b36a	f	work working storage			sm	105	0	106	238
		Domain affinity		Nbpages					
			0	48					
			1	57					
17386	-	work			s	100	34	64	146
		Domain affinity		Nbpages					
			0	5744					
			1	1344					
1a38b	2	work process private			sm	7	4	24	31
		Domain affinity		Nbpages					
			0	3					
			1	4					

The detailed section displays the list of all segments used by the process 221326. In this case, the **-O affinity=detail** option adds for each VsId, the Domain affinity breakdown. The VsId 15364 also shows the shared memory id (shmId: 3 in this case). This information can be matched with the results given by the **ipcs** command.

- To display memory statistics in the legacy format which includes a breakdown by segments, enter:

```
$ svmon -P 209034 -O segment=on
```

Unit: page

```
-----
```

Pid	Command	Inuse	Pin	Pgsp	Virtual
209034	xmwlM	15978	5492	0	15929

VsId	EsId	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
502d	d	work shared	library text	m	495	0	0	495
2002	0	work kernel	segment	m	396	343	0	396
19288	c	work shared	memory segment	sm	1477	0	0	1477
b27a	f	work shared	library data	sm	106	0	0	106
d27c	2	work process	private	sm	90	4	0	90
1b24a	-	cInt	/dev/hd4:15493	s	22	0	-	-
1f24e	1	cInt	code,/dev/hd2:2521	s	18	0	-	-
8079	3	cInt	file mapped read write, /dev/hd3:5	s	8	0	-	-
a27b	-	cInt	/dev/hd2:123146	s	1	0	-	-

- To only display non empty segments and add per page size breakdown for segments with multiple page sizes, enter:

```
$ svmon -P 209034 -O segment=on,filterprop=notempty,mpss=on
```

Pid	Command	Inuse	Pin	Pgsp	Virtual
209034	xmwlM	15977	5492	0	15929

VsId	EsId	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
502d	d	work shared	library text	m	495	0	0	495
2002	0	work kernel	segment	m	396	343	0	396
19288	c	work shared	memory segment	s	5	0	0	1477
				m	92	0	0	0
b27a	f	work shared	library data	s	106	0	0	106
				m	0	0	0	0
d27c	2	work process	private	s	74	4	0	90
				m	1	0	0	0
1b24a	-	cInt	/dev/hd4:15493	s	21	0	-	-
1f24e	1	cInt	code,/dev/hd2:2521	s	18	0	-	-

```

8079      3 cInt file mapped read write,      s      8      0      -      -
          /dev/hd3:5
a27b      - cInt /dev/hd2:123146                  s      1      0      -      -

```

The 2 previous examples show the difference of the values reported in the **Inuse**, **Pin**, **Pgsp** and **Virtual** columns with MPSS pages. On this system **sm** pages are used by the process 209034, the metrics reported in the first report are in 4KB pages (in the smaller page size) while when the break down by page size is displayed with the **-O mpss=on** option, **s** pages are in 4KB page and **m** pages are in 64KB pages. So, for the segment 19288 this gives  $1477*4=5908\text{KB}$  in the first example, and  $5*4*1024 + 92*64*1024 = 5908\text{KB}$  in the second example. Dashes are put on the **Pgsp** and **Virtual** memory columns for the client segments because it is meaningless for this type of segment.

- To display detailed information about mapping segments for a process, in KB unit, enter:

```
$ svmon -P 340216 274676 -O segment=on,unit=KB,mapping=on
```

```
Unit: KB
```

```

-----
      Pid Command      Inuse   Pin   Pgsp  Virtual
274676 ptxtst mmap      57276  21968    0    57256

      Vsid   Esid Type Description      PSize  Inuse   Pin Pgsp  Virtual
502d      d work shared library text      m  31744    0    0  31744
2002      0 work kernel segment          m  25344  21952    0  25344
10661     2 work process private          sm   76    16    0    76
1a36b     f work shared library data      sm   52    0    0    52
14665     1 cInt code,/dev/hd2:825        s   12    0    -    -
11660 *   - work mmap paging             sm    8    0    0    8
          source=b2ba
d65c *   - work mmap paging             sm    8    0    0    8
          source=b2ba
13662 *   - work mmap paging             sm    8    0    0    8
          source=b2ba
4655 *   - work mmap paging             sm    8    0    0    8
          source=b2ba
b2ba     - cInt /dev/hd3:13              s    8    0    -    -
1350 *   - work mmap paging             sm    8    0    0    8
          source=b2ba
18329     3 mmap maps 5 source(s)         sm    0    0    -    -
          source(s)=b2ba/13662, b2ba/d65c, b2ba/4655, b2ba/11660
          source(s)=b2ba/1350
-----
      Pid Command      Inuse   Pin   Pgsp  Virtual
340216 ptxtst mmap      57240  21968    0    57216

      Vsid   Esid Type Description      PSize  Inuse   Pin Pgsp  Virtual
502d      d work shared library text      m  31744    0    0  31744
2002      0 work kernel segment          m  25344  21952    0  25344
f65e     2 work process private          sm   76    16    0    76
19668     f work shared library data      sm   52    0    0    52
1d66c     - cInt /dev/hd3:14              s   12    0    -    -
14665     1 cInt code,/dev/hd2:825        s   12    0    -    -
1c66d     3 mmap maps 3 source(s)         sm    0    0    -    -
          source(s)=1d66c, 1d66c, 1d66c

```

The mapping option is used in this case to also show mmapped segments which are not in the address space of the process. The process 274676 has created a shared memory file (client segment b2ba), this segment is used by mmap segments (11660, d65c, 13662, 4655, 1350) which are not in the address space of the process. The mmap segment of the process gives the list of all mmapped segment and their associated source (b2ba/13662, ...).

The process 340216 has created a private memory file, no extra mmap segments are displayed since all segments which are using this resource are private to the process and are already so shown by default.

## Workload management class report

To print the class report, specify the **-W** flag.

This report contains all the columns detailed in the **common summary metrics** as well as its own defined here:

### Class or Superclass

Indicates the class or superclass name.

The **-O subclass=on** option can be added to display the list of subclasses.

### Examples:

1. To display memory statistics about all WLM classes in the system, enter:

```
# svmon -W -O unit=page,commandline=on,timestamp=on
Command line : svmon -W -O unit=page,commandline=on,timestamp=on
Unit: page                                         Timestamp: 10:41:20
=====
Superclass           Inuse      Pin      Pgps  Virtual
System               121231    94597    19831 135505
Unclassified         27020     8576     67     8659
Default              17691     12       1641  16491
Shared               15871     0         0     13584
Unmanaged            0         0         0         0
```

In this example, all the WLM classes of the system are reported. Since no sort option was specified, the Inuse metric (real memory usage) is the sorting key. The class System uses 121231 pages in real memory. 94597 frames are pinned. The number of pages reserved or used in paging space is 19831. The number of pages allocated in the virtual space is 135505.

2. To display memory statistics about all WLM classes and subclasses in the system, enter:

```
# svmon -W -O subclass=on -O unit=page,commandline=on,timestamp=on
Command line : svmon -W -O subclass=on -O unit=page,commandline=on,timestamp=on
Unit: page                                         Timestamp: 10:43:18
=====
Superclass           Inuse      Pin      Pgps  Virtual
System               120928    94609    19831 135202
System.Default       120928    94609    19831 135202
System.Shared        0         0         0         0
Unclassified         27020     8576     67     8659
Default              17691     12       1641  16491
Default.Default      17691     12       1641  16491
Default.Shared       0         0         0         0
Shared               15871     0         0     13584
Shared.Default       15871     0         0     13584
Shared.Shared        0         0         0         0
Unmanaged            0         0         0         0
```

In this example, all the WLM classes and sub-classes of the system are reported. Since the no sort option was specified, the Inuse metric (real memory usage) is the sorting key. The class System uses 120928 pages in real memory, they are split into 120928 pages in the System Default sub-class, and no pages in the Shared sub-class.

## Workload management tier report

To print the tier report, specify the **-T** flag.

This report contains all the columns detailed in the **common summary metrics** as well as its own defined here:

**Tier** Indicates the tier number

## Superclass

The optional column heading indicates the superclass name when tier applies to a superclass (when the **-a** flag is used).

The **-O subclass=on** option can be added to display the list of subclasses. The **-a <superclassname>** option allows reporting only the details of a given super class.

## Examples:

1. To display memory statistics about all WLM tiers and superclasses in the system, enter:

```
# svmon -T -O unit=page
Unit: page
=====
Tier                Inuse      Pin      Pgps  Virtual
  0                137187    61577    2282   110589
=====
Superclass          Inuse      Pin      Pgps  Virtual
System              81655     61181    2282   81570
Unclassified        26797      384       0     2107
Default             16863      12        0    15040
Shared              11872       0         0    11872
Unmanaged            0           0         0       0
  1                 9886      352       0     8700
=====
Superclass          Inuse      Pin      Pgps  Virtual
myclass             9886      352       0     8700
```

All the superclasses of all the defined tiers are reported. Each Tier has a summary header with the *Inuse*, *Pin*, *Paging space*, and *Virtual* memory, and then the list of all its classes.

2. To display memory statistics about all WLM tiers, superclasses and classes in the system, enter:

```
# svmon -T -O subclass=on -O unit=page,commandline=on,timestamp=on
Command line : svmon -T -O subclass=on -O unit=page,commandline=on,timestamp=on
Unit: page                                     Timestamp: 10:44:31
=====
Tier                Inuse      Pin      Pgps  Virtual
  0                181824    103185   21539  174250
=====
Superclass          Inuse      Pin      Pgps  Virtual
System              121242    94597   19831  135516
=====
Class               Inuse      Pin      Pgps  Virtual
System.Default      121242    94597   19831  135516
System.Shared        0           0         0       0
Unclassified        27020     8576     67     8659
=====
Superclass          Inuse      Pin      Pgps  Virtual
Default             17691      12     1641   16491
=====
Class               Inuse      Pin      Pgps  Virtual
Default.Default     17691      12     1641   16491
Default.Shared       0           0         0       0
=====
Superclass          Inuse      Pin      Pgps  Virtual
Shared              15871       0         0    13584
=====
Class               Inuse      Pin      Pgps  Virtual
Shared.Default      15871       0         0    13584
Shared.Shared        0           0         0       0
Unmanaged            0           0         0       0
```

Details at sub-class level can also be displayed for each class of each Tier.

- To display memory statistics about a particular WLM superclass in a tier, with segment and per page size details, enter:

```
# svmon -T 0 -a myclass2 -O segment=on,pgsz=on,pidlist=on
Unit: page
=====
Tier Superclass                Inuse    Pin    Pgsz  Virtual
  0 myclass2                    36      4      0     36

    PageSize                Inuse    Pin    Pgsz  Virtual
    s   4 KB                 36      4      0     36
    m  64 KB                 0       0      0      0
=====
Class                Inuse    Pin    Pgsz  Virtual
myclass2.Default    36      4      0     36

    Vsid    Esid Type Description                PSize Inuse  Pin Pgsz Virtual
    711     2  work process private                sm   19   4  0    19
           pid(s)=372980
    126a3   f  work shared library data                sm   17   0  0    17
           pid(s)=372980
=====
Class                Inuse    Pin    Pgsz  Virtual
myclass2.Shared      0       0      0      0
```

The statistics of all the subclasses, in the tier 0, of the superclass *myclass2* are reported. The distribution between the different page sizes is displayed by the **-O pgsz=on** option. Then, as **-O segment=on** is specified, the subclass statistics are followed by its segments statistics. Finally, as **-O pidlist=on** is specified for each segment, the list of process which uses it, is displayed.

## Segment report

To print the segment report, specify the **-S** flag.

This report contains all the columns detailed in the **common summary metrics** as well as its own defined here:

- Vsid** Indicates the virtual segment ID. Identifies a unique segment in the VMM.
- Esid** Indicates the effective segment ID. The **Esid** is only valid when the segment belongs to only one process (i.e: only one address space). When provided, it indicates how the segment is used by the process. If the **Vsid** segment is mapped by several processes (i.e: several address spaces), then this field contains - (hyphen). The exact Esid values can be obtained through the **-P** flag applied on each of the process identifiers using the segment. A - (hyphen) also displays for segments used to manage open files or multi-threaded structures because these segments are not part of the user address space of the process.
- Type** Identifies the type of the segment:
  - *pers* indicates a persistent segment
  - *work* indicates a working segment
  - *clnt* indicates a client segment
  - *mmap* indicates a mapped segment
  - *rmap* indicates a real memory mapping segment

### Description

Gives a textual description of the segment. The content of this column depends on the segment type and usage.

If the segment is a persistent segment and is not associated with a log, then the device name and i-node number of the associated file are displayed, separated by a colon. The device name and

i-node can be translated into a file name with the **ncheck** command or by using the **-O filename=on** flag. If the segment is the primary segment of a large file, then the words **large file** are prepended to the description.

**PSize** Indicates the size of the pages inside the segment.

**Note:**

- Mapping device name and inode number to file names can be a lengthy operation for deeply nested file systems. Because of that, the **-O filename=on** option should be used with caution.
- If the segment is a persistent segment and is associated with a log, then the string **log** displays. If the segment is a working segment, then the **svmon** command attempts to determine the role of the segment. For instance, special working segments such as the kernel and shared library are recognized by the **svmon** command. If the segment is the private data segment for a process, then **private** prints out. If the segment is the code segment for a process, and the segment report prints out in response to the **-P** flag, then the string **code** is prepended to the description.
- If the segment is mapped by several processes and used in different ways (that is, a process private segment mapped as shared memory by another process), then the description is empty. The exact description can be obtained through **-P** flag applied on each process identifier using the segment.
- If a segment description is too large to fit in the description space, then the description is truncated. If you need to enlarge the output you can use the **-O format** flag. When set to **-O format=160**, the report is displayed in 160 columns, which means more room for the description field. When set to **-O format=nolimit**, the description will be fully printed even if it brakes the column alignment.

**Restriction:**

- Segment reports can only be generated for primary segments.

**Examples:**

1. To display information about a list of segments including the list of processes using them, enter:

```
# svmon -S 11c02 3393e5 2c10da 2c4158 1b1a34 -O pidlist=on
Unit: page
```

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
11c02	-	work	kernel heap System segment	s	65536	0	0	65536
3393e5	3	work	working storage pid(s)=168138	s	10143	0	0	10143
2c4158	-	work	System segment	s	5632	5632	0	5632
1b1a34	-	work	Unattached segment	L	2	2	0	2
2c10da	-	clnt	/dev/hd2:4183 Unused segment	s	2110	0	-	-

Information about each segment in the list is displayed. The **Esid** column contains information only when **-O pidlist=on** is specified because the **Esid** has a meaning only in the address space of a process. In this case, since the segment **3393e5** belongs to the process **168138**, the **Esid** is reported, in all other cases no information is displayed. The segments **11c02** is the kernel pinned heap. The segment **2c4158** has no special characteristics. The segment **2c10da** is relative to a file whose device is **/dev/hd2** and whose inode number is **4183**. The **Paging space** and **Virtual** fields of the segment **2c10da** are not meaningful (because it is a client segment). The segment **1b1a34** is a 16 MB page segment which contains 2 pages of 16 MB (equivalent to 8192 pages of 4KB).

2. To display information about all unattached segments in the system, enter:

```
# svmon -S -O filtercat=unattached
```

Unit: page

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
1b1a34	-	work		L	2	2	0	2
2618ce	-	work		s	1	0	0	1

In this example, the report contains all the segments coming from processes which have allocated shared memory areas, and which have exited without freeing these memory areas.

3. To display the top 10 (in real memory consumption or sorted by the inuse field) text segments with their corresponding file name, enter:

```
# svmon -S -t 10 -O unit=auto,filterprop=text,filename=on
```

Unit: auto

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
1a0cb	-	clnt	/dev/hd2:4140	s	7.62M	0K	-	-
			/usr/ccs/lib/libc.a					
a37b	-	clnt	/dev/hd2:65692	s	4.34M	0K	-	-
			/usr/java5/jre/bin/libj9jit23.so					
1150	-	clnt	/dev/hd2:16394	s	3.77M	0K	-	-
			/usr/lpp/xlC/lib/aix61/libC.a					
16667	-	clnt	/dev/hd2:2716	s	3.10M	0K	-	-
			/usr/bin/ptxtstoverflow_heap					
14285	-	clnt	/dev/hd2:131333	s	2.91M	0K	-	-
			/opt/rsct/lib/libct_rmf.a					
8159	-	clnt	/dev/hd2:9535	s	2.52M	0K	-	-
			/usr/lib/drivers/nfs.ext					
1b2ca	-	clnt	/dev/hd2:65747	s	2.27M	0K	-	-
			/usr/java5/jre/lib/core.jar					
f23e	-	clnt	/dev/hd2:115081	s	1.88M	0K	-	-
			/usr/opt/perl5/lib/5.8.2/aix-thread-multi/CORE/libperl.					
17026	-	clnt	/dev/hd2:8470	s	1.79M	0K	-	-
			/usr/lib/boot/unix_64					
15104	-	clnt	/dev/hd2:2258	s	1.41M	0K	-	-
			/usr/lib/libdns_nonsecure.a					

The **-O filename=on** option allows in this case to display the filename of each client text segment. The amount of memory used by every segment is put with the unit identifier because of the **-O unit=auto** option. The segment 1a0cb holds 7.62MB of real memory and no pinned memory. The paging space and virtual memory are meaningless for client segments. The Description of the segment f23e is truncated because the default format of the report is 80 columns. The **-O format=180** or **-O format=nolimit** could be used to display the full path of this file.

## Named Shared Libraries

When the Named Shared Libraries (NSLA) areas are used, the segment description contains the name of the area.

When a WPAR was used during a checkpoint and restarted, some shared library areas might be local to the WPAR. The name of the WPAR is printed after the name of the area. Note that using Named Shared Library Areas in a WPAR does not mean that the area is for this WPAR only. For more information, see the documentation on NSLA.

In all other examples, the area is system-wide; therefore, the WPAR name is omitted.

The following is a list of possible examples:

- *myarea* means a system-wide area *myarea* is defined on the system.
- *@myarea* means an *unnamed* area is defined on the WPAR *mywpar*.
- *myarea@mywpar* means an area named *myarea* is defined on the WPAR *mywpar*.

## Examples:

System-wide Named Shared Library area:

```
# svmon -P 381050 -O pidlist=on,pgsz=on,segment=on,summary=basic or
```

```
# svmon -P 381050 -O pidlist=on,pgsz=on
```

Unit: page

```
-----
```

Pid	Command	Inuse	Pin	Pgsp	Virtual
381050	yes	11309	9956	0	11308

PageSize	Inuse	Pin	Pgsp	Virtual
s 4 KB	221	4	0	220
m 64 KB	693	622	0	693

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
0	0	work	kernel segment	m	693	622	0	693
			System segment					
60006	d	work	shared library text	s	185	0	0	185
			myshlarea					
			Shared library text segment					
91a08	2	work	process private	s	18	4	0	18
			pid(s)=381050					
21a23	f	work	shared library data	s	17	0	0	17
			pid(s)=381050					
11920	1	clnt	code,/dev/hd2:338	s	1	0	-	-
			pid(s)=381050					

## Detailed report

The detailed report (-D) displays information about the pages owned by a segment and, on-demand, it can display the frames these pages are mapped to. To print the detailed report, specify the **-D** flag.

Several fields are presented before the listing of the pages used:

**Segid** The segment identifier.

**Type** The type of the segment.

**PSize** The type of the segment.

### Address Range

Ranges in which frames are used by this segment.

Ranges in which frames are used by this segment.

### Size of paging space allocation

### Virtual

Number of pages used by this segment.

**Inuse** Number of frames used by this segment.

### Column headings in a detailed report:

**Page** Relative page number to the virtual space. This page number can be higher than the number of frames in a segment (65535) if the virtual space is larger than a single segment (large file).

**Frame** Frame number in the real memory. Since frames are always considered 4KB in size regardless of the page size of the segment, for any page size larger than 4 KB, a range of frames instead of a single frame is associated to one page. This range is noted as XXXXXXXX..YYYYYYY, which means that the continuous range of frames between ID XXXXXXXX and YYYYYYY is used for the given page.

**Pin** Indicates if the frame is pinned or not.

**Ref** Indicates if the frame has been referenced by a process.

**Mod** Indicates if the frame has been modified by a process.

**ExtSegid**

Extended segment identifier. This field is only set when the page number is higher than the maximum number of frames in a segment.

**ExtPage**

Extended page number. This field is only set when the page number is higher than the maximum number of frames in a segment and indicates the page number within the extended segment.

**Note:**

- The `-@` flag has no effect on the `-D` option.
- This option only supports the additional `-O frame` option, which shows additional frame level details.
- The format used by this report is on 160 columns.

**Examples:**

```
#svmon -D b9015
Segid: b9015
Type: client
PSize: s (4 KB)
Address Range: 0..9 : 122070..122070
```

Page	Psize	Frame	Pin	Ref	Mod	ExtSegid	ExtPage
0	s	74870	N	N	N	-	-
1	s	11269	N	N	N	-	-
2	s	11270	N	N	N	-	-
3	s	11271	N	N	N	-	-
4	s	11272	N	N	N	-	-
5	s	11273	N	N	N	-	-
6	s	11274	N	N	N	-	-
7	s	11275	N	N	N	-	-
8	s	986106	N	N	N	-	-
9	s	4093	N	N	N	-	-
122070	s	78191	N	N	N	208831	dcd6

The segment `b9015` is a client segment with 11 pages. None of them are pinned. The page `122070` is physically the page `dcd6` in the extended segment `208831`.

```
# svmon -D 6902f -O frame=on
Segid: 6902f
Type: working
PSize: s (4 KB)
Address Range: 0..179 : 65309..65535
Size of page space allocation: 0 pages ( 0.0 MB)
Virtual: 99 frames ( 0.4 MB)
Inuse: 99 frames ( 0.4 MB)
```

Page	Psize	Frame	Pin	Ref	Mod	ExtSegid	ExtPage	Pincount	State	Swbits
65483	s	72235	Y	N	N	-	-	1/0	Hidden	88000000
65353	s	4091	Y	N	N	-	-	1/0	Hidden	88000000
65352	s	4090	Y	N	N	-	-	1/0	Hidden	88000000
65351	s	4089	Y	N	N	-	-	1/0	Hidden	88000000
65350	s	1010007	N	N	N	-	-	0/0	In-Use	88020000
65349	s	1011282	N	N	N	-	-	0/0	In-Use	88020000
65354	s	992249	N	N	N	-	-	0/0	In-Use	88020000
65494	s	1011078	N	N	N	-	-	0/0	In-Use	88020000
0	s	12282	N	N	N	-	-	0/0	In-Use	88820000
1	s	12281	N	N	N	-	-	0/0	In-Use	88820000
2	s	64632	N	N	N	-	-	0/0	In-Use	88a20000

3	s	64685	N	N	N	-	-	0/0	In-Use 88a20000
4	s	64630	N	N	N	-	-	0/0	In-Use 88a20000
5	s	64633	N	N	N	-	-	0/0	In-Use 88820000

The frame 72235 is pinned, not referenced and not modified, it is in the Hidden state, it does not pertain to an extended segment nor to a large page segment.

## XML report

To print the XML report, specify the **-X** option.

By default the report is printed to standard output. The **-o filename** flag allows you to redirect the report to a file. When the **-O affinity** option is used, affinity information is added to the report.

**Note:** The **-O affinity=detail** option can take a long time to compute.

The extension of XML reports is **.svm**. To prevent a report overwrite, the option **-O overwrite=off** option can be specified (by default this option is set to **on**).

This XML file uses a XML Schema Definition (XSD) which can be found in the file: **/usr/lib/perf/svmon\_measurement.xsd**. This schema is self-documented and thus can be used by anyone to build custom application using the XML data provided in these reports.

The data provided in this file is a snapshot view of the whole machine. It contains enough data to build an equivalent of the **-G, -P, -S, -W, -U, and -C** options.

---

## Remote Statistics Interface API Overview

The Remote Statistics Interface (RSI) is an application programming interface (API) that is available for developing programs that access the statistics available from one or more **xmtopas** daemons.

Learn the procedure to use the RSI Interface API through the sample programs. The sample programs, and others, are also provided in the machine-readable. The sample programs can be found in the **/usr/samples/perfmgr** directory.

Use the RSI Interface API to write programs that access one or more **xmtopas** daemons. It allows you to develop programs that print, post-process, or otherwise manipulate the raw statistics provided by the **xmtopas** daemons. Such programs are known as Data-Consumer programs. AIX Version 7.1 Technical Reference: Communications, Volume 2 must be installed to see the RSi subroutines

## Makefile

The include files are based on the define directives, which must be properly set. They are defined with the **-D** preprocessor flag.

- **\_AIX**<sup>®</sup> specifies the include files to generate code for AIX.
- **\_BSD** required for proper BSD compatibility.

An example of a Makefile that helps to build a sample program follows:

```
LIBS = -L./ -lbsd -lspmi
CC = cc
CFLAGS = -D_BSD -DRSIv6 -D_AIX®
all:: RsiCons RsiCons1 chmon

RsiCons: RsiCons.c
    $(CC) -o RsiCons RsiCons.c $(CFLAGS) $(LIBS)

RsiCons1: RsiCons1.c
    $(CC) -o RsiCons1 RsiCons1.c $(CFLAGS) $(LIBS)
```

```
chmon: chmon.c $
      $(CC) -o chmon chmon.c $(CFLAGS) $(LIBS) -lcurses
```

If the system that is used to compile does not support ANSI function prototypes, include the `-D_NO_PROTO` flag.

## Remote Statistics Interface list of subroutines

The `xmperf` interface is used to view the graphical display of statistics on all the hosts in a network.

The Remote Statistics Interface (RSI) application programming interface (API) is used to create data-consumer programs that helps to access statistics of any host's `xmtopas` daemon.

The RSI interface consists of the following groups of subroutines.

### Initialization and Termination

Item	Descriptor
RSiInitx	Allocates or changes the table of RSI handles.
RSiOpenx	Initializes the RSI interface for a remote host.
RSiClosex	Terminates the RSI interface for a remote host and releases all memory allocated.
RSiInvitex	Invites data suppliers on the network to identify themselves and returns a table of data-supplier host names.

### Instantiation and Traversal of Context Hierarchy

Item	Descriptor
RSiInstantiatex	Creates (instantiates) all subcontexts of a context object.
RSiPathGetCxx	Searches the context hierarchy for a context that matches a context path name.
RSiFirstCxx	Returns the first subcontext of a context.
RSiNextCxx	Returns the next subcontext of a context.
RSiFirstStatx	Returns the first statistic of a context.
RSiNextStatx	Returns the next statistic of a context.

### Defining Sets of Statistics to Receive

Item	Descriptor
RSiAddSetHotx	Adds a single set of peer statistics to a hotset.
RSiCreateHotSetx	Creates an empty hotset.
RSiCreateStatSetx	Creates an empty statset.
RSiPathAddSetStatx	Adds a single statistic to a statset.
RSiDelSetHotx	Deletes a single set of peer statistics from a hotset.
RSiDelSetStatx	Deletes a single statistic from a statset.
RSiStatGetPathx	Finds the full path name of a statistic identified by an <code>SpmiStatVals</code> pointer.

### Starting, Changing, and Stopping Data Feeding

Item	Descriptor
RSiStartFeedx	Tells xmtopas to start sending data feeds for a statset.
RSiStartHotFeedx	Tells xmtopas to start sending hot feeds for a hotset.
RSiChangeFeedx	Tells xmtopas to change the time interval between sending data feeds for a statset.
RSiChangeHotFeedx	Tells xmtopas to change the time interval between sending hot feeds for a hotset.
RSiStopFeedx	Tells xmtopas to stop sending data feeds for a statset.
RSiStopHotFeedx	Tells xmtopas to stop sending hot feeds for a hotset.

## Receiving and Decoding Data Feed Packets

Item	Descriptor
RSiGetHotItemx	Returns the peer context name and data value for the first (next) SpmiHotItems element by extraction from data feed packet.
RSiMainLoopx	Allows an application to suspend execution and waits to be woken when data feeds arrive.
RSiGetValuex	Returns data value for a given SpmiStatVals pointer by extraction from data feed packet.
RSiGetRawValueX	Returns a pointer to a valid SpmiStatVals structure for a given SpmiStatVals pointer by extraction from data feed packet.

## RSI Interface Concepts and Terms

Learn about the structures and the commonalities of the library functions and important design concepts.

To start using the RSI interface API you must be aware of the format and use of the RSI interface data structures.

### RSI Interface data structures

The RSI interface is based upon control blocks (data structures) that describe the current view of the statistics on a remote host and the state of the interaction between a data consumer program and the remote host's **xmtopas** daemon.

The RSI interface supports the following data structures:

- RSI handle
- SpmiStatVals

### RSI handle

An RSI handle is a pointer to a data structure of type `RsiHandleStructx`. Prior to using any other RSI call, a data-consumer program must use the `RSiInit` subroutine to allocate a table of RSI handles. An RSI handle from the table is initialized when you open the logical connection to a host and that RSI handle must be specified as an argument on all subsequent subroutines to the same host. Only one of the internal fields of the RSI handle should be used by the data-consumer program, namely the pointer to received network packets, `pi`. Only in very special cases will you ever need to use this pointer, which is initialized by `RSiOpenx` and must never be modified by a data-consumer program. If your program changes any field in the RSI handle structure, results are highly unpredictable. The RSI handle is defined in `/usr/include/sys/Rsi.h`.

### SpmiStatVals

A single data value is represented by a structure defined in `/usr/include/sys/Spmidef.h` as struct `SpmiStatVals`. Be aware that none of the fields defined in the structure must be modified by application

programs. The two handles in the structure are symbolic references to contexts and statistics and should not be confused with pointers. The last three fields are updated whenever a data\_feed packet is received. These fields are as follows:

Item	Descriptor
val	The latest actual contents of the statistics data field.
val_change	The difference (delta value) between the latest actual contents of the statistics data field and the previous value observed.
error	An error code as defined by the enum Error in included in the /usr/include/sys/Spmidef.h file.

**Note:** The two value fields are defined as union Value, which means that the actual data fields may be long or float, depending on flags in the corresponding SpmiStat structure. The SpmiStat structure cannot be accessed directly from the StatVals structure (the pointer is not valid, as previously mentioned). Therefore, to determine the type of data in the val and val\_change fields, you must have saved the SpmiStat structure as returned by the **RSiPathAddSetStatx** subroutine. This is rather clumsy, so the RSiGetValuex subroutine does everything for you and you do not need to keep track of SpmiStat structures.

The SpmiStat structure is used to describe a statistic. It is defined in the /usr/include/sys/Spmidef.h file of type SpmiStat struct . If you ever need information from this data structure (apart from information that can be returned by the RSiStatGetPathx subroutine) be sure to save it as it is returned by the **RSiPathAddSetStatx** subroutine.

The RSiGetValuex subroutine provides another way of getting access to an SpmiStat structure but can only do so while a data feed packet is being processed.

The **xmtopas** daemon accepts the definition of sets of statistics that are to be extracted simultaneously and sent to the data-consumer program in a single data packet. The structure that describes such a set of statistics is defined in the /usr/include/sys/Spmidef.h file of type SpmiStatSet struct . As returned by the **RSiCreateStatSetx**, the SpmiStatSet pointer must be treated as a handle whose only purpose is to identify the correct set of statistics to several other subroutines.

When returned in a data feed packet, the SpmiStatSet structure holds the actual time the data feed packet was created (according to the remote host's clock) and the elapsed time since the latest previous data feed packet for the same SpmiStatSet was created.

SpmiHotSet structure represents another set of access structures that allow an application program to define an alternative way of extracting and processing metrics. They are used to extract data values for the most or least active statistics for a group of peer contexts. For example, it can be used to define that the program wants to receive information about the two highest loaded disks, optionally subject to the load exceeding a specified threshold.

When the SPMI receives a read request for an SpmiHotSet, the SPMI reads the latest value for all the peer sets of statistics in the hotset in one operation. This action reduces the system overhead caused by access of kernel structures and other system areas, and ensures that all data values for the peer sets of statistics within a hotset are read at the same time. The hotset may consist of one or many sets of peer statistics.

**SpmiHotVals** One SpmiHotVals structure is created for each set of peer statistics selected for the hotset. When the SPMI executes a request from the application program to read the data values for a hotset, all SpmiHotVals structures in the set are updated. The RSi application program can then traverse the list of SpmiHotVals structures by using the **RSiGetHotItemx** subroutine call.

The SpmiHotVals structure carries the data values from the SPMI to the application program. Its data carrying fields are:

<b>Item</b>	<b>Descriptor</b>
error	Returns a zero value if the SPMI's last attempt to read the data values for a set of peer statistics was successful. Otherwise, this field contains an error code as defined in the <code>sys/Spmidef.h</code> file.
avail_resp	Used to return the number of peer statistic data values that meet the selection criteria (threshold). The field <code>max_responses</code> determines the maximum number of entries actually returned.
count	Contains the number of elements returned in the array items. This number is the number of data values that met the selection criteria (threshold), capped at <code>max_responses</code> .
items	The array used to return count elements. This array is defined in the <code>SpmiHotItems</code> data structure. Each element in the <code>SpmiHotItems</code> array has the following fields: <ul style="list-style-type: none"> <li><b>name</b> The name of the peer context for which the values are returned.</li> <li><b>val</b> Returns the value of the counter or level field for the peer statistic. This field returns the statistic's value as maintained by the original supplier of the value. However, the <code>val</code> field is converted to an SPMI data format.</li> <li><b>val_change</b> Returns the difference between the previous reading of the counter and the current reading when the statistic contains counter data. When this value is divided by the elapsed time returned in the <code>SpmiHotSet</code> Structure, an event rate-per-time-unit can be calculated.</li> </ul>

## RSI Request-Response Interface

The RSI interface API has two distinctly different ways of operation.

The RSI request-response protocol that sends a single request to **xmtopas** daemon and waits for a response. A timeout occurs if no response has been received within a specified time limit and a single retry is attempted. If the retry also results in a timeout, the same is communicated to the caller by placing the `RSiTimeout` constant in the external integer `RSiErrno` field . If any other error occurred, the external integer field has some other non-zero value.

If neither a communication error nor a timeout error occurred, a packet is available in the receive buffer pointed to by the `pi` pointer in the RSI handle. The packet includes a status code that tells whether the subroutine was successful at the **xmtopas** daemon. You must check the status code in a packet if it matters what exactly it is because the `RSiBadStat` constant is placed in `RSiErrno` field to indicate to your program that a bad status code was received.

You can use the indication of error or success as defined for each subroutine to determine if the subroutine succeeded or you can test the external integer `RSiErrno`. If this field is `RSiOkay` the subroutine succeeded; otherwise it did not. The error codes returned in `RSiErrno` are defined in the `RSiErrorType` enum .

All the library functions use the request-response interface, except for `RSiMainLoop` (which uses a network driven interface) and `RSiInitx`, `RSiGetValuex`, and `RSiGetRawValuex` (that do not involve network traffic).

## RSI Network driven interface

The **xmquery** protocol defines three types of data packets that are sent from the data supplier of the **xmtopas** daemon without being solicited by a request packet.

The request packet types are the `still_alive`, the `data_feed`, and the `except_rec` packets. The `still_alive` packets are handled internally in the RSI interface and require no programming in the data-consumer program.

The `data_feed` packets are received asynchronously with any packets produced by the request-response type subroutines. If a `data_feed` packet is received when processing a request-response function, control is passed to a callback function, which must be named when the RSI handle is initialized with the **RSiOpenx** subroutine.

When the data-consumer program is not using the request-response functions, it still needs to be able to receive and process `data_feed` packets. This is done with the **RSiMainLoopx** function, which invokes the callback function whenever a packet is received.

Actually, the data feed callback function is invoked for all packets received that cannot be identified as a response to the latest request sent, except if such packets are of type `i_am_back`, `still_alive`, or `except_rec`. Note that this means that responses to “request-response” packets that arrive after a timeout is sent to the callback function. It is the responsibility of your callback function to test for the packet type received.

The `except_rec` packets are received asynchronously with any packets produced by the request-response type subroutines. If an `except_rec` packet is received when processing a request-response function, control is passed to a callback function, which must be named when the RSI handle is initialized with the **RSiOpenx** subroutine.

When the data-consumer program is not using the request-response functions, it still needs to be able to receive and process `except_rec` packets. This is done with the **RSiMainLoopx** function which invokes the callback function whenever a packet is received.

**Note:** The API discards `except_rec` messages from a remote host unless a callback function to process the message type was specified on the **RSiOpenx** subroutine call for that host.

## Resynchronizing

Network connections can go bad, hosts can go down, interfaces can be taken down and processes can stop functioning.

In the case of the **xmtopas** protocol, such situations usually result in one or more of the following:

- Missing packets
- Resynchronizing requests

### Missing packets

Responses to outstanding requests are not received, which generate a timeout. That's fairly easy to cope with because the data-consumer program has to handle other error return codes anyway. It also results in expected data feeds not being received. Your program may want to test for this happening. The proper way to handle this situation is to use the **RSiClosex** function to release all memory related to the dead host and to free the RSI handle. After this is done, the data-consumer program may attempt another **RSiOpenx** to the remote system or may simply exit.

### Resynchronizing requests

Whenever an **xmtopas** daemon hears from a given data-consumer program on a particular host for the first time, it responds with a packet of `i_am_back` type, effectively prompting the data-consumer program to resynchronize with the daemon. Also, when the daemon attempts to reconnect to data-consumer programs that it talked to when it was killed or died, it sends an `i_am_back` packet.

It is important that you understand how the **xmtopas** daemon handles “first time contacted.” It is based upon tables internal to the daemon. Those tables identify all the data-consumers that the daemon knows about. Be aware that a data-consumer program is known by the host name of the host where it executes suffixed by the IP port number used to talk to the daemon. Each data-consumer program running is identified uniquely as are multiple running copies of the same data-consumer program.

Whenever a data-consumer program exits orderly, it alerts the daemon that it intends to exit and the daemon removes it from the internal tables. If, however, the data-consumer program decides to not request data feeds from the daemon for some time, the daemon detects that the data consumer has lost interest and removes the data consumer from its tables as described in Life and Death of **xmtopas**. If the data-consumer program decides later that it wants to talk to the **xmtopas** daemon again, the daemon responds with an `i_am_back` packet.

The `i_am_back` packets are given special treatment by the RSI interface. Each time one is received, a resynchronizing callback function is invoked. This function must be defined on the **RSiOpenx** subroutine.

**Note:** All data-consumer programs can expect to have this callback invoked once during execution of the **RSiOpenx** subroutine because the remote **xmtopas** does not know the data consumer. This is usual and should not cause your program to panic. If the resynchronize callback is invoked twice during processing of the **RSiOpenx** function, the open failed and can be retried, if appropriate.

## Specifying port range for RSI communication

A random communication port is required between the **xmtopas** or **xmtopas** interface and the consumers. The `Rsi.hosts` configuration file is used to set the ports within a specified range.

To set the port range, complete these steps:

1. Locate the `Rsi.hosts` file in the `$HOME` or the `/etc/perf` directory. If the file does not exist in either of the directories, search the file in the `/usr/lpp/perfmggr` directory.
2. Specify the start and the end port in the acceptable range as mentioned in the `Rsi.hosts` file. If the `Rsi.hosts` file cannot be located in directories or the port range is specified incorrectly, the RSI communication uses random ports.

To specify the port range in the `Rsi.hosts` file, use the following command:

```
portrange <start_port> <end_port>
```

Example:

```
portrange 3001 3003
```

When the RSI communication starts, it uses 3001, 3002 or 3003 ports in the specified range. Only 3 RSI agents can listen to the ports and the subsequent RSI communication fails.

## A Simple Data-Consumer Program

The use of the application programming interface (API) is illustrated by creating a small data-consumer program to produce a continuous list of statistics from a host.

The first version accesses only CPU-related statistics. It assumes that you want to get your statistics from the local host unless you specify a host name on the command line. The program continues to display the statistics until it is killed. The source code for the sample program can be found in the `/usr/samples/perfmggr/RsiCons1.c` file.

## Initializing and terminating the program

The main function of the sample program uses the three subroutines as shown in the following code segment. The lines 12 through 15 use any command line argument to override the default host name obtained by the `uname` function. Then lines 17 through 28 initialize the RSI interface using the **RSiInitx** and **RSiOpenx** subroutines. The program exits if the initialization fails.

```
[01] extern char  RSiEMsg[];
[02] extern int   RSiErrno;
[03] char  host[64], apath[256], head1[24][10], head2[24][10];
[04] char  *nptr, **navn = &nptr, *dptr, **desc = &dptr;
[05] struct utsname  uname_struct;
[07] RsiHandlex  rsh;
[08] struct SpmiStatVals *svp[24];
```

```

[09] int    lct = 99, tix = 0;
[10] [11] main(int argc, char **argv)
[12] {
[13]     uname(&uname_struct);
[14]     strcpy(host, uname_struct.nodename);
[15]     if (argc > 1)
[16]         strcpy(host, argv[1]);
[17]     if (!(rsh = RsiInitx(1)))
[18]     {
[19]         fprintf(stderr, "Unable to initialize RSI interface\n");
[20]         exit(98);
[21]     }
[22]     if (RSiOpenx(rsh, 100, 2048, host, feeding, resync, NULL))
[23]     {
[24]         if (strlen(RSiEMsg))
[25]             fprintf(stderr, "%s", RSiEMsg);
[26]         fprintf(stderr, "Error contacting host\n", host);
[27]         exit(-99);
[28]     }
[29]     signal(SIGINT, must_exit);
[30]     signal(SIGTERM, must_exit);
[31]     signal(SIGSEGV, must_exit);
[32]     signal(SIGQUIT, must_exit);
[33]
[34]     strcpy(aph, "hosts/");
[35]     strcat(aph, host);
[36]     strcat(aph, "/");
[37]     lststats(aph);
[38]     RSiClosex(rsh);
[39]     exit(0);
[40] } The following lines (29-32) make sure that the program detects any attempt to kill or terminate it.
If this happens, the function must_exit is invoked. This function has the sole purpose of making sure the
association with the xmtopas daemon is terminated. It does this as shown in the following piece of code:
void must_exit() { RSiClosex(rsh); exit(-9); }

```

Finally, lines 34 through 36 prepare an initial value path name for the main processing loop of the data-consumer program. This is the method followed to create the value path names. Then, the main processing loop in the internal `lststats` function is called. If this function returns, issue an `RSiClosex` call and exit the program.

## Defining a Statset

Eventually, you want the sample of the data-consumer program to receive data feeds from the `xmtopas` daemon. Thus, start preparing the `SpmiStatSet`, which defines the set of statistics with which you are interested. This is done with the `RSiCreateStatSetx` subroutine.

```

[01] void lststats(char *basepath)
[02] {
[03]     struct SpmiStatSet *ssp;
[04]     char    tmp[128];
[05]
[06]     if (!(ssp = RSiCreateStatSetx(rsh)))
[07]     {
[08]         fprintf(stderr, "RsiCons1 can't create StatSet\n");
[09]         exit(62);
[10]     }
[11]
[12]     strcpy(tmp, basepath);
[13]     strcat(tmp, "CPU/cpu0");
[14]     if ((tix = addstat(tix, ssp, tmp, "cpu0")) == -1)
[15]     {
[16]         if (strlen(RSiEMsg))
[17]             fprintf(stderr, "%s", RSiEMsg);
[18]         exit(63);
[19]     }
[20]

```

```

[21]   RSiStartFeedx(rsh, ssp, 1000);
[22]   while(TRUE)
[23]       RSiMainLoopx(499);
[24] }

```

In the sample program, the `SpmiStatSet` is created in the local `lststats` function shown previously in lines 6 through 10.

Lines 12 through 19 invoke the local function `addstat` (Adding Statistics to the Statset), which finds all the CPU-related statistics in the context hierarchy and initializes the arrays to collect and print the information. The first two lines expand the value path name passed to the function by appending `CPU/cpu0`. The resulting string is the path name of the context where all CPU-related statistics for `cpu0` are held. The path name has the `hosts/hostname/CPU/cpu0` format without a terminating slash, which is what is expected by the subroutines that take a value path name as an argument. The `addstat` function is shown in the next section. It uses three of the traversal functions to access the CPU-related statistics.

### Data-Consumer initialization of data feeds

The only part of the main processing function in the main section yet to explain consists of lines 21 through 23. The first line simply tells the `xmtopas` daemon to start feeding observations of statistics for an `SpmiStatSet` by issuing the `RSiStartFeedx` subroutine call. The next two lines define an infinite loop that calls the `RSiMainLoopx` function to check for incoming `data_feed` packets.

There are two more subroutines concerned with controlling the flow of data feeds from `xmtopas` daemon. Neither is used in the sample program. The subroutines are described in `RSiChangeFeedx` and `RSiStopFeedx` structures.

### Adding Statistics to the Statset

```

[01] int addstat(int ix, struct SpmiStatSet *ssp, char *path, char *txt)
[02] {
[03]     cx_handle   *cxh;
[04]     int         i = ix;
[05]     char        tmp[128];
[06]     struct SpmiStatLink *statlink;
[07]
[08]     if (!(cxh = RSiPathGetCxx(rsh, path)))
[09]     {
[10]         fprintf(stderr, "RSiPathGetCxx can't access host %s (path %s)\n", host, path);
[11]         exit(61);
[12]     }
[13]
[14]     if ((statlink = RSiFirstStatx(rsh, cxh, navn, desc)))
[15]     {
[16]         while (statlink)
[17]         {
[18]             if (i > 23)
[19]                 break;
[20]             strcpy(head1[i], txt);
[21]             strcpy(head2[i], *navn);
[22]             strcpy(tmp, path);
[23]             strcat(tmp, "/");
[24]             strcat(tmp, *navn);
[25]             if (!(svp[i] = RSiPathAddSetStatx(rsh, ssp, tmp)))
[26]                 return(-1);
[27]             i++;
[28]             statlink = RSiNextStatx(rsh, cxh, statlink, navn, desc);
[29]         }
[30]     }
[31]     return(i);
[32] }

```

The use of **RSiPathGetCxx** by the sample program is shown in lines 8 through 12. Following that, in lines 14 through 30, two subroutines are used to get all the statistics values defined for the CPU context. This is done by using **RSiFirstStatx** and **RSiNextStatx** subroutines.

In lines 20-21, the short name of the context ("cpu0") and the short name of the statistic are saved in two arrays for use when printing the column headings. Lines 22-24 construct the full path name of the statistics value by concatenating the full context path name and the short name of the value. This is necessary to proceed with adding the value to the **SpmiStatSet** with the **RSiPathAddSetStatx**. The value is added by using the lines 25 and 26.

## Data-Consumer decoding of data feeds

Whenever a `data_feed` is detected by the RSI interface, the data feed callback function defined in the **RSiOpenx** subroutine is invoked, passing the RSI handle as an argument to the callback function. The sample program's callback function for data feeds is shown in the following example. Most of the lines in the function are concerned with printing headings after each 20 detail lines printed. This is in line numbers 9 through 19 and 26.

```
[01] void feeding(RSiHandlex rsh, pack *p)
[02] {
[03]     int i;
[04]     float f;
[05]     long v;
[06]
[07]     if (p->type != data_feed)
[08]         return;
[09]     if (lct > 20)
[10]     {
[11]         printf("\n\n");
[12]         for (i = 0; i < tix; i++)
[13]             printf("%08s", head1[i]);
[14]         printf("\n");
[15]         for (i = 0; i < tix; i++)
[16]             printf("%08s", head2[i]);
[17]         printf("\n");
[18]         lct = 0;
[19]     }
[20]     for (i = 0; i < tix; i++)
[21]     {
[22]         v = RSiGetValuex(rsh, svp[i]) * 10.0;
[23]         printf("%6d.%d", v/10, v%10);
[24]     }
[25]     printf("\n");
[26]     lct++;
[27] }
```

Actual processing of received statistics values is done by the lines 20-24. It involves the use of the library **RSiGetValuex** subroutine. The following is an example of output from the sample program `RsiCons1`:

```
$ RsiCons1 umbra
```

cpu0	cpu0	cpu0	cpu0	cpu0	cpu0	cpu0	cpu0
user	kern	wait	idle	uticks	kticks	wticks	iticks
0.0	0.0	0.0	100.0	0.0	0.0	0.0	100.0
0.0	0.0	0.0	100.0	0.0	0.0	0.0	99.9
0.2	3.1	0.0	96.5	0.2	3.2	0.0	96.6
3.5	5.5	1.5	89.1	3.5	5.5	1.5	89.1
5.8	3.4	0.0	90.8	5.8	3.4	0.0	90.8
8.8	8.3	0.1	82.5	8.8	8.3	0.2	82.5
67.5	2.4	3.0	27.0	67.5	2.3	2.9	26.9
16.0	0.6	0.8	82.5	16.0	0.6	0.8	82.6
67.5	5.0	0.0	27.3	67.5	5.0	0.0	27.3
19.0	6.1	0.9	73.8	19.1	6.1	0.9	73.8
22.5	0.8	1.6	75.0	22.5	0.8	1.6	74.9
60.2	6.1	0.0	33.5	60.2	6.1	0.0	33.5

```
$
```

## An Alternative way to decode data feeds

To know more about the data received in `data_feed` packets than what can be obtained by using the `RSiGetValuex` subroutine, you can use the library `RSiGetRawValuex` subroutine.

## Expanding the data-consumer program

A slightly more capable version of the sample program discussed in the previous sections is provided as the `/usr/samples/perfmgr/RsiCons.c` file. This program also lists the statistics with the short name `xfer` for all the disks found in the system where the daemon runs. To do so, the program uses some additional subroutines to traverse contexts.

### Traversing contexts

The `adddisk` function in the following list shows how the `RSiFirstCxx`, `RSiNextCxx`, and the `RSiInstantiatex` subroutines are combined with `RSiPathGetCxx` to make sure all subcontexts are accessed. The sample program's `addstat` internal function is used to add the statistics of each subcontext to the `SpmiStatSet` structure. A programmer who wanted to traverse all levels of subcontexts below a start context could easily create a recursive function to do this.

```
01] int adddisk(int ix, struct SpmiStatSet *ssp, char *path)
[02] {
[03]     int     i = ix;
[04]     char    tmp[128];
[05]     cx_handle *cxh;
[06]     struct SpmiStatLink *statlink;
[07]     struct SpmiCxLink *cxlink;
[08]
[09]     cxh = RSiPathGetCxx(rsh, path);
[10]     if ((!cxh) || (!cxh->cxt))
[11]     {
[12]         if (strlen(RSiEMsg))
[13]             fprintf(stderr, "%s", RSiEMsg);
[14]         fprintf(stderr, "RSiPathGetCxx can't access host %s (path %s)\n",
[15]             host, path);
[16]         exit(64);
[17]     }
[18]     if (rsh->pi->data.getcx.context.inst_freq == SiContInst)
[19]     {
[20]         if ((i = RSiInstantiatex(rsh, cxh)))
[21]             return(-1);
[22]     }
[23]     if ((cxlink = RSiFirstCxx(rsh, cxh, navn, desc)))
[24]     {
[25]         while (cxlink)
[26]         {
[27]             strcpy(tmp, path);
[28]             if (strlen(tmp))
[29]                 strcat(tmp, "/");
[30]             if (*navn)
[31]                 strcat(tmp, *navn);
[32]             if ((i = addstat(i, ssp, tmp, *navn)) == -1)
[33]             {
[34]                 if (strlen(RSiEMsg))
[35]                     fprintf(stderr, "%s", RSiEMsg);
[36]                 exit(63);
[37]             }
[38]             cxlink = RSiNextCxx(rsh, cxh, cxlink, navn, desc);
[39]         }
[40]     }
[41]     return(i);
[42] }
```

The output from the `RsiCons` program when run on the `xmtopas` daemon on an AIX operating system host is shown in the following example.

\$ RsiCons encee

CPU	CPU	CPU	CPU	hdisk3	hdisk1	hdisk0	cd0
uticks	kticks	wticks	iticks	xfer	xfer	xfer	xfer
19.6	10.0	4.1	67.1	2.7	4.1	0.0	0.0
10.9	15.3	8.2	65.3	0.0	8.2	0.0	0.0
0.5	2.0	0.0	97.5	0.0	0.0	0.0	0.0
10.5	4.0	0.0	85.5	0.0	0.0	0.0	0.0
55.4	8.9	0.0	35.4	2.4	0.0	0.0	0.0
19.0	5.5	0.0	75.5	0.0	0.0	0.0	0.0
5.9	6.4	0.0	87.4	0.0	0.0	0.0	0.0
10.5	7.0	0.0	82.5	0.0	0.0	0.0	0.0
7.9	7.4	0.0	84.4	0.0	0.0	0.0	0.0
88.5	8.5	3.0	0.0	9.5	4.5	0.0	0.0
89.4	8.9	1.4	0.0	5.9	0.0	0.0	0.0
92.5	5.5	2.0	0.0	9.0	8.5	0.0	0.0
71.0	6.0	23.0	0.0	44.0	41.0	0.0	0.0
37.9	2.4	58.9	0.4	67.9	61.4	0.0	0.0
17.5	4.5	0.0	78.0	1.5	3.0	0.0	0.0
0.5	1.5	10.0	88.0	7.5	1.5	0.0	0.0

\$

## Inviting data suppliers

The **RSiInvitex** subroutine allows to design programs that can present the end user with a list of potential data-supplier hosts rather than requiring the user to specify which host to monitor.

### Identifying data suppliers

The **RSiInvitex** subroutine uses one or more of the following methods to obtain the Internet Protocol (IP) addresses to which an invitational `are_you_there` message can be sent.

The last two methods depend on the presence of the `$HOME/Rsi.hosts` file. PTX also has alternative locations of the `Rsi.hosts` file. The three ways to invite data-supplier hosts are:

1. Unless instructed not to by the user, the broadcast address corresponding to each of the network interfaces of the local host is found. The invitational message is sent on each network interface using the corresponding broadcast address. Broadcasts are not attempted on the Localhost (loopback) interface or on point-to-point interfaces such as X.25 or Serial Line Interface Protocol (SLIP) connections.
2. If a list of Internet broadcast addresses is supplied in the `$HOME/Rsi.hosts` file, an invitational message is sent on each such broadcast address. Note that if you specify the broadcast address of a local interface, broadcasts are sent twice on those interfaces. You may want to use this as a feature in order to minimize the likelihood of the invitation being lost.
3. If a list of host names is supplied in the `$HOME/Rsi.hostsfile`, the host IP address for each host in the list is looked up and a message is sent to each host. The look-up is done through a `gethostbyname()` call, so that whichever name service is active for the host where the data-consumer application runs is used to find the host address.

The `$HOME/Rsi.hosts` file has a simple layout. Only one keyword is recognized and only if placed in column one of a line. That keyword is:

`nobroadcast` and means that the `are_you_there` message should not be broadcast using method 1 shown previously. This option is useful in situations where a large number of hosts are on the network and only a well-defined subset should be remotely monitored. To say that you don't want broadcasts but want direct contact to three hosts, your `$HOME/Rsi.hosts` file might look like this:

```
nobroadcast
birte.austin.ibm.com
gatea.almaden.ibm.com
umbra
```

This example shows that the hosts to monitor do not necessarily have to be in the same domain or on a local network. However, doing remote monitoring across a low-speed communications line is unlikely to be popular; neither with other users of that communications line nor with yourself.

Be aware that whenever you want to monitor remote hosts that are not on the same subnet as the data-consumer host, you must specify the broadcast address of the other subnets or all the host names of those hosts in the \$HOME/Rsi.hosts file. The reason is that IP broadcasts do not propagate through IP routers or gateways.

The following example illustrates a situation where you want to do broadcasting on all local interfaces, want to broadcast on the subnet identified by the broadcast address 129.49.143.255, and also want to invite the host called umbra. (The subnet mask corresponding to the broadcast address in this example is 255.255.240.0 and the range of addresses covered by the broadcast is 129.49.128.0 - 129.49.143.255.)

```
129.49.143.255
```

If the **RSiInvitex** subroutine detects that the name server is inoperational or has abnormally long response time, it returns the IP addresses of hosts rather than the host names. If the name server fails after the list of hosts is partly built, the same host may appear twice, once with its IP address and once with its host name.

The execution time of the **RSiInvitex** subroutine depends primarily on the number of broadcast addresses you place in the \$HOME/Rsi.hosts file. Each broadcast address increases the execution time with roughly 50 milliseconds plus the time required to process the responses. The minimum execution time of the subroutine is roughly 1.5 seconds, during which time your application only gets control if callback functions are specified and if packets arrive that must be given to those callback functions.

## A Full-Screen, character-based monitor

This program uses the API and the curses programming interface to create a screen full of statistics.

Another sample program written to the data-consumer API is the `chmon` program. Source code to the program is in `/usr/samples/perfmgr/chmon.c`. The `chmon` program is also stored as an executable during the installation of the Manager component. An example program follows:

```
Data-Consumer API      Remote Monitor for host      Tue Apr 14 09:09:05
1992
CHMON Sample Program      ***  birte  ***      Interval:      5 seconds

% CPU                      EVENTS/QUEUES  FILE/TTY
Kernel  13.3  |#####| Pswitch 1295 Readch 24589
User    23.7  |#####| Syscall 6173 Writech 1646
Wait    6.5   |##| Reads 487 Rawin 0
Idle    56.1  |#####| Writes 143 Ttyout 106
                                                Forks 1 Igets 1763
PAGING counts  PAGING SPACE  REAL MEM 48MB  Execs 1 Namei 809
Faults  131  % Used 33.7  % Comp 68.0  Runqueue 1 Dirblk 174
Steals  0    % Free 66.2  % NonComp 15.0  Swapqueue 0 Reads 48
Reclaim 0    Size,MB 96  % Client 4.0  Writes 143

PAGING page/s  DISK      Read Write  %  NETWORK  Read Write
Pgspin 0  ACTIVITY KB/sec KB/sec Busy  ACTIVITY KB/sec KB/sec
Pgspout 0  hdisk0 0.0 35.1 15.7  lo0 1.1 1.1
Pagein 0  hdisk1 0.0 0.0 0.0  tr0 1.1 0.0
Pageout 11  hdisk2 0.0 9.5 3.5
Sios 10  cd1 0.0 0.0 0.0

Process wait (514) %cpu 63.2, PgSp: 0.0mb, uid:
Process xlcentry (12657) %cpu 58.0, PgSp: 1.1mb, uid: birte
Process make (21868) %cpu 15.0, PgSp: 0.2mb, uid: birte
Process make (5998) %cpu 15.0, PgSp: 0.1mb, uid: birte
```

The chmon command line is:

```
chmon[-iseconds_interval] [-pno_of_processes] [hostname>]
```

Item	Descriptor
seconds_interval	Is the interval between observations. Must be specified in seconds. No blanks must be entered between the flag and the interval. Defaults to 5 seconds.
no_of_processes	Is the number of "hot" processes to be shown. A process is considered "hotter" the more CPU it uses. No blanks must be entered between the flag and the count field. Defaults to 0 (no) processes.
hostname	Is the host name of the host to be monitored. Default is the local host. The sample program exits after 2,000 observations have been taken, or when you type the letter "q" in its window.

## List of RSI Error Codes

All RSI subroutines use constants to define error codes.

The RSI Error Code table lists the error descriptions.

Symbolic Name	Number	Description
RSITimeout	280	A time-out occurred while waiting for a response to a request.
RSIBusy	281	An RSiOpenx subroutine was issued, but another is already active.
RSISendErr	282	An error occurred when the library attempted to send a UDP packet with the sendto() system call.
RSIPollErr	283	A system error occurred while issuing or processing a poll() or select() system call.
RSIRecvErr	284	A system error occurred while attempting to read an incoming UDP packet with the recvfrom() system call.
RSISizeErr	285	A recvfrom() system call returned a UDP packet with incorrect length or incorrect source address.
RSIResync	286	While waiting for a response to an outgoing request, one of the following occurred and cause an error return to the calling program: <ol style="list-style-type: none"> <li>1. An error occurred while processing an exception packet.</li> <li>2. An error occurred while processing an i_am_back packet.</li> <li>3. An i_am_back packet was received in response to an output request other than are_you_there.</li> <li>4. While waiting for a response to an outgoing request, some asynchronous function closed the handle for the remote host.</li> </ol> <p>The code may also be set when a success return code is returned to the caller, in which case it shows that either an exception packet or an i_am_back packet was processed successfully while waiting for a response.</p>
RSIBadStat	287	A bad status code was received in the data packet received.
RSIBadArg	288	An argument that is not valid was passed to an RSi subroutine.

Symbolic Name	Number	Description
RSiBadHost	289	A valid host address cannot be constructed from an IP address or the nameservice doesn't know the hostname.
RSiDupHost	290	An <b>RSiOpenx</b> call was issued against a host but a connection is already open to a host with this IP address and a different hostname.
RSiSockErr	291	An error occurred while opening or communicating with a socket.
RSiNoPort	292	The RSi is unable to find the port number to use when inviting remote suppliers. The likely cause is that the xmquery entry is missing from the /etc/services file or the NIS (Yellow Pages) server.
RSiNoMatch	293	One of the following occurred: <ol style="list-style-type: none"> <li>1. The SpmiStatVals argument on the <b>RSiStatGetPathx</b> call is not valid.</li> <li>2. On an <b>RSiPathAddSetStatx</b> call, the SpmiStatSet argument is not valid or the path name given in the last argument does not exist.</li> <li>3. On an <b>RSiAddSetHotx</b> call, the SpmiHotSet argument is not valid, the grand parent context doesn't exist or none of its subcontexts contain the specified statistic.</li> <li>4. On an <b>RSiDelSetStatx</b> call, the SpmiStatSet or the SpmiStatVals argument is not valid.</li> <li>5. On an <b>RSiDelSetHotx</b> call, the SpmiHotSet or the SpmiHotVals argument is not valid.</li> <li>6. On an <b>RSiPathGetCxx</b> call, the path name given does not exist. On an <b>RSiGetValuex</b> or <b>RSiGetRawValuex</b> call, the SpmiStatVals argument is not valid.</li> <li>7. On an <b>RSiGetHotItemx</b> call, the SpmiHotSet argument was not valid.</li> </ol>
RSiInstErr	294	An error was returned when attempting to instantiate a remote context.
RSiNoFeed	295	When extracting a data value with the <b>RSiGetValuex</b> call, the data value was marked as not valid by the remote data supplier.
RSiTooMany	296	An attempt was made to add more values to a statset than the current buffer size permits.
RSiNoMem	297	Memory allocation error.
RSiNotInit	298	An RSi call was attempted before an <b>RSiInitx</b> call was issued.
RSiNoLicense	299	License expired or no license found.
RSiNotSupported	300	The subroutine call requires a later protocol version that is the one supported by the remote system's <b>xmtopas</b> daemon.

---

## Notices

This information was developed for products and services offered in the US.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing  
IBM Corporation  
North Castle Drive, MD-NC119  
Armonk, NY 10504-1785  
US*

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing  
Legal and Intellectual Property Law  
IBM Japan Ltd.  
19-21, Nihonbashi-Hakozakicho, Chuo-ku  
Tokyo 103-8510, Japan*

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licenseses of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Director of Licensing  
IBM Corporation  
North Castle Drive, MD-NC119  
Armonk, NY 10504-1785  
US*

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

The performance data and client examples cited are presented for illustrative purposes only. Actual performance results may vary depending on specific configurations and operating conditions.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

#### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work must include a copyright notice as follows:

© (your company name) (year).

Portions of this code are derived from IBM Corp. Sample Programs.

© Copyright IBM Corp. \_enter the year or years\_.

---

## Privacy policy considerations

IBM Software products, including software as a service solutions, (“Software Offerings”) may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering’s use of cookies is set forth below.

This Software Offering does not use cookies or other technologies to collect personally identifiable information.

If the configurations deployed for this Software Offering provide you as the customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM’s Privacy Policy at <http://www.ibm.com/privacy> and IBM’s Online Privacy Statement at <http://www.ibm.com/privacy/details> the section entitled “Cookies, Web Beacons and Other Technologies” and the “IBM Software Products and Software-as-a-Service Privacy Statement” at <http://www.ibm.com/software/info/product-privacy>.

---

## Trademarks

IBM, the IBM logo, and [ibm.com](http://www.ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the web at [www.ibm.com/legal/copytrade.shtml](http://www.ibm.com/legal/copytrade.shtml).

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

UNIX is a registered trademark of The Open Group in the United States and other countries.



---

# Index

## A

- a.out file 259
- API calls
  - basic
    - pm\_delete\_program 60
    - pm\_get\_data 60
    - pm\_get\_program 60
    - pm\_get\_tdata 60
    - pm\_get\_Tdata 60
    - pm\_reset\_data 60
    - pm\_set\_program 60
    - pm\_start 60
    - pm\_stop 60
    - pm\_tstart 60
    - pm\_tstop 60
- applications
  - compiling for Xprofiler 257

## B

- binary executable
  - specifying from Xprofiler GUI 265
- bos.perf.libperfstat 5.2.0 file set 214

## C

- Call Graph Profile report 294
- calls between functions, how depicted 276
- clustering functions 284
- clusters, library 276
- code
  - disassembler
    - viewing 305
  - source
    - viewing 303
- command-line flags
  - specifying from Xprofiler GUI 267
  - Xprofiler 260
- commands
  - gprof 247
  - prof 245
  - tprof 249
- configuraiton files
  - saving 302
- configuration files
  - loading 302
- controlling how the display is updated 276
- counter multiplexing mode 61
  - pm\_get\_data\_mx 62
  - pm\_get\_program\_mx 62
  - pm\_get\_tdata\_mx 62
  - pm\_set\_program\_mx 62
- CPU Utilization Reporting Tool
  - see curt 2
- curt 2
  - Application Pthread Summary (by PID) Report 14
  - Application Summary (by process type) Report 13
  - Application Summary by Process ID (PID) Report 12
  - Application Summary by Thread ID (Tid) Report 11
  - default reports 6

- curt (*continued*)
  - Event Explanation 3
  - Event Name 3
  - examples 4
  - FILH Summary Report 19
  - flags 2
  - FLIH types 20
  - General Information 6
  - Global SLIH Summary Report 21
  - Hook ID 3
  - Kproc Summary (by Tid) Report 13
  - measurement and sampling 3
  - parameters 2
  - Pending Pthread Calls Summary Report 19
  - Pending System Calls Summary Report 15
  - Processor Summary Report 9
  - Pthread Calls Summary Report 19
  - report overview 5
  - sample report
    - e flag 22
    - p flag 26
    - P flag 29
    - s flag 23
    - t flag 24
  - syntax 2
  - System Calls Summary Report 15
  - System Summary Report 7
- customizable resources
  - Xprofiler 309

## D

- data
  - basic 288
  - detailed 292
  - getting from reports 292
  - performance 288
- disassembler code
  - viewing 305
- disk space requirements 258
- display
  - Xprofiler 271

## E

- event list
  - POWERCOMPAT 53
- examples
  - performance monitor APIs 63

## F

- features
  - X Windows
    - customizing 309
- file
  - binary executable
    - specifying from Xprofiler GUI 265
  - profile data
    - specifying from Xprofiler GUI 266

- files
  - loading from Xprofiler GUI 262
- filtering, function call tree 278
- finding objects in call tree 286
- flags
  - specifying from Xprofiler GUI 267
  - Xprofiler 260
- Flat Profile report 293
- function call tree
  - clustering 283
  - controlling graphic style 276
  - controlling orientation of 277
  - controlling representation of 277
  - displaying 279
  - excluding specific objects 279
  - filtering 278
  - including specific objects 279
  - restoring 278
- Function Index report 297
- functions, how depicted 274

## G

- gennames utility 35
- Global Actions on Tunable Parameters 233
- global interfaces
  - perfstat\_cpu\_util interface 105
  - perfstat\_partition\_config interface 96
  - perfstat\_process 152
  - perfstat\_process\_util 155
  - perfstat\_processor\_pool\_util 157
- gmon.out file 259
- gprof
  - and Xprofiler 257

## I

- info stanza 218
- installp 258

## K

- kernel tuning 217
  - attributes
    - pre520tune 217
  - commands 217
    - flags 219
    - tunchange 221
    - tuncheck 222
    - tundefault 224
    - tunrestore 222
    - tunsave 223
  - commands syntax 219
  - file manipulation commands 221
  - initial setup 224
  - introduction 217, 230
  - migration and compatibility 217
  - reboot tuning procedures 225
  - recovery procedure 225
  - SMIT interface 225
  - tunable parameters 217
  - tunables file directory 218
  - tunables parameters
    - type 219
  - Web-base System Manager 230

## L

- lastboot 218
- lastboot.log 218
- library clusters 276
- Library Statistics report 299
- limitations
  - Xprofiler 256
- locating objects in call tree 286

## N

- nextboot 218
- Node Interfaces 203

## O

- objects, locating in call tree 286

## P

- parameter details 240
- performance data, getting 288
- performance monitor API
  - accuracy 51
  - common rules 58
  - context and state 51
    - state inheritance 52
    - system level context 51
    - thread context 51
    - thread counting-group and process context 51
  - programming 50
  - security considerations 57
  - thread accumulation 57
  - thread group accumulation 57
- performance monitor plug-in 230
- perfstat 80
  - characteristics 80
  - component-specific interfaces 100
  - global interfaces 81
  - perfstat\_bridgedadapters interface 173
  - perfstat\_cpu interface 101
  - perfstat\_cpu\_total Interface 82
  - perfstat\_disk interface 124
  - perfstat\_disk\_total Interface 88
  - perfstat\_diskadapter interface 128
  - perfstat\_diskpath interface 126
  - perfstat\_fcstat interface 131
  - perfstat\_memory\_total Interface 86
  - perfstat\_netadapter interface 144
  - perfstat\_netbuffer interface 142
  - perfstat\_netinterface interface 140
  - perfstat\_netinterface\_total Interface 88
  - perfstat\_pagingspace interface 147
  - perfstat\_partition\_total Interface 89
  - perfstat\_protocol interface 149
  - perfstat\_ssp interface 177
  - perfstat\_ssp\_ext interface 181
  - perfstat\_virtual\_fcadapter interface 167
  - perfstat\_virtualdiskadapter interface 164
  - perfstat\_virtualdisktarget interface 170
- perfstat API programming
  - see perfstat 80
- perfstat\_cpu\_util interfaces
  - simplelparstat.c 111
  - simplempstat.c 116

- Plug-In for Web-base System Manager System Tuning 230
- pm\_delete\_program 58
- pm\_error 58
- pm\_groups\_info\_t 58
- pm\_info\_t 58
- pm\_init API initialization 58
- pm\_initialize 58
- pm\_initialize API initialization 59
- pm\_set\_program 58
- pmapi library 58
- POWERCOMPAT 53
- procmon tool 241
- profile data files
  - specifying from Xprofiler GUI 266
- profiled data
  - saving screen images of 307
- profiling 245
- programs
  - compiling for Xprofiler 257

## R

- reboot procedure 225
- recovery procedure 225
- release specific features 212
- Remote Statistics Interface (RSI)
  - A Full-Screen, character-based monitor 360
  - Adding statistics to the Statset 356
  - An Alternative way to decode data feeds 358
  - Concepts and Terms 350
  - Data structures 350
  - Data-Consumer decoding of data feeds 357
  - Defining a Statset 355
  - Expanding the data-consumer program 358
  - Identifying data suppliers 359
  - Initializing and terminating the program 354
  - Inviting data suppliers 359
  - List of RSi Error Codes 361
  - List of subroutines 349
  - Makefile 348
  - Remote Statistics Interface (RSI) overview 348
  - Request-Response Interface 352
  - Resynchronizing 353
  - RSI network driven interface 352
  - Sample code 354
  - Specifying port range for RSI communication 354
  - Traversing contexts 358
- reports
  - Call Graph Profile 294
  - Flat Profile 293
  - Function Index 297
  - getting data from 292
  - Library Statistics 299
  - saving to a file 301
- requirements
  - Xprofiler 256
- resource settings
  - Xprofiler 309
- resources
  - Xprofiler
    - customizing 309
- resources, customizable
  - Xprofiler 309

## S

- screen images
  - saving 307
- search file sequence
  - setting 270
- settings, resource
  - Xprofiler 309
- simple performance lock analysis tool (splat)
  - see splat 32
- SMIT Interface 225
- software requirements 258
- source code
  - viewing 303
- splat 32
  - address-to-name resolution 35
  - AIX kernel lock details 38
  - command syntax 32
  - condition-variable report 49
  - event explanation 33
  - event name 33
  - execution, trace, and analysis intervals 34
  - flags 32
  - hook ID 33
  - measurement and sampling 33
  - mutex function detail 47
  - mutex pthread detail 46
  - mutex reports 45
  - parameters 32
  - PThread synchronizer reports 45
  - read/write lock reports 47
  - reports 35
    - execution summary 35
    - gross lock summary 36
    - per-lock summary 37
  - simple and runQ lock details 39, 41
  - trace discontinuities 34

## T

- thread counting-group information 61
  - consistency flag 61
  - member count 61
  - process flag 61
- timing commands 245
- tunable parameters
  - global actions 233
- tunables 218
- tuncheck 218
- tundefault 218
- tuning tables
  - actions 237
  - using 236
- tunrestore 218
- tunsave 218

## U

- unclustering functions 285

## W

- WPAR interfaces 185

## X

- X Windows
  - features
    - customizing 309
- X-Windows Performance Profiler (Xprofiler) 256
  - see X-Windows Performance Profiler (Xprofiler) 256
- Xprofiler
  - and gprof 257
  - binary executable file
    - specifying 265
  - command-line flags 260
    - specifying from GUI 267
  - compiling applications for 257
  - controlling fonts 310
  - customizable resources 309
  - display 271
  - file menu
    - controlling variables 311
  - files and directories created 259
  - filter menu
    - controlling variables 314
  - hidden menus 273
  - how installation alters system 259
  - installing 258
    - using SMIT 258
  - limitations 256, 258
  - loading files from GUI 262
  - main menus 273
  - main window 272, 310
  - overview 256
  - profile data files
    - specifying 266
  - requirements 256
  - resource settings 309
  - resources
    - customizing 309
  - screen dump
    - controlling variables 312
  - setting search file sequence 270
  - starting 259
  - view menu
    - controlling variables 313
- Xprofiler installation information 258
- Xprofiler preinstallation information 258





Printed in USA